

# TURBO PASCAL<sup>®</sup>

REFERENCE  
GUIDE

B O R L A N D



# **Turbo Pascal®**

---

## **Reference Guide**

**Version 5.0**

**Copyright© 1983, 1989  
All rights reserved**

**Borland International  
1800 Green Hills Road  
P.O. Box 660001  
Scotts Valley, CA 95066-0001**

**This manual was produced with  
Sprint® The Professional Word Processor**

**All Borland products are trademarks or registered trademarks of  
Borland International, Inc. Other brand and product names are trademarks  
or registered trademarks of their respective holders.  
Copyright® 1989 Borland International.**

**Printed in the U.S.A.**

**109876543**

# Table of Contents

<b>Introduction</b>	1
What's On Your Disks .....	1
Installing Turbo Pascal On Your System .....	4
About This Manual .....	4
Typography .....	5
How to Contact Borland .....	5

## **Part 1 Programmer's Reference**

<b>Chapter 1 Tokens and Constants</b>	9
Special Symbols and Reserved Words .....	9
Identifiers .....	11
Labels .....	12
Numbers .....	13
Character Strings .....	14
Constant Declarations .....	15
Comments .....	16
Program Lines .....	16

<b>Chapter 2 Blocks, Locality, and Scope</b>	17
Syntax .....	17
Rules of Scope .....	19
Scope of Interface and Standard Identifiers .....	19

<b>Chapter 3 Types</b>	21
Simple Types .....	22
Ordinal Types .....	22
Integer Types .....	23
Boolean Type .....	24
Char Type .....	24
Enumerated Types .....	24
Subrange Types .....	25
Real Types .....	26
Software Floating Point .....	26
8087 Floating Point .....	27
String Types .....	27
Structured Types .....	28
Array Types .....	28
Record Types .....	29
Set Types .....	31
File Types .....	31



Pointer Types .....	32
Procedural Types .....	33
Identical and Compatible Types .....	33
Type Identity .....	33
Type Compatibility .....	34
Assignment Compatibility .....	34
The Type Declaration Part .....	35
<b>Chapter 4 Variables</b> .....	<b>37</b>
Variable Declarations .....	37
The Data Segment .....	38
The Stack Segment .....	38
Absolute Variables .....	39
Variable References .....	39
Qualifiers .....	40
Arrays, Strings, and Indexes .....	41
Records and Field Designators .....	41
Pointers and Dynamic Variables .....	42
Variable Typecasts .....	42
<b>Chapter 5 Typed Constants</b> .....	<b>45</b>
Simple-Type Constants .....	46
String-Type Constants .....	46
Structured-Type Constants .....	46
Array-Type Constants .....	47
Record-Type Constants .....	48
Set-Type Constants .....	48
Pointer-Type Constants .....	49
<b>Chapter 6 Expressions</b> .....	<b>51</b>
Expression Syntax .....	52
Operators .....	54
Arithmetic Operators .....	54
Logical Operators .....	56
Boolean Operators .....	56
String Operator .....	57
Set Operators .....	58
Relational Operators .....	58
Comparing Simple Types .....	59
Comparing Strings .....	59
Comparing Packed Strings .....	60
Comparing Pointers .....	60
Comparing Sets .....	60
Testing Set Membership .....	60
The @ Operator .....	61
@ with a Variable .....	61

@ with a Value Parameter .....	61
@ with a Variable Parameter .....	62
@ with a Procedure or Function .....	62
Function Calls .....	62
Set Constructors .....	63
Value Typecasts .....	64
<b>Chapter 7 Statements</b> .....	<b>65</b>
Simple Statements .....	65
Assignment Statements .....	66
Procedure Statements .....	66
Goto Statements .....	67
Structured Statements .....	67
Compound Statements .....	67
Conditional Statements .....	68
If Statements .....	68
Case Statements .....	69
Repetitive Statements .....	70
Repeat Statements .....	70
While Statements .....	71
For Statements .....	72
With Statements .....	74
<b>Chapter 8 Procedures and Functions</b> .....	<b>77</b>
Procedure Declarations .....	77
Forward Declarations .....	78
External Declarations .....	79
Inline Declarations .....	80
Function Declarations .....	80
Parameters .....	82
Value Parameters .....	82
Variable Parameters .....	83
Untyped Variable Parameters .....	83
Procedural Types .....	84
Procedural Type Declarations .....	84
Procedural Variables .....	85
Procedural Type Parameters .....	87
Procedural Types in Expressions .....	89
<b>Chapter 9 Programs and Units</b> .....	<b>93</b>
Program Syntax .....	93
The Program Heading .....	93
The Uses Clause .....	93
Unit Syntax .....	94
The Unit Heading .....	95
The Interface Part .....	95

The Implementation Part .....	95
The Initialization Part .....	96
Indirect Unit References .....	96
Circular Unit References .....	97
Sharing Other Declarations .....	99
<b>Chapter 10 Input and Output</b> .....	<b>101</b>
An Introduction to I/O .....	101
Standard Procedures and Functions for All Files .....	102
Procedures .....	102
Functions .....	103
Standard Procedures and Functions for Text Files .....	103
Procedures .....	104
Functions .....	104
Standard Procedures and Functions for Untyped Files .....	105
The FileMode Variable .....	105
Devices in Turbo Pascal .....	106
DOS Devices .....	106
The CON Device .....	107
The LPT1, LPT2, and LPT3 Devices .....	107
The COM1 and COM2 Devices .....	107
The NUL Device .....	107
Text File Devices .....	108
<b>Chapter 11 Standard Procedures and Functions</b> .....	<b>109</b>
Flow Control Procedures .....	109
Dynamic Allocation Procedures and Functions .....	109
Procedures .....	110
Functions .....	110
Transfer Functions .....	110
Arithmetic Functions .....	110
Ordinal Procedures and Functions .....	111
Procedures .....	111
Functions .....	111
String Procedures and Functions .....	112
Procedures .....	112
Functions .....	112
Pointer and Address Functions .....	112
Miscellaneous Procedures and Functions .....	112
Procedures .....	112
Functions .....	113
<b>Chapter 12 Standard Units</b> .....	<b>115</b>
Standard Unit Dependencies .....	116
The System Unit .....	116
The Printer Unit .....	119

The Dos Unit .....	119
Constants, Types, and Variables .....	120
Flags Constants .....	120
File Mode Constants .....	120
File Record Types .....	120
File Attribute Constants .....	121
The Registers Type .....	122
The DateTime Type .....	122
The SearchRec Type .....	122
The File-Handling String Types .....	123
The DosError Variable .....	123
Interrupt Support Procedures .....	123
Date and Time Procedures .....	124
Disk Status Functions .....	124
File-Handling Procedures and Functions .....	124
Procedures .....	124
Functions .....	125
Process-Handling Procedures and Functions .....	125
Procedures .....	125
Functions .....	125
Environment-Handling Functions .....	125
Miscellaneous Procedures and Function .....	125
Procedures .....	125
Function .....	126
The Crt Unit .....	126
The Input and Output Files .....	126
Windows .....	126
Special Characters .....	127
Line Input .....	127
Constants, Types, and Variables .....	128
Crt Mode Constants .....	128
Text Color Constants .....	128
Crt Variables .....	129
CheckBreak .....	129
CheckEOF .....	130
CheckSnow .....	130
DirectVideo .....	130
LastMode .....	131
TextAttr .....	131
WindMin and WindMax .....	131
Procedures .....	132
Functions .....	132
The Graph Unit .....	133
Drivers .....	133
IBM 8514 Support .....	134

Coordinate System .....	135
Current Pointer .....	135
Text .....	136
Figures and Styles .....	136
Viewports and Bit Images .....	137
Paging and Colors .....	137
Error-Handling .....	137
Getting Started .....	138
User-Written Heap Management Routines .....	140
Graph Unit Constants, Types and Variables .....	142
Constants .....	142
Types .....	146
Variables .....	148
Procedures .....	148
Functions .....	151
The Turbo3 Unit .....	152
Interface Section .....	152
Kbd .....	153
CBreak .....	154
Procedures .....	154
Functions .....	154
The Graph3 Unit .....	155
Procedures .....	155
<b>Chapter 13 Overlays</b> .....	<b>159</b>
The Overlay Unit .....	160
Constants and Variables .....	161
The OvrResult Variable .....	161
Result Codes .....	161
Procedures and Functions .....	162
OvrInit .....	162
OvrInitEMS .....	162
OvrSetBuf .....	163
OvrGetBuf .....	163
OvrClearBuf .....	163
Designing Overlaid Programs .....	164
Overlay Code Generation .....	164
The FAR Call Requirement .....	164
Initializing the Overlay Manager .....	165
Initialization Sections in Overlaid Units .....	167
What Not to Overlay .....	168
Debugging Overlays .....	169
External Routines in Overlays .....	169
<b>Chapter 14 Using the 8087</b> .....	<b>171</b>
The 8087 Data Types .....	172

Extended Range Arithmetic .....	173
Comparing Reals .....	174
The 8087 Evaluation Stack .....	175
Writing Reals with the 8087 .....	176
Units Using the 8087 .....	176
Detecting the 8087 .....	176
Using 8087 Emulation in Assembly Language .....	178
<b>Chapter 15 Inside Turbo Pascal</b> .....	<b>179</b>
The Heap Manager .....	181
Disposal Methods .....	182
The Free List .....	185
The Heap Error Function .....	187
Internal Data Formats .....	188
Integer Types .....	188
Char Types .....	189
Boolean Types .....	189
Enumerated Types .....	189
Floating-Point Types .....	189
The Real Type .....	189
The Single Type .....	190
The Double Type .....	190
The Extended Type .....	191
The Comp Type .....	191
Pointer Types .....	192
String Types .....	192
Set Types .....	192
Array Types .....	193
Record Types .....	193
File Types .....	193
Procedural Types .....	194
Calling Conventions .....	195
Variable Parameters .....	195
Value Parameters .....	195
Function Results .....	196
NEAR and FAR Calls .....	197
Nested Procedures and Functions .....	197
Entry and Exit Code .....	198
Register-Saving Conventions .....	199
Linking with Assembly Language .....	199
Turbo Assembler and Turbo Pascal .....	200
Examples of Assembly Language Routines .....	201
Turbo Assembler Example .....	204
Inline Machine Code .....	205
Inline Statements .....	205
Inline Directives .....	207

Direct Memory and Port Access .....	208
The Mem, MemW, and MemL Arrays .....	208
The Port and PortW Arrays .....	208
Interrupt Handling .....	209
Writing Interrupt Procedures .....	209
Text File Device Drivers .....	210
The Open Function .....	211
The InOut Function .....	212
The Flush Function .....	212
The Close Function .....	212
Examples of Text File Device Drivers .....	212
Exit Procedures .....	216
Automatic Optimizations .....	217
Constant Folding .....	218
Constant Merging .....	218
Short-Circuit Evaluation .....	218
Order of Evaluation .....	219
Range-Checking .....	219
Shift Instead of Multiply .....	219
Automatic Word Alignment .....	219
Dead Code Removal .....	220
Smart Linking .....	220
<b>Chapter 16 Turbo Pascal Reference Lookup</b> .....	<b>223</b>
Sample procedure .....	223
Abs function .....	224
Addr function .....	224
Append procedure .....	225
Arc procedure .....	226
ArcTan function .....	226
Assign procedure .....	227
AssignCrt procedure .....	228
Bar procedure .....	229
Bar3D procedure .....	229
BlockRead procedure .....	230
BlockWrite procedure .....	232
ChDir procedure .....	233
Chr function .....	233
Circle procedure .....	234
ClearDevice procedure .....	234
ClearViewPort procedure .....	235
Close procedure .....	236
CloseGraph procedure .....	236
ClrEol procedure .....	237
ClrScr procedure .....	237
Concat function .....	238

Copy function .....	239
Cos function .....	239
CSeg function .....	240
Dec procedure .....	240
Delay procedure .....	240
Delete procedure .....	241
DeLine procedure .....	241
DetectGraph procedure .....	242
DiskFree function .....	243
DiskSize function .....	243
Dispose procedure .....	244
DosExitCode function .....	245
DosVersion function .....	245
DrawPoly procedure .....	246
DSeg function .....	247
Ellipse procedure .....	247
EnvCount function .....	248
EnvStr function .....	248
Eof function (text files) .....	249
Eof function (typed, untyped files) .....	249
Eoln function .....	250
Erase procedure .....	250
Exec procedure .....	251
Exit procedure .....	253
Exp function .....	253
FExpand function .....	254
FilePos function .....	254
FileSize function .....	255
FillChar procedure .....	255
FillEllipse procedure .....	256
FillPoly procedure .....	257
FindFirst procedure .....	258
FindNext procedure .....	259
FloodFill procedure .....	259
Flush procedure .....	261
Frac function .....	261
FreeMem procedure .....	261
FSearch function .....	262
FSplit procedure .....	263
GetArcCoords procedure .....	264
GetAspectRatio procedure .....	265
GetBkColor function .....	266
GetCBreak procedure .....	267
GetColor function .....	267
GetDate procedure .....	268



GetDefaultPalette function .....	268
GetDir procedure .....	269
GetDriverName function .....	270
GetEnv function .....	270
GetFAttr procedure .....	271
GetFillPattern procedure .....	272
GetFillSettings procedure .....	273
GetFTime procedure .....	274
GetGraphMode function .....	274
GetImage procedure .....	276
GetIntVec procedure .....	277
GetLineSettings procedure .....	277
GetMaxColor function .....	278
GetMaxMode function .....	279
GetMaxX function .....	280
GetMaxY function .....	281
GetMem procedure .....	281
GetModeName function .....	282
GetModeRange procedure .....	283
GetPalette procedure .....	283
GetPaletteSize function .....	284
GetPixel function .....	285
GetTextSettings procedure .....	285
GetTime procedure .....	287
GetVerify procedure .....	287
GetViewSettings procedure .....	287
GetX function .....	288
GetY function .....	289
GotoXY procedure .....	290
GraphDefaults procedure .....	291
GraphErrorMsg function .....	291
GraphResult function .....	292
Halt procedure .....	294
Hi function .....	295
HighVideo procedure .....	295
ImageSize function .....	296
Inc procedure .....	297
InitGraph procedure .....	297
Insert procedure .....	300
InsLine procedure .....	300
InstallUserDriver function .....	301
InstallUserFont function .....	304
Int function .....	305
Intr procedure .....	305
IOResult function .....	306

Keep procedure .....	307
KeyPressed function .....	307
Length function .....	308
Line procedure .....	308
LineRel procedure .....	309
LineTo procedure .....	310
Ln function .....	311
Lo function .....	312
LowVideo procedure .....	312
Mark procedure .....	313
MaxAvail function .....	313
MemAvail function .....	314
MkDir procedure .....	314
Move procedure .....	315
MoveRel procedure .....	316
MoveTo procedure .....	317
MsDos procedure .....	318
New procedure .....	318
NormVideo procedure .....	319
NoSound procedure .....	319
Odd function .....	319
Ofs function .....	320
Ord function .....	320
OutText procedure .....	320
OutTextXY procedure .....	322
OvrClearBuf procedure .....	323
OvrGetBuf function .....	324
OvrInit procedure .....	325
OvrInitEMS procedure .....	325
OvrSetBuf procedure .....	327
PackTime procedure .....	328
ParamCount function .....	328
ParamStr function .....	328
Pi function .....	329
PieSlice procedure .....	329
Pos function .....	330
Pred function .....	331
Ptr function .....	331
PutImage procedure .....	331
PutPixel procedure .....	334
Random function .....	334
Randomize procedure .....	335
Read procedure (text files) .....	335
Read procedure (typed files) .....	337
ReadKey function .....	337

ReadLn procedure .....	338
Rectangle procedure .....	339
RegisterBGIDriver function .....	340
RegisterBGIfont function .....	342
Release procedure .....	344
Rename procedure .....	345
Reset procedure .....	345
RestoreCrtMode procedure .....	346
Rewrite procedure .....	347
RmDir procedure .....	348
Round function .....	349
RunError procedure .....	349
Sector procedure .....	350
Seek procedure .....	351
SeekEof function .....	351
SeekEoln function .....	352
Seg function .....	352
SetActivePage procedure .....	353
SetAllPalette procedure .....	354
SetAspectRatio procedure .....	355
SetBkColor procedure .....	356
SetCBreak procedure .....	357
SetColor procedure .....	358
SetDate procedure .....	358
SetFAttr procedure .....	359
SetFillPattern procedure .....	359
SetFillStyle procedure .....	361
SetFTime procedure .....	362
SetGraphBufSize procedure .....	362
SetGraphMode procedure .....	363
SetIntVec procedure .....	365
SetLineStyle procedure .....	366
SetPalette procedure .....	367
SetRGBPalette procedure .....	369
SetTextBuf procedure .....	370
SetTextJustify procedure .....	372
SetTextStyle procedure .....	373
SetTime procedure .....	374
SetUserCharSize procedure .....	375
SetVerify procedure .....	376
SetViewPort procedure .....	376
SetVisualPage procedure .....	378
SetWriteMode procedure .....	379
Sin function .....	380
SizeOf function .....	381

Sound procedure .....	381
SPtr function .....	382
Sqr function .....	382
Sqrt function .....	382
SSeg function .....	382
Str procedure .....	383
Succ function .....	383
Swap function .....	384
SwapVectors procedure .....	384
TextBackground procedure .....	385
TextColor procedure .....	385
TextHeight function .....	386
TextMode procedure .....	387
TextWidth function .....	389
Trunc function .....	390
Truncate procedure .....	391
UnpackTime procedure .....	391
UpCase function .....	391
Val procedure .....	392
WhereX function .....	393
WhereY function .....	393
Window procedure .....	394
Write procedure (text files) .....	395
Write procedure (typed files) .....	397
Writeln procedure .....	397

## **Part 2 Appendices**

<b>Appendix A</b> Comparing Turbo Pascal 5.0 with ANSI Pascal .....	401
Exceptions to ANSI Pascal Requirements .....	401
Extensions to ANSI Pascal .....	403
Implementation-Dependent Features .....	405
Treatment of Errors .....	406

<b>Appendix B</b> Compiler Directives .....	407
Switch Directives .....	408
Align Data .....	408
Boolean Evaluation .....	409
Debug Information .....	410
Emulation .....	410
Force FAR Calls .....	411
Input/Output-Checking .....	411
Local Symbol Information .....	412
Numeric Processing .....	412
Overlay Code Generation .....	413
Range-Checking .....	413

Stack-Overflow Checking .....	414
Var-String Checking .....	414
Parameter Directives .....	415
Include File .....	415
Link Object File .....	415
Memory Allocation Sizes .....	416
Overlay Unit Name .....	416
Conditional Compilation .....	416
Conditional Symbols .....	417
The DEFINE Directive .....	419
The UNDEF Directive .....	419
The IFDEF Directive .....	419
The IFNDEF Directive .....	419
The IFOPT Directive .....	420
The ELSE Directive .....	420
The ENDIF Directive .....	420
<b>Appendix C Reference Materials</b> .....	421
ASCII Codes .....	421
Extended Key Codes .....	424
Keyboard Scan Codes .....	425
<b>Appendix D Error Messages and Codes</b> .....	427
Compiler Error Messages .....	427
Run-time Errors .....	443
DOS Errors .....	443
I/O Errors .....	445
Critical Errors .....	446
Fatal Errors .....	447
<b>Index</b> .....	449

# List of Figures

Figure 15.1: Turbo Pascal Memory Map .....	180
Figure 15.2: Disposal Method Using Mark and Release .....	182
Figure 15.3: Heap Layout with Release(P) Executed .....	183
Figure 15.4: Creating a "Hole" in the Heap .....	184
Figure 15.5: Enlarging the Free Block .....	184
Figure 15.6: Releasing the Free Block .....	185

# List of Tables

Table 3.1: Predefined Integer Types .....	23
Table 3.2: Real Data Types .....	26
Table 6.1: Precedence of Operators .....	51
Table 6.2: Binary Arithmetic Operations .....	55
Table 6.3: Unary Arithmetic Operations .....	55
Table 6.4: Logical Operations .....	56
Table 6.5: Boolean Operations .....	56
Table 6.6: String Operation .....	57
Table 6.7: Set Operations .....	58
Table 6.8: Relational Operations .....	59
Table 6.9: Pointer Operation .....	61
Table 12.1: Standard Units .....	116
Table 16.1: Components of the Output String .....	396
Table 16.2: Components of the Fixed-Point String .....	396
Table C.1: ASCII Table .....	422
Table C.2: Extended Key Codes .....	424
Table C.3: Keyboard Scan Codes .....	426

Welcome to the second book in the Turbo Pascal 5.0 set. The first book, *Turbo Pascal User's Guide*, provided you with many basics (and more) for getting started with programming in Turbo Pascal, plus guided you through using the integrated environment. Now you're ready to delve into the details of the Turbo Pascal language.

## What's On Your Disks

---

The distribution disks that come with this manual include two different versions of the Pascal compiler: an integrated environment version and a stand-alone, command-line version.

You might not need all the files that come on your distribution disks. Use the INSTALL program and then delete the files you don't need from your working disks. (See the "Turbo Pascal Utilities" Appendix in the *User's Guide* for information on INSTALL.) The README file contains a complete file list. For your reference, here's a summary of most of the files on disks and how to determine which ones to retain:

README	To see any last-minute notes and corrections, type <code>README</code> at the system prompt. (If you have a printer, you can print it out.) Once you review this material, keep it around for future reference.
HELPME!.DOC	Contains answers to many common questions about Turbo Pascal 5.0.
TURBO.EXE	This is the integrated (menu-driven) environment version of Turbo Pascal. It lets you edit, compile, run, and debug your program. See Chapter 7 in the <i>User's Guide</i> , "All About the Integrated Environment," for more information.
TURBO.TPL	This contains the units (program libraries) that come with Turbo Pascal, including <i>System</i> , <i>Crt</i> , <i>Dos</i> , <i>Overlay</i> ,



and *Printer*—this is a must! See Chapter 12, “Standard Units,” for more information on these units.

TURBO.HLP	This contains the online, context-sensitive help text used by the integrated environment and the THELP utility. See the section “Online Help” in Chapter 2 of the <i>User’s Guide</i> for details on the help feature, and Appendix C of the <i>User’s Guide</i> , “Turbo Pascal Utilities, for information on THELP.
THELP.COM	This is the memory-resident that provides access to Turbo Pascal’s context-sensitive help system from any program. See Appendix C in the <i>User’s Guide</i> , “Turbo Pascal Utilities.”
TPC.EXE	This is the command-line version of Turbo Pascal. If you use a separate editor, make heavy use of batch files, and so on, you’ll probably want to use this. Refer to Chapter 8, “Command-Line Reference,” in the <i>User’s Guide</i> for information on how to use the command-line compiler.
GRAPH.TPU	This contains the <i>Graph</i> unit (the Borland Graphics Interface unit). See the section “The Graph Unit” in Chapter 12 of this manual for more information.
*.ARC files	Packed files that contain documentation files, example programs, graphics drivers fonts, interface section listings for Turbo Pascal’s units, and more. Chapter 1 of the <i>User’s Guide</i> walks you through the dearchiving of these files with the INSTALL program.
*.BGI files	BGI graphics device drivers.
*.CHR files	BGI graphics stroked character fonts.
*.DOC files	These include the interface section listings for all the standard units.
*.PAS files	These include an overlay example and the MicroCalc source files, as well as other sample programs.
INSTALL.EXE	This new utility sets up Turbo Pascal on your system. Refer to Chapter 1 of the <i>User’s Guide</i> for information on INSTALL.
TPUMOVER.EXE	This utility allows you to move units to or remove units from the TURBO.TPL file. Appendix C in the <i>User’s Guide</i> , “Turbo Pascal Utilities,” contains information on TPUMOVER.

TINST.EXE	This utility allows you to customize certain features of TURBO.EXE. See Appendix D in the <i>User's Guide</i> , "Customizing Turbo Pascal," for more information.
TINSTXFR.EXE	This utility transfers the customized settings you created with TINST in 4.0 to 5.0. See Appendix D in the <i>User's Guide</i> , "Customizing Turbo Pascal."
MAKE.EXE	This is an intelligent project manager that allows you to keep your programs up-to-date and is especially useful when mixing assembler and Pascal and using the command-line compiler (TPC.EXE). See Appendix C in the <i>User's Guide</i> , "Turbo Pascal Utilities," for more information on using MAKE.
GREP.COM	This is a fast, powerful text search utility. See Appendix C in the <i>User's Guide</i> , "Turbo Pascal Utilities," for more information on using GREP.
TOUCH.COM	This utility changes the date and time of one or more files to the current date and time, making it "newer" than the files that depend on it. It's generally used in conjunction with MAKE.EXE.
BINOBJ.EXE	Use this utility to convert a binary data file to an .OBJ file.
TPCONFIG.EXE	This utility takes your integrated environment configuration file and converts it to work with the command-line compiler (as TPC.CFG). It's helpful if you want to use the integrated environment to set all your options, but want to compile with the command-line version. This utility will also convert a TPC.CFG file to a .TP file.
UPGRADE.DTA UPGRADE.EXE	This utility does a quick upgrade of Turbo Pascal version 3.0 source files, modifying them for compatibility with Turbo Pascal version 5.0. See the section on UPGRADE in Appendix A of the <i>User's Guide</i> for more information.
GRAPH3.TPU TURBO3.TPU	These are version 3.0 compatibility units. Refer to Appendix A in the <i>User's Guide</i> , "Differences Between Turbo Pascal 3.0, 4.0, and 5.0."
README.COM	This is the program to display the README file. Once you've read the README, you can delete this.

## *Installing Turbo Pascal On Your System*

---

Your Turbo Pascal package includes all the files and programs necessary to run both the integrated environment and command-line versions of the compiler. A new program, INSTALL.EXE, sets up Turbo Pascal on your system. INSTALL works on both floppy-based and hard disk systems. Refer to Chapter 1 in the *User's Guide* for information about INSTALL.

## **About This Manual**

---

This book is split into two parts: a programmer's reference and appendices. The first part of this manual, "Programmer's Reference," offers technical information on the following features of the language:

- Chapter 1: Tokens and Constants
- Chapter 2: Blocks, Locality, and Scope
- Chapter 3: Types
- Chapter 4: Variables
- Chapter 5: Typed Constants
- Chapter 6: Expressions
- Chapter 7: Statements
- Chapter 8: Procedures and Functions
- Chapter 9: Programs and Units
- Chapter 10: Input and Output
- Chapter 11: Standard Procedures and Functions
- Chapter 12: Standard Units
- Chapter 13: Overlays
- Chapter 14: Using the 8087
- Chapter 15: Inside Turbo Pascal
- Chapter 16: Turbo Pascal Reference Lookup

Part two, "Appendices," discusses 5.0 and ANSI Pascal, covers the compiler directives provided, provides some reference materials (an ASCII chart, extended key codes, and keyboard scan codes), and lists all the compiler and run-time error messages generated by Turbo Pascal.

- Appendix A: Comparing Turbo Pascal 5.0 with ANSI Pascal
- Appendix B: Compiler Directives
- Appendix C: Reference Materials
- Appendix D: Error Messages and Codes

# Typography

---

This manual was produced by Borland's Sprint: The Professional Word Processor on a PostScript printer. The different typefaces displayed are used for the following purposes:

<i>Italics</i>	In text, this typeface represents constant identifiers, field identifiers, and formal parameter identifiers, as well as unit names, labels, variables, procedures, and functions.
<b>Boldface</b>	Turbo Pascal's reserved words are set in this typeface.
Monospace	This type represents text that appears on your screen.
<i>Keycaps</i>	This typeface indicates a key on your keyboard. It is often used when describing a key you have to press to perform a particular function; for example, "Press <i>Esc</i> to exit from a menu."

## How to Contact Borland

---

If, after reading this manual and using Turbo Pascal, you would like to contact Borland with comments or suggestions, we suggest the following procedures:

- The best way is to log on to Borland's forum on CompuServe: Type GO BPROGA at the main CompuServe menu and follow the menus to section 2. Leave your questions or comments here for the support staff to process.
- If you prefer, write a letter detailing your problem and send it to

Technical Support Department  
Borland International  
P.O. Box 660001  
1800 Green Hills Road  
Scotts Valley, CA 95066-0001

**Please note:** If you include a program example in your message, it must be limited to 100 lines or less. We request that you submit it on disk, include all the necessary support files on that disk, and provide step-by-step instructions on how to reproduce the problem. Before you decide to get technical support, try to replicate the problem with the code contained on a floppy disk, just to be sure we can duplicate the problem using the disk you provide us.

■ You can also telephone our Technical Support department at (408) 438-5300. To help us handle your problem as quickly as possible, have these items handy before you call:

- product name and version number
- product serial number
- computer make and model number
- operating system and version number

If you're not familiar with Borland's No-Nonsense License statement, now's the time to read the agreement at the front of this manual and mail in your completed product registration card.

P

A

R

T


---

**1**

# **Programmer's Reference**



The names in rectangular boxes stand for actual constructions. Those in circular boxes—reserved words, operators, and punctuation—are the actual terms to be used in the program.



Special symbols and reserved words are characters that have one or more fixed meanings. These single characters are special symbols:

+ - \* / = < > [ ] . , ( ) : ; ^ @ { } \$ #

These character pairs are also special symbols:

<= >= := .. (\* \*) (.)

Some special symbols are also operators. A left bracket ([) is equivalent to the character pair of left parentheses and a period ((.)). Similarly, a right bracket (]) is equivalent to the character pair of a period and a right parentheses (.)).

Following are Turbo Pascal's reserved words:

---

<b>absolute</b>	<b>end</b>	<b>inline</b>	<b>procedure</b>	<b>type</b>
<b>and</b>	<b>external</b>	<b>interface</b>	<b>program</b>	<b>unit</b>
<b>array</b>	<b>file</b>	<b>interrupt</b>	<b>record</b>	<b>until</b>
<b>begin</b>	<b>for</b>	<b>label</b>	<b>repeat</b>	<b>uses</b>
<b>case</b>	<b>forward</b>	<b>mod</b>	<b>set</b>	<b>var</b>
<b>const</b>	<b>function</b>	<b>nil</b>	<b>shl</b>	<b>while</b>
<b>div</b>	<b>goto</b>	<b>not</b>	<b>shr</b>	<b>with</b>
<b>do</b>	<b>if</b>	<b>of</b>	<b>string</b>	<b>xor</b>
<b>downto</b>	<b>implementation</b>	<b>or</b>	<b>then</b>	
<b>else</b>	<b>in</b>	<b>packed</b>	<b>to</b>	

---



## Tokens and Constants

*Tokens* are the smallest meaningful units of text in a Pascal program, and they are categorized as special symbols, identifiers, labels, numbers, and string constants.

A Pascal program is made up of tokens and separators, where a separator is either a blank or a comment. Two adjacent tokens must be separated by one or more separators if each token is a reserved word, an identifier, a label, or a number.

Separators cannot be part of tokens except in string constants.

## Special Symbols and Reserved Words

Turbo Pascal uses the following subsets of the ASCII character set:

- **Letters**—the English alphabet, *A* through *Z* and *a* through *z*.
- **Digits**—the Arabic numerals 0 through 9.
- **Hex digits**—the Arabic numerals 0 through 9, the letters *A* through *F*, and the letters *a* through *f*.
- **Blanks**—the space character (ASCII 32) and all ASCII control characters (ASCII 0 to 31), including the end-of-line or return character (ASCII 13).

What follows are *syntax diagrams* for letter, digit, and hex digit. To read a syntax diagram, follow the arrows. Alternative paths are often possible; paths that begin at the left and end with an arrow on the right are valid. A path traverses boxes that hold the names of elements used to construct that portion of the syntax.

Reserved words appear in lowercase **boldface** throughout this manual. Turbo Pascal isn't case sensitive, however, so you can use either uppercase or lowercase letters in your programs.


## Identifiers

---

Identifiers denote constants, types, variables, procedures, functions, units, programs, and fields in records. An identifier can be of any length, but only the first 63 characters are significant.

An identifier must begin with a letter or an underscore character and cannot contain spaces. Letters, digits, and underscore characters (ASCII \$5F) are allowed after the first character. Like reserved words, identifiers are not case sensitive.

When several instances of the same identifier exist, you may need to qualify the identifier by a unit identifier in order to select a specific instance (units are described in Chapter 4 of the *User's Guide* and 12 of this manual). For example, to qualify the identifier *Ident* by the unit identifier *UnitName*, you would write *UnitName.Ident*. The combined identifier is called a *qualified identifier*.



Here are some examples of identifiers:


```

Writeln
Exit
Real2String
System.MemAvail
Dos.Exec
Crt.Window
  
```

In this manual, standard and user-defined identifiers are *italicized* when they are referred to in text.

## Labels


A *label* is a digit sequence in the range 0 to 9999. Leading zeros are not significant. Labels are used with **goto** statements.




As an extension to standard Pascal, Turbo Pascal also allows identifiers to function as labels.

## Numbers

Ordinary decimal notation is used for numbers that are constants of type integer and real. A hexadecimal integer constant uses a dollar sign (\$) as a prefix. Engineering notation (E or e, followed by an exponent) is read as "times ten to the power of" in real types. For example, 7E-2 means  $7 \times 10^{-2}$ ; 12.25e+6 or 12.25e6 both mean  $12.25 \times 10^{+6}$ . Syntax diagrams for writing numbers follow.






Numbers with decimals or exponents denote real-type constants. Other decimal numbers denote integer-type constants; they must be within the range -2147483648 to 2147483647.

Hexadecimal numbers denote integer-type constants; they must be within the range \$00000000 to \$FFFFFFF. The resulting value's sign is implied by the hexadecimal notation.

## Character Strings

A character string is a sequence of zero or more characters from the extended ASCII character set (Appendix C), written on one line in the program and enclosed by apostrophes. A character string with nothing between the apostrophes is a *null string*. Two sequential apostrophes in a character string denote a single character, an apostrophe. The length attribute of a character string is the actual number of characters within the apostrophes.

As an extension to standard Pascal, Turbo Pascal allows control characters to be embedded in character strings. The # character followed by an unsigned integer constant in the range 0 to 255 denotes a character of the corresponding ASCII value. There must be no separators between the # character and the integer constant. Likewise, if several control characters are part of a character string, there must be no separators between them.



A character string of length zero (the null string) is compatible only with string types. A character string of length one is compatible with any char and string type. A character string of length  $n$ , where  $n$  is greater than or


equal to 2, is compatible with any string type and with packed arrays of  $n$  characters.

Here are some examples of character strings:

```
'TURBO'      'You''ll see'    ''''      ';'      ''
#13#10      'Line 1'#13'Line2'    #7#7'Wake up!'#7#7
```

## Constant Declarations

A constant declaration declares an identifier that marks a constant within the block containing the declaration. A constant identifier cannot be included in its own declaration.



As an extension to standard Pascal, Turbo Pascal allows use of constant expressions. A *constant expression* is an expression that can be evaluated by the compiler without actually executing the program. Examples of constant expressions follow:

```
100
'A'
256 - 1
(2.5 + 1) / (2.5 - 1)
'Turbo' + ' ' + 'Pascal'
Chr(32)
Ord('Z') - Ord('A') + 1
```

The simplest case of a constant expression is a simple constant, such as 100 or 'A'; wherever standard Pascal allows only a simple constant, Turbo Pascal allows a constant expression.

Since the compiler has to be able to completely evaluate a constant expression at compile time, the following constructs are *not* allowed in constant expressions:

- references to variables and typed constants
- function calls (except those noted in the following text)
- the address operator (@)

Except for these restrictions, constant expressions follow the exact syntactical rules as ordinary expressions (described in Chapter 6, "Expressions").

The following standard functions are allowed in constant expressions:

Abs	Chr	Hi	Length	Lo	Odd	Ord
Pred	Ptr	Round	SizeOf	Succ	Swap	Trunc

Here are some examples of the use of constant expressions in constant declarations:

```
const
  Min      = 0;
  Max      = 100;
  Center   = (Max - Min) div 2;
  Beta     = Chr(225);
  NumChars = Ord('Z') - Ord('A') + 1;
  Message  = 'Out of memory';
  ErrStr   = ' Error: ' + Message + '. ';
  ErrPos   = 80 - Length(ErrorStr) div 2;
  Ln10     = 2.302585092994045684;
  Ln10R    = 1 / Ln10;
  Numeric  = ['0'..'9'];
  Alpha    = ['A'..'Z','a'..'z'];
  AlphaNum = Alpha + Numeric;
```

## Comments

---

The following constructs are comments and are ignored by the compiler:

```
{ Any text not containing right brace }
(* Any text not containing star/right parenthesis *)
```

A comment that contains a dollar sign (\$) immediately after the opening { or (\* is a compiler directive. A mnemonic of the compiler command follows the \$ character. The compiler directives are summarized in Appendix B.

## Program Lines

---


Turbo Pascal program lines have a maximum length of 126 characters.

## Blocks, Locality, and Scope

A block is made up of declarations, which are written and combined in any order, and statements. Each block is part of a procedure declaration, a function declaration, or a program or unit. All identifiers and labels declared in the declaration part are local to the block.


### Syntax

The overall syntax of any block follows this format:




The *label declaration part* is where labels that mark statements in the corresponding statement part are declared. Each label must mark only one statement.






The digit sequence used for a label must be in the range 0 to 9999.


The *constant declaration part* consists of constant declarations local to the block.




The *type declaration part* includes all type declarations local to the block.




The *variable declaration part* is composed of variable declarations local to the block.



The *procedure and function declaration part* comprises procedure and function declarations local to the block.



The *statement part* defines the statements or algorithmic actions to be executed by the block.



## Rules of Scope

---

The presence of an identifier or label in a declaration defines the identifier or label. Each time the identifier or label occurs again, it must be within the *scope* of this declaration. The scope of an identifier or label encompasses its declaration to the end of the current block, including all blocks enclosed by the current block; some exceptions follow.

- **Redeclaration in an enclosed block:** Suppose that *Exterior* is a block that encloses another block, *Interior*. If *Exterior* and *Interior* both have an identifier with the same name, for example, *j*, then *Interior* can only access the *j* it declared, and similarly *Exterior* can only access the *j* it declared.
- **Position of declaration within its block:** Identifiers and labels cannot be used until after they are declared. An identifier or label's declaration must come before any occurrence of that identifier or label in the program text, with one exception.

The base type of a pointer type can be an identifier that has not yet been declared. However, the identifier must eventually be declared in the same type declaration part that the pointer type occurs in.

- **Redeclaration within a block:** An identifier or label can only be declared *once* in the outer level of a given block. The only exception to this is when it is declared within a contained block or is in a record's field list.

A record field identifier is declared within a record type and is significant only in combination with a reference to a variable of that record type. So, you can redeclare a field identifier (with the same spelling) within the same block but not at the same level within the same record type. However, an identifier that has been declared can be redeclared as a field identifier in the same block.

## Scope of Interface and Standard Identifiers

---


Programs or units containing **uses** clauses have access to the identifiers belonging to the interface parts of the units in those **uses** clauses.

Each unit in a **uses** clause imposes a new scope that encloses the remaining units used and the entire program. The first unit in a **uses** clause represents the outermost scope, and the last unit represents the innermost scope. This implies that if two or more units declare the same identifier, an unqualified reference to the identifier will select the instance declared by the last unit in the **uses** clause. However, by writing a qualified identifier, every instance of the identifier can be selected.

The identifiers of Turbo Pascal's predefined constants, types, variables, procedures, and functions act as if they were declared in a block enclosing all used units and the entire program. In fact, these standard objects are defined in a unit called *System*, which is used by any program or unit before the units named in the **uses** clause. This suggests that any unit or program can redeclare the standard identifiers, but a specific reference can still be made through a qualified identifier, for example, *System.Integer* or *System.Writeln*.

# Types

When you declare a variable, you must state its type. A variable's *type* circumscribes the set of values it can have and the operations that can be performed on it. A *type declaration* specifies the identifier that denotes a type.



When an identifier occurs on the left side of a type declaration, it is declared as a type identifier for the block in which the type declaration occurs. A type identifier's scope does not include itself except for pointer types.

There are five major classes of types:


- simple types
- string types
- structured types
- pointer types
- procedural types

Each of these classes are described in the following sections.

## Simple Types

---

Simple types define ordered sets of values.



A type real identifier is one of the standard identifiers: real, single, double, extended, or comp. Refer to the sections entitled “Numbers” and “String Constants” in Chapter 1 to find out how to denote constant type integer and real values.


## Ordinal Types

---

Ordinal types are a subset of simple types. All simple types other than real types are ordinal types, which are set off by four characteristics:

- All possible values of a given ordinal type are an ordered set, and each possible value is associated with an *ordinality*, which is an integral value. Except for type integer values, the first value of every ordinal type has ordinality 0, the next has ordinality 1, and so on for each value in that ordinal type. A type integer value's ordinality is the value itself. In any ordinal type, each value other than the first has a predecessor, and each value other than the last has a successor based on the ordering of the type.
- The standard function *Ord* can be applied to any ordinal-type value to return the ordinality of the value.
- The standard function *Pred* can be applied to any ordinal-type value to return the predecessor of the value. If applied to the first value in the ordinal type, *Pred* produces an error.
- The standard function *Succ* can be applied to any ordinal-type value to return the successor of the value. If applied to the last value in the ordinal type, *Succ* produces an error.

The syntax of an ordinal type follows.



Turbo Pascal has seven predefined ordinal types: integer, shortint, longint, byte, word, boolean, and char. In addition, there are two other classes of user-defined ordinal types: enumerated types and subrange types.

## Integer Types

There are five predefined integer types: shortint, integer, longint, byte, and word. Each type denotes a specific subset of the whole numbers, according to the following table:

Table 3.1: Predefined Integer Types

Type	Range	Format
shortint	-128 .. 127	Signed 8-bit
integer	-32768 .. 32767	Signed 16-bit
longint	-2147483648 .. 2147483647	Signed 32-bit
byte	0 .. 255	Unsigned 8-bit
word	0 .. 65535	Unsigned 16-bit

Arithmetic operations with type integer operands use 8-bit, 16-bit, or 32-bit precision, according to the following rules:

- The type of an integer constant is the predefined integer type with the smallest range that includes the value of the integer constant.
- For a binary operator (an operator that takes two operands), both operands are converted to their common type before the operation. The *common type* is the predefined integer type with the smallest range that includes all possible values of both types. For instance, the common type of integer and byte is integer, and the common type of integer and word is longint. The operation is performed using the precision of the common type, and the result type is the common type.
- The expression on the right of an assignment statement is evaluated independently from the size or type of the variable on the left.
- Any byte-sized operand is converted to an intermediate word-sized operand that is compatible with both integer and word before any arithmetic operation is performed.

An integer type value can be explicitly converted to another integer type through typecasting. (Typecasting is described in Chapters 4 and 6.)

## Boolean Type

Type boolean values are denoted by the predefined constant identifiers *false* and *true*. Because boolean is an enumerated type, these relationships hold:

- *false* < *true*
- *Ord*(*false*) = 0
- *Ord*(*true*) = 1
- *Succ*(*false*) = *true*
- *Pred*(*true*) = *false*


## Char Type

This type's set of values are characters, ordered according to the extended ASCII character set (Appendix C). The function call *Ord*(*Ch*), where *Ch* is a char value, returns *Ch*'s ordinality.

A string constant of length 1 can denote a constant character value. Any character value can be generated with the standard function *Chr*.

## Enumerated Types

Enumerated types define ordered sets of values by enumerating the identifiers that denote these values. Their ordering follows the sequence in which the identifiers are enumerated.



When an identifier occurs within the identifier list of an enumerated type, it is declared as a constant for the block in which the enumerated type is declared. This constant's type is the enumerated type being declared.

An enumerated constant's ordinality is determined by its position in the identifier list in which it is declared. The enumerated type in which it is

declared becomes the constant's type. The first enumerated constant in a list has an ordinality of zero.

An example of an enumerated type follows:


```
type
  suit = (club,diamond,heart,spade);
```

Given these declarations, *diamond* is a constant of type *suit*.

When the *Ord* function is applied to an enumerated type's value, *Ord* returns an integer that shows where the value falls with respect to the other values of the enumerated type. Given the preceding declarations, *Ord(club)* returns zero, *Ord(diamond)* returns 1, and so on.

## Subrange Types

A subrange type is a range of values from an ordinal type called the *host type*. The definition of a subrange type specifies the least and the largest value in the subrange; its syntax follows:



Both constants must be of the same ordinal type. Subrange types of the form *a..b* require that *a* is less than or equal to *b*.

Examples of subrange types:

```
0..99
-128..127
club..heart
```

A variable of a subrange type has all the properties of variables of the host type, but its run-time value must be in the specified interval.

One syntactic ambiguity arises from allowing constant expressions where Standard Pascal only allows simple constants. Consider the following declarations:

```
const
  x = 50;
  y = 10;
type
  color = (red,green,blue);
  scale = (x-y)*2..(x+y)*2;
```

Standard Pascal syntax dictates that, if a type definition starts with a parenthesis, it is an enumerated type, such as the *color* type described previously. However, the intent of the declaration of *scale* is to define a



subrange type. The solution is to either reorganize the first subrange expression so that it does not start with a parenthesis, or to set another constant equal to the value of the expression, and then use that constant in the type definition:

```
type
  scale = 2*(x-y) .. (x+y) *2;
```

## Real Types

A real type has a set of values that is a subset of real numbers, which can be represented in floating-point notation with a fixed number of digits. A value's floating-point notation normally comprises three values— $m$ ,  $b$ , and  $e$ —such that  $m \times b^e = n$ , where  $b$  is always 2, and both  $m$  and  $e$  are integral values within the real type's range. These  $m$  and  $e$  values further prescribe the real type's range and precision.

There are five kinds of real types: real, single, double, extended, and comp.

The real types differ in the range and precision of values they hold (see Table 3.2).

Table 3.2: Real Data Types

Type	Range	Significant Digits	Size in Bytes
real	$2.9 \times 10^{-39} \dots 1.7 \times 10^{38}$	11-12	6
single	$1.5 \times 10^{-45} \dots 3.4 \times 10^{38}$	7-8	4
double	$5.0 \times 10^{-324} \dots 1.7 \times 10^{308}$	15-16	8
extended	$3.4 \times 10^{-4932} \dots 1.1 \times 10^{4932}$	19-20	10
comp	$-2^{63}+1 \dots 2^{63}-1$	19-20	8

**Note:** The comp type holds only integral values within the range  $-2^{63}+1$  to  $2^{63}-1$ , which is approximately  $-9.2 \times 10^{18}$  to  $9.2 \times 10^{18}$ .

Turbo Pascal supports two models of code generation for performing real-type operations: *software* floating point and *8087* floating point. The appropriate model is selected through the  $\$N$  compiler directive. If no 8087 is present, enabling the  $\{ \$E \}$  compiler directive will provide full 8087 emulation in software.

## Software Floating Point

In the  $\{ \$N- \}$  state, which is selected by default, the code generated performs all real type calculations in software by calling run-time library routines. For reasons of speed and code size, only operations on variables of type

real are allowed in this state. Any attempt to compile statements that operate on the single, double, extended, and comp types generates an error.

## 8087 Floating Point

In the  $\{N+\}$  state, the code generated performs all real type calculations using 8087 instructions. This state permits the use of all five real types.


Turbo Pascal includes a run-time library that will automatically *emulate* an 8087 in software if one is not present; the  $\$E$  compiler directive is used to determine whether or not the 8087 emulator should be included in a program.

For further details on 8087 floating-point code generation and software emulation, refer to Chapter 14, "Using the 8087."

## String Types

---

A type string value is a sequence of characters with a dynamic length attribute (depending on the actual character count during program execution) and a constant size attribute from 1 to 255. A string type declared without a size attribute is given the default size attribute 255. The length attribute's current value is returned by the standard function *Length*.




The ordering between any two string values is set by the ordering relationship of the character values in corresponding positions. In two strings of unequal length, each character in the longer string without a corresponding character in the shorter string takes on a higher or greater-than value; for example, 'Xs' is greater than 'X'. Null strings can only be equal to other null strings, and they hold the least string values.

Characters in a string can be accessed as components of an array, as described in "Arrays, Strings, and Indexes" in Chapter 4. Type string operators are described in "String Operator" and "Relational Operators" in Chapter 6, "Expressions." Type string standard procedures and functions are described in "String Procedures and Functions" on page 112.

# Structured Types

A structured type, characterized by its structuring method and by its component type(s), holds more than one value. If a component type is structured, the resulting structured type has more than one level of structuring. A structured type can have unlimited levels of structuring.




The word **packed** in a structured type's declaration tells the compiler to compress data storage, even at the cost of diminished access to a component of a variable of this type. The word **packed** has no effect in Turbo Pascal; instead packing occurs automatically whenever possible.

**Note:** The maximum permitted size of any structured type in Turbo Pascal is 65520 bytes.

## Array Types

Arrays have a fixed number of components of one type—the component type. In the following syntax diagram, the component type follows the word **of**.



The index types, one for each dimension of the array, specify the number of elements. Valid index types are all ordinal types except longint and subranges of longint. The array can be indexed in each dimension by all values of the corresponding index type; the number of elements is therefore the number of values in each index type. The number of dimensions is unlimited.

The following is an example of an array type:

```
array[1..100] of real
```

If an array type's component type is also an array, you can treat the result as an array of arrays or as a single multidimensional array. For instance,

```
array[boolean] of array[1..10] of array[Size] of real
```

is interpreted the same way by the compiler as

```
array[boolean,1..10,Size] of real
```

You can also express

```
packed array[1..10] of packed array[1..8] of boolean
```

as

```
packed array[1..10,1..8] of boolean
```

You access an array's components by supplying the array's identifier with one or more indexes in brackets (see "Arrays, Strings, and Indexes" in Chapter 4).


An array type of the form

```
packed array[m..n] of char
```

where  $m$  is less than  $n$  is called a packed string type (the word **packed** may be omitted, because it has no effect in Turbo Pascal). A packed string type has certain properties not shared by other array types (see "Identical and Compatible Types" later in this chapter).

## Record Types

A record type comprises a set number of components, or fields, that can be of different types. The record type declaration specifies the type of each field and the identifier that names the field.



The fixed part of a record type sets out the list of fixed fields, giving an identifier and a type for each. Each field contains information that is always retrieved in the same way.


The following is an example of a record type:

```

record
  year: integer;
  month: 1..12;
  day: 1..31;
end

```

The variant part shown in the syntax diagram of a record type declaration distributes memory space for more than one list of fields, so the information can be accessed in more ways than one. Each list of fields is a *variant*. The variants overlay the same space in memory, and all fields of all variants can be accessed at all times.



You can see from the diagram that each variant is identified by at least one constant. All constants must be distinct and of an ordinal type compatible with the tag field type. Variant and fixed fields are accessed the same way.

An optional identifier, the tag field identifier, can be placed in the variant part. If a tag field identifier is present, it becomes the identifier of an additional fixed field—the tag field—of the record. The program can use the tag field's value to show which variant is active at a given time. Without a tag field, the program selects a variant by another criterion.

Some record types with variants follow.

```

record
  firstName, lastName : string[40];
  birthDate : Date;

```

```

case citizen : boolean of
  true  : (birthPlace: string[40]);
  false : (country   : string[20];
          entryPort  : string[20];
          entryDate  : Date;
          exitDate   : Date);
end

record
  x,y : real;
  case kind : Figure of
    rectangle : (height,width: real);
    triangle  : (size1,side2,angle: real);
    circle    : (radius: real);
end

```

## Set Types

---

A set type's range of values is the power set of a particular ordinal type (the base type). Each possible value of a set type is a subset of the possible values of the base type.

A variable of a set type can hold from none to all values of the set.



The base type must not have more than 256 possible values, and the ordinal values of the upper and lower bounds of the base type must be within the range 0 to 255. For these reasons, the base type of a set cannot be shortint, integer, longint, or word.


Set-type operators are described in the section entitled "Set Operators" in Chapter 6. "Set Constructors" in the same chapter shows how to construct set values.

Every set type can hold the value [ ], which is called the *empty set*.

## File Types

---

A file type consists of a linear sequence of components of the component type, which can be of any type except a file type or any structured type with a file-type component. The number of components is not set by the file-type declaration.




If the word **of** and the component type are omitted, the type denotes an untyped file. Untyped files are low-level I/O channels primarily used for direct access to any disk file regardless of its internal format.

The standard file type *text* signifies a file containing characters organized into lines. Text files use special input/output procedures, which are discussed in Chapter 10, "Input and Output."

## Pointer Types

---

A pointer type defines a set of values that point to dynamic variables of a specified type called the *base* type. A type pointer variable contains the memory address of a dynamic variable.



If the base type is an undeclared identifier, it must be declared in the same type declaration part as the pointer type.

You can assign a value to a pointer variable with the *New* procedure, the *@* operator, or the *Ptr* function. The *New* procedure allocates a new memory area in the application heap for a dynamic variable and stores the address of that area in the pointer variable. The *@* operator directs the pointer variable to the memory area containing any existing variable, including variables that already have identifiers. The *Ptr* function points the pointer variable to a specific memory address.

The reserved word *nil* denotes a pointer-valued constant that does not point to anything.

The predefined type pointer denotes an untyped pointer, that is, a pointer that does not point to any specific type. Variables of type pointer cannot be dereferenced; writing the pointer symbol ^ after such a variable is an error. Like the value denoted by the word *nil*, values of type pointer are compatible with all other pointer types.

See Chapter 4's section entitled "Pointers and Dynamic Variables" for the syntax of referencing the dynamic variable pointed to by a pointer variable.

## Procedural Types

---

Standard Pascal regards procedures and functions strictly as program parts that can be executed through procedure or function calls. Turbo Pascal has a much broader view of procedures and functions: It allows procedures and functions to be treated as objects that can be assigned to variables and passed as parameters. Such actions are made possible through *procedural types*.

For a complete discussion of procedural types, please refer to the “Procedural Types” section on page 84.

## Identical and Compatible Types

---

Two types may be the same, and this sameness (identity) is mandatory in some contexts. At other times, the two types need only be compatible or merely assignment-compatible. They are identical when they are declared with, or their definitions stem from, the same type identifier.

### *Type Identity*

---

Type identity is required only between actual and formal variable parameters in procedure and function calls.

Two types—say, *T1* and *T2*—are identical if one of the following is True: *T1* and *T2* are the same type identifier; *T1* is declared to be equivalent to a type identical to *T2*.

The second condition connotes that *T1* does not have to be declared directly to be equivalent to *T2*. The type declarations

```
T1 = integer;  
T2 = T1;  
T3 = integer;  
T4 = T2;
```

result in *T1*, *T2*, *T3*, *T4*, and *integer* as identical types. The type declarations

```
T5 = set of integer;  
T6 = set of integer;
```

don’t make *T5* and *T6* identical, since **set of integer** is not a type identifier. Two variables declared in the same declaration, for example:

```
V1, V2: set of integer;
```



are of identical types—unless the declarations are separate. The declarations

```
V1: set of integer;  
V2: set of integer;  
V3: integer;  
V4: integer;
```

mean V3 and V4 are of identical type, but not V1 and V2.

## *Type Compatibility*

---

Compatibility between two types is sometimes required, such as in expressions or in relational operations. Type compatibility is important, however, as a precondition of assignment compatibility.

Type compatibility exists when at least one of the following conditions is True:

- Both types are the same.
- Both types are real types.
- Both types are integer types.
- One type is a subrange of the other.
- Both types are subranges of the same host type.
- Both types are set types with compatible base types.
- Both types are packed string types with an identical number of components.
- One type is a string type and the other is a string type, packed string type, or char type.
- One type is pointer and the other is any pointer type.
- Both types are procedural types with identical result types, an identical number of parameters, and a one-to-one identity between parameter types.

## *Assignment Compatibility*

---

Assignment compatibility is necessary when a value is assigned to something, such as in an assignment statement or in passing value parameters.

A value of type  $T_2$  is assignment-compatible with a type  $T_1$  (that is,  $T_1 := T_2$  is allowed) if any of the following are True:

- $T_1$  and  $T_2$  are identical types and neither is a file type or a structured type that contains a file-type component at any level of structuring.

- $T_1$  and  $T_2$  are compatible ordinal types, and the values of type  $T_2$  falls within the range of possible values of  $T_1$ .
- $T_1$  and  $T_2$  are real types, and the value of type  $T_2$  falls within the range of possible values of  $T_1$ .
- $T_1$  is a real type, and  $T_2$  is an integer type.
- $T_1$  and  $T_2$  are string types.
- $T_1$  is a string type, and  $T_2$  is a char type.
- $T_1$  is a string type, and  $T_2$  is a packed string type.
- $T_1$  and  $T_2$  are compatible, packed string types.
- $T_1$  and  $T_2$  are compatible set types, and all the members of the value of type  $T_2$  fall within the range of possible values of  $T_1$ .
- $T_1$  and  $T_2$  are compatible pointer types.
- $T_1$  and  $T_2$  are compatible procedural types.
- $T_1$  is a procedural type, and  $T_2$  is a procedure or function with an identical result type, an identical number of parameters, and a one-to-one identity between parameter types.

A compile or run-time error occurs when assignment compatibility is necessary and none of the items in the preceding list are True.

## The Type Declaration Part

---

Programs, procedures, and functions that declare types have a type declaration part. An example of this follows:

```

type
  Range      = integer;
  Number     = integer;
  Color      = (red,green,blue);
  CharVal    = Ord('A')..Ord('Z');
  TestIndex  = 1..100;
  TestValue  = -99..99;
  TestList   = array[TestIndex] of TestValue;
  TestListPtr = ^TestList;
  Date       = record
    year: integer;
    month: 1..12;
    day: 1..31;
  end;
  MeasureData = record
    when: Date;
    count: TestIndex;
    data: TestListPtr;
  end;

```

```

MeasureList = array[1..50] of MeasureData;
Name        = string[80];
Sex         = (male,female);
Person      = ^PersonData;
PersonData  = record
    name,firstName: Name;
    age:           integer;
    married:       boolean;
    father,child,sibling: Person;
    case s: Sex of
        male:      (bearded: boolean);
        female:    (pregnant: boolean);
    end;
PersonBuf   = array[0..SizeOf(PersonData)-1] of Byte;
People      = file of PersonData;


```

In the example, *Range*, *Number*, and *integer* are identical types. *TestIndex* is compatible and assignment-compatible with, but not identical to, the types *Number*, *Range*, and *integer*. Notice the use of constant expressions in the declarations of *CharVal* and *PersonBuf*.

# Variables

## Variable Declarations

A variable declaration embodies a list of identifiers that designate new variables and their type.



The type given for the variable(s) can be a type identifier previously declared in a **type** declaration part in the same block, in an enclosing block, or in a unit; it can also be a new type definition.

When an identifier is specified within the identifier list of a variable declaration, that identifier is a variable identifier for the block in which the declaration occurs. The variable can then be referred to throughout the block, unless the identifier is redeclared in an enclosed block. Redclaration causes a new variable using the same identifier, without affecting the value of the original variable.

An example of a variable declaration part follows:

```

var
  X,Y,Z: real;
  I,J,K: integer;
  Digit: 0..9;
  C: Color;
  Done,Error: boolean;
  Operator: (plus, minus, times);
  Hue1,Hue2: set of Color;

```

```
Today: Date;  
Results: MeasureList;  
P1,P2: Person;  
Matrix: array[1..10,1..10] of real;
```

Variables declared outside procedures and functions are called *global variables*, and reside in the *data segment*. Variables declared within procedures and functions are called *local variables*, and reside in the *stack segment*.

## *The Data Segment*

---

The maximum size of the data segment is 65520 bytes. When a program is linked (this happens automatically at the end of the compilation of a program), the global variables of all units used by the program, as well as the program's own global variables, are placed in the data segment.

If you need more than 65520 bytes of global data, you should allocate the larger structures as dynamic variables. For further details on this subject, see "Pointers and Dynamic Variables" on page 42.

## *The Stack Segment*

---

The size of the stack segment is set through a \$M compiler directive—it can be anywhere from 1024 to 65520 bytes. The default stack segment size is 16384 bytes.


Each time a procedure or function is activated (called), it allocates a set of local variables on the stack. On exit, the local variables are disposed. At any time during the execution of a program, the total size of the local variables allocated by the active procedures and functions cannot exceed the size of the stack segment.

The \$\$ compiler directive is used to include stack overflow checks in the code. In the default {\$\$+} state, code is generated to check for stack overflow at the beginning of each procedure and function. In the {\$\$-} state, no such checks are performed. A stack overflow may very well cause a system crash, so don't turn off stack checks unless you are absolutely sure that an overflow will never occur.

## Absolute Variables

---

Variables can be declared to reside at specific memory addresses, and are then called *absolute variables*. The declaration of such variables must include an **absolute** clause following the type:



Note that the variable declaration's identifier list can only specify one identifier when an **absolute** clause is present.

The first form of the **absolute** clause specifies the segment and offset at which the variable is to reside:

```
CrtMode : byte absolute $0040:$0049;
```

The first constant specifies the segment base, and the second specifies the offset within that segment. Both constants must be within the range \$0000 to \$FFFF (0 to 65535).

The second form of the **absolute** clause is used to declare a variable “on top” of another variable, meaning it declares a variable that resides at the same memory address as another variable.

```
var  
Str: string[32];  
StrLen: byte absolute Str;
```

This declaration specifies that the variable *StrLen* should start at the same address as the variable *Str*, and because the first byte of a string variable contains the dynamic length of the string, *StrLen* will contain the length of *Str*.


## Variable References

---

A variable reference signifies one of the following:

- a variable
- a component of a structured- or string-type variable
- a dynamic variable pointed to by a pointer-type variable


The syntax for a variable reference is



Note that the syntax for a variable reference allows a function call to a pointer function. The resulting pointer is then dereferenced to denote a dynamic variable.

## Qualifiers

A variable reference is a variable identifier with zero or more qualifiers that modify the meaning of the variable reference.



An array identifier with no qualifier, for example, references the entire array:

`Results`

An array identifier followed by an index denotes a specific component of the array—in this case a structured variable:

`Results[Current+1]`

With a component that is a record, the index can be followed by a field designator; here the variable access signifies a specific field within a specific array component.

`Results[Current+1].data`

The field designator in a pointer field can be followed by the pointer symbol (a ^) to differentiate between the pointer field and the dynamic variable it points to.

`Results[Current+1].data^`

If the variable being pointed to is an array, indexes can be added to denote components of this array.


`Results[Current+1].data^[J]`

## Arrays, Strings, and Indexes

---

A specific component of an array variable is denoted by a variable reference that refers to the array variable, followed by an index that specifies the component.

A specific character within a string variable is denoted by a variable reference that refers to the string variable, followed by an index that specifies the character position.



The index expressions select components in each corresponding dimension of the array. The number of expressions can't exceed the number of index types in the array declaration. Furthermore, each expression's type must be assignment-compatible with the corresponding index type.

When indexing a multidimensional array, multiple indexes or multiple expressions within an index can be used interchangeably. For example:

`Matrix[I][J]`

is the same as

`Matrix[I,J]`

You can index a string variable with a single index expression, whose value must be in the range  $0..n$ , where  $n$  is the declared size of the string. This accesses one character of the string value, with the type `char` given to that character value.


The first character of a string variable (at index 0) contains the dynamic length of the string; that is, `Length(S)` is the same as `Ord(S[0])`. If a value is assigned to the length attribute, the compiler does not check whether this value is less than the declared size of the string. It is possible to index a string beyond its current dynamic length. The characters thus read are random, and assignments beyond the current length will not affect the actual value of the string variable.

## Records and Field Designators

---

A specific field of a record variable is denoted by a variable reference that refers to the record variable, followed by a field designator specifying the field.





Some examples of a field designator include:

```

Today.year
Results[1].count
Results[1].when.month
  
```

In a statement within a **with** statement, a field designator doesn't have to be preceded by a variable reference to its containing record.

## Pointers and Dynamic Variables

---

The value of a pointer variable is either **nil** or the address of a value that points to a dynamic variable.

The dynamic variable pointed to by a pointer variable is referenced by writing the pointer symbol (^) after the pointer variable.

You create dynamic variables and their pointer values with the standard procedures *New* and *GetMem*. You can use the @ (address-of) operator and the standard function *Ptr* to create pointer values that are treated as pointers to dynamic variables.

**nil** does not point to any variable. The results are undefined if you access a dynamic variable when the pointer's value is **nil** or undefined.

Some examples of references to dynamic variables:


```

P1^
P1^.sibling^
Results[1].data^
  
```

## Variable Typecasts

---

A variable reference of one type can be changed into a variable reference of another type through a *variable typecast*.



When a variable typecast is applied to a variable reference, the variable reference is treated as an instance of the type specified by the type identifier. The size of the variable (the number of bytes occupied by the variable) must be the same as the size of the type denoted by the type

identifier. A variable typecast can be followed by one or more qualifiers, as allowed by the specified type.

Some examples of variable typecasts follow:


```
type
  ByteRec = record
    lo,hi: byte;
  end;
  WordRec = record
    low,high: word;
  end;
  PtrRec = record
    ofs,seg: word;
  end;
  BytePtr = ^Byte;
var
  B: byte;
  W: word;
  L: longint;
  P: pointer;
begin
  W := $1234;
  B := ByteRec(W).lo;
  ByteRec(W).hi := 0;
  L := $01234567;
  W := WordRec(L).lo;
  B := ByteRec(WordRec(L).lo).hi;
  B := BytePtr(L)^;
  P := Ptr($40,$49);
  W := PtrRec(P).seg;
  Inc(PtrRec(P).ofs, 4);
end.
```

Notice the use of the *ByteRec* type to access the low- and high-order bytes of a word; this corresponds to the built-in functions *Lo* and *Hi*, except that a variable typecast can also be used on the left hand side of an assignment. Also, observe the use of the *WordRec* and *PtrRec* types to access the low- and high-order words of a long integer, and the offset and segment parts of a pointer.



## Typed Constants

Typed constants can be compared to initialized variables—variables whose values are defined on entry to their block. Unlike an untyped constant (see the section entitled “Constant Declarations” in Chapter 1), the declaration of a typed constant specifies both the type and the value of the constant.



Typed constants can be used exactly like variables of the same type, and can appear on the left-hand side in an assignment statement. Note that typed constants are initialized *only once*—at the beginning of a program. Thus, for each entry to a procedure or function, the locally declared typed constants are not reinitialized.

## Simple-Type Constants

---

Declaring a typed constant as a simple type simply specifies the value of the constant:

```
const
  Maximum   : integer = 9999;
  Factor    : real = -0.1;
  Breakchar : char = #3;
```

Because a typed constant is actually a variable with a constant value, it cannot be interchanged with ordinary constants. For instance, it cannot be used in the declaration of other constants or types.

```
const
  Min : integer = 0;
  Max : integer = 99;
type
  Vector = array[Min..Max] of integer;
```

The *Vector* declaration is invalid, because *Min* and *Max* are typed constants.

## String-Type Constants

---

The declaration of a typed constant of a string type specifies the maximum length of the string and its initial value:

```
const
  Heading   : string[7] = 'Section';
  NewLine   : string[2] = #13#10;
  TrueStr   : string[5] = 'Yes';
  FalseStr  : string[5] = 'No';
```


## Structured-Type Constants

---

The declaration of a structured-type constant specifies the value of each of the structure's components. Turbo Pascal supports the declaration of type array, record, set, and pointer constants; type file constants, and constants of array and record types that contain type file components are not allowed.

## Array-Type Constants

The declaration of an array-type constant specifies, enclosed in parentheses and separated by commas, the values of the components.



An example of an array-type constant follows:

```
type
  Status = (Active, Passive, Waiting);
  StatusMap = array[Status] of string[7];
const
  StatStr: StatusMap = ('Active', 'Passive', 'Waiting');
```

This example defines the array constant *StatStr*, which can be used to convert values of type *Status* into their corresponding string representations. The components of *StatStr* are

```
StatStr[Active] = 'Active'
StatStr[Passive] = 'Passive'
StatStr[Waiting] = 'Waiting'
```

The component type of an array constant can be any type except a file type. Packed string-type constants (character arrays) can be specified both as single characters and as strings. The definition

```
const
  Digits: array[0..9] of char = ('0', '1', '2', '3', '4', '5', '6', '7', '8', '9');
```

can be expressed more conveniently as

```
const
  Digits: array[0..9] of char = '0123456789';
```

Multidimensional array constants are defined by enclosing the constants of each dimension in separate sets of parentheses, separated by commas. The innermost constants correspond to the rightmost dimensions. The declaration

```
type
  Cube = array[0..1, 0..1, 0..1] of integer;
const
  Maze: Cube = (((0, 1), (2, 3)), ((4, 5), (6, 7)));
```

provides an initialized array *Maze* with the following values:

```


Maze[0,0,0] = 0
Maze[0,0,1] = 1
Maze[0,1,0] = 2
Maze[0,1,1] = 3
Maze[1,0,0] = 4
Maze[1,0,1] = 5
Maze[1,1,0] = 6
Maze[1,1,1] = 7

```

## Record-Type Constants

---

The declaration of a record-type constant specifies the identifier and value of each field, enclosed in parentheses and separated by semicolons.



Some examples of record constants follow:

```

type
  Point = record
    x,y: real;
  end;
  Vector = array[0..1] of Point;
  Month = (Jan,Feb,Mar,Apr,May,Jun,Jly,Aug,Sep,Oct,Nov,Dec);
  Date = record
    d: 1..31; m: Month; y: 1900..1999;
  end;

const
  Origin : Point = (x: 0.0; y: 0.0);
  Line : Vector = ((x: -3.1; y: 1.5), (x: 5.8; y: 3.0));
  SomeDay : Date = (d: 2; m: Dec; y: 1960);

```


The fields must be specified in the same order as they appear in the definition of the record type. If a record contains fields of file types, the constants of that record type cannot be declared. If a record contains a variant, only fields of the selected variant can be specified. If the variant contains a tag field, then its value must be specified.

## Set-Type Constants

---

The declaration of a set-type constant specifies zero or more member constants, enclosed in square brackets and separated by commas. A

member constant is a constant, or a range consisting of two constants, separated by two periods.



Some examples of set constants follow:

```

type
  Digits = set of 0..9;
  Letters = set of 'A'..'Z';
const
  EvenDigits: Digits = {0,2,4,6,8};
  Vowels : Letters = ['A','E','I','O','U','Y'];
  HexDigits : set of '0'..'z' = ['0'..'9','A'..'F','a'...'f'];

```

## Pointer-Type Constants

The declaration of a pointer-type constant can only specify the value `nil`. Some examples include

```

type
  NamePtr = ^NameRec;
  NameRec = record
    Next: NamePtr;
    Name: string[31];
  end;
const
  NameList: NamePtr = nil;
  NoName: NameRec = (Next: nil; Name: '');

```





## Expressions

Expressions are made up of *operators* and *operands*. Most Pascal operators are *binary*, that is, they take two operands; the rest are *unary* and take only one operand. Binary operators use the usual algebraic form, for example,  $a + b$ . A unary operator always precedes its operand, for example,  $-b$ .

In more complex expressions, rules of precedence clarify the order in which operations are performed (see Table 6.1).

Table 6.1: Precedence of Operators

Operators	Precedence	Categories
@, not	first (high)	unary operators
*, /, div, mod, and, shl, shr	second	multiplying operators
+, -, or, xor	third	adding operators
=, <>, <, >, <=, >=, in	fourth (low)	relational operators

There are three basic rules of precedence:


1. First, an operand between two operators of different precedence is bound to the operator with higher precedence.
2. Second, an operand between two equal operators is bound to the one on its left.
3. Third, expressions within parentheses are evaluated prior to being treated as a single operand.

Operations with equal precedence are normally performed from left to right, although the compiler may at times rearrange the operands to generate optimum code.


# Expression Syntax

The precedence rules follow from the syntax of expressions, which are built from factors, terms, and simple expressions.

A factor's syntax follows:




A function call activates a function and denotes the value returned by the function (see "Function Calls" on page 62). A set constructor denotes a value of a set type (see the "Set Constructors" section on page 63). A value typecast changes the type of a value (see "Value Typecasts" on page 64). An unsigned constant has the following syntax:



Some examples of factors include

X	{ Variable reference }
@X	{ Pointer to a variable }
15	{ Unsigned constant }
(X+Y+Z)	{ Subexpression }
Sin(X/2)	{ Function call }
['0..'9','A'..'Z']	{ Set constructor }
<b>not</b> Done	{ Negation of a boolean }
char(Digit+48)	{ Value typecast }


Terms apply the multiplying operators to factors:



Here are some examples of terms:

X\*Y  
 Z/(1-Z)  
 Done **or** Error  
 (X <= Y) **and** (Y < Z)


Simple expressions apply adding operators and signs to terms:



Here are some examples of simple expressions:

X+Y  
-X  
Hue1 + Hue2  
I\*J + 1

An expression applies the relational operators to simple expressions:



Here are some examples of expressions:

X = 1.5  
Done <> Error  
(I < J) = (J < K)  
C in Hue1

## Operators

---

The operators are classified as arithmetic operators, logical operators, string operators, set operators, relational operators, and the @ operator.

### Arithmetic Operators

---

The following tables show the types of operands and results for binary and unary arithmetic operations.

Table 6.2: Binary Arithmetic Operations

Operator	Operation	Operand Types	Result Type
+	addition	integer type real type	integer type real type
-	subtraction	integer type real type	integer type real type
*	multiplication	integer type real type	integer type real type
/	division	integer type real type	real type real type
div	integer division	integer type	integer type
mod	remainder	integer type	integer type

**Note:** The + operator is also used as a string or set operator, and the +, -, and \* operators are also used as set operators.

Table 6.3: Unary Arithmetic Operations

Operator	Operation	Operand Types	Result Type
+	sign identity	integer type real type	integer type real type
-	sign negation	integer type real type	integer type real type

Any operand whose type is a subrange of an ordinal type is treated as if it were of the ordinal type.

If both operands of a +, -, \*, **div**, or **mod** operator are of an integer type, the result type is of the common type of the two operands. (See the section “Integer Types” in Chapter 3 for a definition of common types.)

If one or both operands of a +, -, or \* operator are of a real type, the type of the result is real in the {\$N-} state or extended in the {\$N+} state.

If the operand of the sign identity or sign negation operator is of an integer type, the result is of the same integer type. If the operand is of a real type, the type of the result is real or extended.

The value of  $x/y$  is always of type real or extended regardless of the operand types. An error occurs if  $y$  is zero.

The value of  $i \text{ div } j$  is the mathematical quotient of  $i/j$ , rounded in the direction of zero to an integer-type value. An error occurs if  $j$  is zero.

The **mod** operator returns the remainder obtained by dividing its two operands, that is,

$$i \text{ mod } j = i - (i \text{ div } j) * j$$

The sign of the result of **mod** is the same as the sign of *i*. An error occurs if *j* is zero.

## Logical Operators

The types of operands and results for logical operations are shown in Table 6.4.

Table 6.4: Logical Operations

Operator	Operation	Operand Types	Result Type
<b>not</b>	Bitwise negation	integer type	integer type
<b>and</b>	Bitwise and	integer type	integer type
<b>or</b>	Bitwise or	integer type	integer type
<b>xor</b>	Bitwise xor	integer type	integer type
<b>shl</b>	Shift left	integer type	integer type
<b>shr</b>	Shift right	integer type	integer type

**Note:** The **not** operator is a unary operator.

If the operand of the **not** operator is of an integer type, the result is of the same integer type.

If both operands of an **and**, **or**, or **xor** operator are of an integer type, the result type is the common type of the two operands.

The operations *i shl j* and *i shr j* shift the value of *i* to the left or to the right by *j* bits. The type of the result is the same as the type of *i*.

## Boolean Operators

The types of operands and results for Boolean operations are shown in Table 6.5.

Table 6.5: Boolean Operations

Operator	Operation	Operand Types	Result Type
<b>not</b>	negation	Boolean	Boolean
<b>and</b>	logical and	Boolean	Boolean
<b>or</b>	logical or	Boolean	Boolean
<b>xor</b>	logical xor	Boolean	Boolean

**Note:** The **not** operator is a unary operator.

Normal Boolean logic governs the results of these operations. For instance, *a* and *b* is True only if both *a* and *b* are True.

Turbo Pascal supports two different models of code generation for the **and** and **or** operators: complete evaluation and short-circuit (partial) evaluation.

Complete evaluation means that every operand of a Boolean expression, built from the **and** and **or** operators, is guaranteed to be evaluated, even when the result of the entire expression is already known. This model is convenient when one or more operands of an expression are functions with side effects that alter the meaning of the program.

Short-circuit evaluation guarantees strict left-to-right evaluation and that evaluation stops as soon as the result of the entire expression becomes evident. This model is convenient in most cases, since it guarantees minimum execution time, and usually minimum code size. Short-circuit evaluation also makes possible the evaluation of constructs that would not otherwise be legal; for instance:

```
while (I<=Length(S)) and (S[I]<>' ') do Inc(I);  
while (P<nil) and (P^.Value<5) do P:=P^.Next;
```

In both cases, the second test is not evaluated if the first test is False.

The evaluation model is controlled through the **\$B** compiler directive. The default state is **{B-}** (unless changed using the Options/Compiler menu), and in this state short-circuit evaluation code is generated. In the **{B+}** state, complete evaluation code is generated.

Since standard Pascal does not specify which model should be used for Boolean expression evaluation, programs depending on either model being in effect are not truly portable. However, sacrificing portability is often worth gaining the execution speed and simplicity provided by the short-circuit model.

## String Operator

The types of operands and results for string operation are shown in Table 6.6.

Table 6.6: String Operation

Operator	Operation	Operand Types	Result Type
+	concatenation	string type, char type, or packed string type	string type



Turbo Pascal allows the + operator to be used to concatenate two string operands. The result of the operation  $s + t$ , where  $s$  and  $t$  are of a string type, a char type, or a packed string type, is the concatenation of  $s$  and  $t$ . The result is compatible with any string type (but not with char types and packed string types). If the resulting string is longer than 255 characters, it is truncated after character 255.

## Set Operators

The types of operands for set operations are shown in Table 6.7.

Table 6.7: Set Operations

Operator	Operation	Operand Types
+	union	compatible set types
-	difference	compatible set types
*	intersection	compatible set types

The results of set operations conform to the rules of set logic:

- An ordinal value  $c$  is in  $a + b$  only if  $c$  is in  $a$  or  $b$ .
- An ordinal value  $c$  is in  $a - b$  only if  $c$  is in  $a$  and not in  $b$ .
- An ordinal value  $c$  is in  $a * b$  only if  $c$  is in both  $a$  and  $b$ .

If the smallest ordinal value that is a member of the result of a set operation is  $a$  and the largest is  $b$ , then the type of the result is **set of  $a..b$** .

## Relational Operators

The types of operands and results for relational operations are shown in Table 6.8.

Table 6.8: Relational Operations

Operator Type	Operation	Operand Types	Result Type
=	equal	compatible simple, pointer, set, string, or packed string types	Boolean
<>	not equal	compatible simple, pointer, set, string, or packed string types	Boolean
<	less than	compatible simple, string, or packed string types	Boolean
>	greater than	compatible simple, string, or packed string types	Boolean
<=	less or equal	compatible simple, string, or packed string types	Boolean
>=	greater or equal	compatible simple, string, or packed string types	Boolean
<=	subset of	compatible set types	Boolean
>=	superset of	compatible set types	Boolean
in	member of	left operand: any ordinal type <i>t</i> ; right operand: set whose base is compatible with <i>t</i> .	Boolean

## Comparing Simple Types

When the operands of =, <>, <, >, >=, or <= are of simple types, they must be compatible types; however, if one operand is of a real type, the other can be of an integer type.

## Comparing Strings

The relational operators =, <>, <, >, >=, and <= compare strings according to the ordering of the extended ASCII character set. Any two string values can be compared, because all string values are compatible.

A character-type value is compatible with a string-type value, and when the two are compared, the character-type value is treated as a string-type

value with length 1. When a packed string-type value with  $n$  components is compared with a string-type value, it is treated as a string-type value with length  $n$ .

## Comparing Packed Strings

The relational operators `=`, `<>`, `<`, `>`, `>=`, and `<=` can also be used to compare two packed string-type values if both have the same number of components. If the number of components is  $n$ , then the operation corresponds to comparing two strings, each of length  $n$ .

## Comparing Pointers

The operators `=` and `<>` can be used on compatible pointer-type operands. Two pointers are equal only if they point to the same object.

**Note:** When comparing pointers, Turbo Pascal simply compares the segment and offset parts. Because of the segment mapping scheme of the 80x86 processors, two logically different pointers can in fact point to the same physical memory location. For instance, `Ptr($0040,$0049)` and `Ptr($0000,$0449)` are two pointers to the same physical address. Pointers returned by the standard procedures `New` and `GetMem` are always normalized (offset part in the range \$0000 to \$000F), and will therefore always compare correctly. When creating pointers with the `Ptr` standard function, special care must be taken if such pointers are to be compared.

## Comparing Sets

If  $a$  and  $b$  are set operands, their comparisons produce these results:

- $a = b$  is True only if  $a$  and  $b$  contain exactly the same members; otherwise,  $a <> b$ .
- $a <= b$  is True only if every member of  $a$  is also a member of  $b$ .
- $a >= b$  is True only if every member of  $b$  is also a member of  $a$ .

## Testing Set Membership

The `in` operator returns *true* when the value of the ordinal-type operand is a member of the set-type operand; otherwise, it returns *false*.

## The @ Operator

A pointer to a variable can be created with the @ operator. Table 6.9 shows the operand and result types.

Table 6.9: Pointer Operation

Operator	Operation	Operand Types	Result Type
@	Pointer formation	Variable reference or procedure or function identifier	Pointer (same as nil)

@ is a unary operator that takes a variable reference or a procedure or function identifier as its operand, and returns a pointer to the operand. The type of the value is the same as the type of *nil*, therefore it can be assigned to any pointer variable.

**Note:** Special rules apply to use of the @ operator with a procedural variable. For further details, refer to the “Procedural Types” section on page 84.

### @ with a Variable

The use of @ with an ordinary variable (not a parameter) is uncomplicated. Given the declarations

```
type
  TwoChar = array[0..1] of char;
var
  Int: integer;
  TwoCharPtr: ^TwoChar;
```

then the statement

```
TwoCharPtr := @Int;
```

causes *TwoCharPtr* to point to *Int*. *TwoCharPtr*<sup>^</sup> becomes a re-interpretation of the value of *Int*, as though it were an `array[0..1] of char`.

### @ with a Value Parameter

Applying @ to a formal value parameter results in a pointer to the stack location containing the actual value. Suppose *Foo* is a formal value parameter in a procedure and *FooPtr* is a pointer variable. If the procedure executes the statement

```
FooPtr := @Foo;
```

then  $\text{FooPtr}^{\wedge}$  references *Foo*'s value. However,  $\text{FooPtr}^{\wedge}$  does not reference *Foo* itself, rather it references the value that was taken from *Foo* and stored on the stack.

## @ with a Variable Parameter

Applying @ to a formal variable parameter results in a pointer to the actual parameter (the pointer is taken from the stack). Suppose *One* is a formal variable parameter of a procedure, *Two* is a variable passed to the procedure as *One*'s actual parameter, and *OnePtr* is a pointer variable. If the procedure executes the statement

```
OnePtr := @One;
```

then *OnePtr* is a pointer to *Two*, and  $\text{OnePtr}^{\wedge}$  is a reference to *Two* itself.

## @ with a Procedure or Function


You can apply @ to a procedure or a function to produce a pointer to its entry point. Turbo Pascal does not give you a mechanism for using such a pointer. The only use for a procedure pointer is to pass it to an assembly language routine or to use it in an inline statement. See "Turbo Assembler and Turbo Pascal" on page 200 for information on interfacing Turbo Assembler and Turbo Pascal.


## Function Calls

---

A function call activates the function specified by the function identifier. Any identifier declared to denote a function is a function identifier.

The function call must have a list of actual parameters if the corresponding function declaration contains a list of formal parameters. Each parameter takes the place of the corresponding formal parameter according to parameter rules set forth in Chapter 10, "Input and Output."





Some examples of function calls follow:


```

Sum(A, 63)
Maximum(147, J)
Sin(X+Y)
Eof(F)
Volume(Radius, Height)
  
```

**Note:** A function can also be invoked via a procedural variable. For further details, refer to the “Procedural Types” section on page 84.

## Set Constructors

A set constructor denotes a set-type value, and is formed by writing expressions within brackets ([ ]). Each expression denotes a value of the set.



The notation [ ] denotes the empty set, which is assignment-compatible with every set type. Any member group  $x..y$  denotes as set members all values in the range  $x..y$ . If  $x$  is greater than  $y$ , then  $x..y$  does not denote any members and  $[x..y]$  denotes the empty set.

All expression values in member groups in a particular set constructor must be of the same ordinal type.

Some examples of set constructors follow:


```

[red, C, green]
[1, 5, 10..K mod 12, 23]
['A'..'Z', 'a'..'z', Chr(Digit+48)]
  
```

# Value Typecasts

---

The type of an expression can be changed to another type through a value typecast.



The expression type and the specified type must both be either ordinal types or pointer types. For ordinal types, the resulting value is obtained by converting the expression. The conversion may involve truncation or extension of the original value if the size of the specified type is different from that of the expression. In cases where the value is extended, the sign of the value is always preserved; that is, the value is sign-extended.


The syntax of a value typecast is almost identical to that of a variable typecast (see "Variable Typecasts" on page 42). However, value typecasts operate on values, not on variables, and can therefore not participate in variable references; that is, a value typecast may not be followed by qualifiers. In particular, value typecasts cannot appear on the left-hand side of an assignment statement.

Some examples of value typecasts include

```
integer('A')
char(48)
boolean(0)
Color(2)
Longint(@Buffer)
BytePtr(Ptr($40,$49))
```

## Statements

Statements describe algorithmic actions that can be executed. Labels can prefix statements, and these labels can be referenced by **goto** statements.




As you saw in Chapter 1, a label is either a digit sequence in the range 0 to 9999 or an identifier.

There are two main types of statements: simple statements and structured statements.

## Simple Statements

A *simple* statement is a statement that doesn't contain any other statements.






## Assignment Statements

---

Assignment statements either replace the current value of a variable with a new value specified by an expression or specify an expression whose value is to be returned by a function.



The expression must be assignment-compatible with the type of the variable or the result type of the function (see the section "Type Compatibility" on page 34).


Some examples of assignment statements follow:

```
X      := Y+Z;  
Done := (I>=1) and (I<100);  
Huel := [blue, Succ(C)];  
I      := Sqr(J) - I*K;
```

## Procedure Statements

---

A **procedure** statement specifies the activation of the procedure denoted by the procedure identifier. If the corresponding procedure declaration contains a list of formal parameters, then the procedure statement must have a matching list of actual parameters (parameters listed in definitions are *formal* parameters; in the calling statement, they are *actual* parameters). The actual parameters are passed to the formal parameters as part of the call.



Some examples of procedure statements follow:

```
PrintHeading;  
Transpose(A,N,M);  
Find(Name,Address);
```

**Note:** A procedure can also be invoked via a procedural variable. For further details, refer to the "Procedural Types" section on page 84.

## Goto Statements

---

A **goto** statement transfers program execution to the statement prefixed by the label referenced in the **goto** statement. The syntax diagram of a **goto** statement follows:




The following rules should be observed when using **goto** statements:

- The label referenced by a **goto** statement must be in the same block as the **goto** statement. In other words, it is not possible to jump into or out of a procedure or function.
- Jumping into a structured statement from outside that structured statement (that is, jumping to a “deeper” level of nesting) can have undefined effects, although the compiler will not indicate an error.

## Structured Statements

---


Structured statements are constructs composed of other statements that are to be executed in sequence (compound and **with** statements), conditionally (conditional statements), or repeatedly (repetitive statements).



## Compound Statements

---

The compound statement specifies that its component statements are to be executed in the same sequence as they are written. The component statements are treated as one statement, crucial in contexts where the Pascal syntax only allows one statement. **begin** and **end** bracket the statements, which are separated by semicolons.




Here's an example of a compound statement:

```
begin
  Z := X;
  X := Y;
  Y := Z;
end;
```

## Conditional Statements


---

A conditional statement selects for execution a single one (or none) of its component statements.



## If Statements

The syntax for an if statement reads like this:



The expression must yield a result of the standard type boolean. If the expression produces the value *true*, then the statement following **then** is executed.

If the expression produces *false* and the **else** part is present, the statement following **else** is executed; if the **else** part is not present, nothing is executed.

The syntactic ambiguity arising from the construct

```
if e1 then if e2 then s1 else s2
```

is resolved by interpreting the construct as follows:

```
if e1 then
begin
  if e2 then
    s1
  else
    s2
end
```

In general, an **else** is associated with the closest **if** not already associated with an **else**.

Two examples of **if** statements follow:


```

if X < 1.5 then
  Z := X+Y
else
  Z := 1.5;
if P1 <> nil then
  P1 := P1^.father;

```

## Case Statements

The **case** statement consists of an expression (the selector) and a list of statements, each prefixed with one or more constants (called case constants) or with the word **else**. The selector must be of an ordinal type, and the ordinal values of the upper and lower bounds of that type must be within the range -32768 to 32767. Thus, string types and the integer types **longint** and **word** are invalid selector types. All case constants must be unique and of an ordinal type compatible with the selector type.



The **case** statement executes the statement prefixed by a **case** constant equal to the value of the selector or a **case** range containing the value of the selector. If no such **case** constant of the **case** range exists and an **else** part is

present, the statement following **else** is executed. If there is no **else** part, nothing is executed.

Examples of **case** statements follow:


```
case Operator of
  plus:  X := X+Y;
  minus: X := X-Y;
  times: X := X*Y;
end;

case I of
  0,2,4,6,8: Writeln('Even digit');
  1,3,5,7,9: Writeln('Odd digit');
  10..100:  Writeln('Between 10 and 100');
else
  Writeln('Negative or greater than 100');
end;
```

## *Repetitive Statements*

---


Repetitive statements specify certain statements to be executed repeatedly.



If the number of repetitions is known beforehand, the **for** statement is the appropriate construct. Otherwise, the **while** or **repeat** statement should be used.

## *Repeat Statements*

A **repeat** statement contains an expression that controls the repeated execution of a statement sequence within that **repeat** statement.



The expression must produce a result of type boolean. The statements between the symbols **repeat** and **until** are executed in sequence until, at the end of a sequence, the expression yields *true*. The sequence is executed at

least once, because the expression is evaluated *after* the execution of each sequence.


Examples of **repeat** statements follow:

```
repeat
  K := I mod J;
  I := J;
  J := K;
until J = 0;

repeat
  Write('Enter value (0..9): ');
  Readln(I);
until (I >= 0) and (I <= 9);
```

## While Statements

A **while** statement contains an expression that controls the repeated execution of a statement (which can be a compound statement).



The expression controlling the repetition must be of type *boolean*. It is evaluated *before* the contained statement is executed. The contained statement is executed repeatedly as long as the expression is *true*. If the expression is *false* at the beginning, the statement is not executed at all.

Examples of **while** statements include:


```
while Data[I] <> X do I := I + 1;

while I > 0 do
begin
  if Odd(I) then Z := Z * X;
  I := I div 2;
  X := Sqr(X);
end;

while not Eof(InFile) do
begin
  Readln(InFile, Line);
  Process(Line);
end;
```

## For Statements

The **for** statement causes a statement (which can be a compound statement) to be repeatedly executed while a progression of values is assigned to a control variable.



The control variable must be a variable identifier (without any qualifier) that signifies a variable declared to be local to the block containing the **for** statement. The control variable must be of an ordinal type. The initial and final values must be of a type assignment-compatible with the ordinal type.

When a **for** statement is entered, the initial and final values are determined once for the remainder of the execution of the **for** statement.

The statement contained by the **for** statement is executed once for every value in the range *initial value* to *final value*. The control variable always starts off at *initial value*. When a **for** statement uses **to**, the value of the control variable is incremented by one for each repetition. If *initial value* is greater than *final value*, the contained statement is not executed. When a **for** statement uses **downto**, the value of the control variable is decremented by one for each repetition. If *initial value* value is less than *final value*, the contained statement is not executed.

It's an error if the contained statement alters the value of the control variable. After a **for** statement is executed, the value of the control variable value is undefined, unless execution of the **for** statement was interrupted by a **goto** from the **for** statement.

With these restrictions in mind, the **for** statement

```
for V := Expr1 to Expr2 do Body;
```

is equivalent to

```
begin
```

```

Temp1 := Expr1;
Temp2 := Expr2;
if Temp1 <= Temp2 then
begin
  V := Temp1;
  Body;
  while V <> Temp2 do
    begin
      V := Succ(V);
      Body;
    end;
  end;
end;

```

and the **for** statement

```

for V := Expr1 downto Expr2 do Body;

```

is equivalent to

```

begin
  Temp1 := Expr1;
  Temp2 := Expr2;
  if Temp1 >= Temp2 then
    begin
      V := Temp1;
      Body;
      while V <> Temp2 do
        begin
          V := Pred(V);
          Body;
        end;
      end;
    end;
  end;

```

where *Temp1* and *Temp2* are auxiliary variables of the host type of the variable *V* and don't occur elsewhere in the program.

Examples of **for** statements follow:

```


for I := 2 to 63 do
  if Data[I] > Max then Max := Data[I]
for I := 1 to 10 do
  for J := 1 to 10 do
    begin
      X := 0;
      for K := 1 to 10 do
        X := X + Mat1[I,K] * Mat2[K,J];
      Mat[I,J] := X;
    end;
  for C := red to blue do Check(C);

```



## With Statements

The **with** statement is shorthand for referencing the fields of a record. Within a **with** statement, the fields of one or more specific record variables can be referenced using their field identifiers only. The syntax of a **with** statement follows:



Following is an example of a **with** statement:

```
with Date do
  if month = 12 then
    begin
      month := 1;
      year  := year + 1
    end
  else
    month := month + 1;
```

This is equivalent to

```
if Date.month = 12 then
begin
  Date.month := 1;
  Date.year  := Date.year + 1
end
else
  Date.month := Date.month + 1;
```

Within a **with** statement, each variable reference is first checked to see if it can be interpreted as a field of the record. If so, it is always interpreted as such, even if a variable with the same name is also accessible. Suppose the following declarations have been made:

```
type
  Point = record
    x,y: integer;
  end;
var
  x: Point;
  y: integer;
```

In this case, both  $x$  and  $y$  can refer to a variable or to a field of the record. In the statement

```
with x do
begin
  x := 10;
  y := 25;
end;
```

the  $x$  between **with** and **do** refers to the variable of type *Point*, but in the compound statement,  $x$  and  $y$  refer to  $x.x$  and  $x.y$ .

The statement

```
with V1,V2, ... Vn do s;
```

is equivalent to

```
with V1 do
  with V2 do
    ....
    with Vn do
      S;
```

In both cases, if  $Vn$  is a field of both  $V1$  and  $V2$ , it is interpreted as  $V2.Vn$ , not  $V1.Vn$ .

If the selection of a record variable involves indexing an array or dereferencing a pointer, these actions are executed once before the component statement is executed.




## Procedures and Functions

Procedures and functions allow you to nest additional blocks in the main program block. Each procedure or function declaration has a heading followed by a block. A procedure is activated by a procedure statement; a function is activated by the evaluation of an expression that contains its call and returns a value to that expression.

This chapter discusses the different types of procedure and function declarations and their parameters.

### Procedure Declarations

A procedure declaration associates an identifier with a block as a procedure; that procedure can then be activated by a procedure statement.



The procedure heading names the procedure's identifier and specifies the formal parameters (if any). The syntax for a formal parameter list is shown in the section "Parameters" on page 82.

A procedure is activated by a procedure statement, which states the procedure's identifier and any actual parameters required. The statements to be executed on activation are noted in the statement part of the procedure's block. If the procedure's identifier is used in a procedure statement within the procedure's block, the procedure is executed recursively (it calls itself while executing).

Here's an example of a procedure declaration:

```
procedure NumString(N: integer; var S: string);
var
  V: integer;
begin
  V := Abs(N);
  S := '';
  repeat
    S := Chr(N mod 10 + Ord('0')) + S;
    N := N div 10;
  until N = 0;
  if N < 0 then S := '-' + S;
end;
```

A procedure declaration can optionally specify an **interrupt** directive before the block, and the procedure is then considered an interrupt procedure. Interrupt procedures are described in full in Chapter 15, "Inside Turbo Pascal." For now, note that interrupt procedures cannot be called from procedure statements, and that every interrupt procedure must specify a parameter list exactly like the following:

```
procedure MyInt (Flags, CS, IP, AX, BX, CX, DX, SI, DI, DS, ES, BP: word);
interrupt;
```

Instead of the block in a procedure or function declaration, you can write a **forward**, **external**, or **inline** declaration.

## *Forward Declarations*

---

A procedure declaration that specifies the directive **forward** instead of a block is a **forward** declaration. Somewhere after this declaration, the procedure must be defined by a *defining* declaration—a procedure declaration that uses the same procedure identifier but omits the formal parameter list and includes a block. The **forward** declaration and the defining declaration must appear in the same procedure and function declaration part. Other procedures and functions can be declared between

them, and they can call the forward-declared procedure. Mutual recursion is thus possible.

The **forward** declaration and the defining declaration constitute a complete procedure declaration. The procedure is considered declared at the **forward** declaration.

An example of a **forward** declaration follows:

```
procedure Walter(m,n : integer); forward;
procedure Clara(x,y : real);
begin
  :
  Walter(4,5);
  :
end;
procedure Walter;
begin
  :
  Clara(8.3,2.4);
  :
end;
```

A procedure's defining declaration can be an **external** declaration; however, it cannot be an **inline** declaration or another **forward** declaration. Likewise, the defining declaration cannot specify an **interrupt** directive.

**Forward** declarations are not allowed in the interface part of a unit.

## *External Declarations*

---

**External** declarations allow you to interface with separately compiled procedures and functions written in assembly language. The **external** code must be linked with the Pascal program or unit through `{$L filename}` directives. For further details on linking with assembly language, refer to Chapter 15.

Examples of **external** procedure declarations follow:

```
procedure MoveWord(var source,dest; count: word); external;
procedure MoveLong(var source,dest; count: word); external;

procedure FillWord(var dest; data: integer; count: word); external;
procedure FillLong(var dest; data: longint; count: word); external;

{$L BLOCK.OBJ}
```

You should use **external** procedures when you need to incorporate substantial amounts of assembly code. If you only require small amounts of code, use **inline** procedures instead.

## Inline Declarations


The **inline** directive permits you to write machine code instructions instead of the block. When a normal procedure is called, the compiler generates code that pushes the procedure's parameters onto the stack, and then generates a CALL instruction to call the procedure. When you "call" an inline procedure, the compiler generates code from the inline directive instead of the CALL. Thus, an inline procedure is "expanded" every time you refer to it, just like a macro in assembly language. Here's a short example of two inline procedures:

```
procedure DisableInterrupts; inline($FA); { CLI }  
procedure EnableInterrupts; inline($FB); { STI }
```

Inline procedures are described in full in Chapter 15, "Inside Turbo Pascal."

## Function Declarations

A **function** declaration defines a part of the program that computes and returns a value.



The **function** heading specifies the identifier for the function, the formal parameters (if any), and the function result type.

A function is activated by the evaluation of a **function call**. The **function call** gives the function's identifier and any actual parameters required by the function. A **function call** appears as an operand in an expression. When the expression is evaluated, the function is executed, and the value of the operand becomes the value returned by the function.

The statement part of the function's block specifies the statements to be executed upon activation of the function. The block should contain at least one assignment statement that assigns a value to the function identifier. The result of the function is the last value assigned. If no such assignment statement exists or if it is not executed, the value returned by the function is unspecified.

If the function's identifier is used in a function call within the function's block, the function is executed recursively.

Following are examples of **function declarations**:

```
function Max(a: Vector; n: integer): extended;
var
  x: extended;
  i: integer;
begin
  x := a[1];
  for i := 2 to n do
    if x < a[i] then x := a[i];
  Max := x;
end;

function Power(x: extended; y: integer): extended;
var
  z: extended;
  i: integer;
begin
  z := 1.0; i := y;
  while i > 0 do
    begin
      if Odd(i) then z := z * x;
      i := i div 2;
      x := Sqr(x);
    end;
    Power := z;
end;
```


Like procedures, functions can be declared as **forward**, **external**, or **inline**; however, **interrupt** functions are not allowed.



# Parameters

---

The declaration of a procedure or function specifies a formal parameter list. Each parameter declared in a formal parameter list is local to the procedure or function being declared, and can be referred to by its identifier in the block associated with the procedure or function.



There are three kinds of parameters: *value*, *variable*, and *untyped variable*. They are characterized as follows:

- A parameter group without a preceding **var** and followed by a type is a list of value parameters.
- A parameter group preceded by **var** and followed by a type is a list of variable parameters.
- A parameter group preceded by **var** and not followed by a type is a list of untyped variable parameters.

## Value Parameters

---

A formal value parameter acts like a variable local to the procedure or function, except that it gets its initial value from the corresponding actual parameter upon activation of the procedure or function. Changes made to a formal value parameter do not affect the value of the actual parameter.

A value parameter's corresponding actual parameter in a procedure statement or function call must be an expression, and its value must not be of file type or of any structured type that contains a file type.

The actual parameter must be assignment-compatible with the type of the formal value parameter. If the parameter type is **string**, then the formal parameter is given a size attribute of 255.

## *Variable Parameters*

---

A variable parameter is employed when a value must be passed from a procedure or function to the caller. The corresponding actual parameter in a procedure statement or function call must be a variable reference. The formal variable parameter represents the actual variable during the activation of the procedure or function, so any changes to the value of the formal variable parameter are reflected in the actual parameter.

Within the procedure or function, any reference to the formal variable parameter accesses the actual parameter itself. The type of the actual parameter must be identical to the type of the formal variable parameter (you can bypass this restriction through untyped variable parameters). If the formal parameter type is **string**, it is given the length attribute 255, and the actual variable parameter must be a string type with a length attribute of 255.

File types can only be passed as variable parameters.

If referencing an actual variable parameter involves indexing an array or finding the object of a pointer, these actions are executed before the activation of the procedure or function.

## *Untyped Variable Parameters*

---

When a formal parameter is an untyped variable parameter, the corresponding actual parameter may be any variable reference, regardless of its type.

Within the procedure or function, the untyped variable parameter is typeless; that is, it is incompatible with variables of all other types, unless it is given a specific type through a variable typecast.

An example of untyped variable parameters follows:

```
function Equal(var source,dest; size: word): boolean;
type
  Bytes = array[0..MaxInt] of byte;
var
  N: integer;
begin
  N := 0;
  while (N<size) and (Bytes(dest)[N] <> Bytes(source)[N]) do Inc(N);
```

```

    Equal := N = size;
end;

```

This function can be used to compare any two variables of any size. For instance, given the declarations

```

type
    Vector = array[1..10] of integer;
    Point  = record
        x,y: integer;
    end;
var
    Vec1,Vec2: Vector;
    N: integer;
    P: Point;

```

then the function calls

```

Equal(Vec1,Vec2,SizeOf(Vector))
Equal(Vec1,Vec2,SizeOf(integer)*N)
Equal(Vec[1],Vec1[6],SizeOf(integer)*5)
Equal(Vec1[1],P,4)

```

compare *Vec1* to *Vec2*, compare the first *N* components of *Vec1* to the first *N* components of *Vec2*, compare the first five components of *Vec1* to the last five components of *Vec1*, and compare *Vec1[1]* to *P.x* and *Vec1[2]* to *P.y*.


## Procedural Types

---

As an extension to Standard Pascal, Turbo Pascal allows procedures and functions to be treated as objects that can be assigned to variables and passed as parameters; *procedural types* make this possible.

### Procedural Type Declarations

A procedural type declaration specifies the parameters and, for a function, the result type.



In essence, the syntax for writing a procedural type declaration is exactly the same as for writing a procedure or function header, except that the identifier after the **procedure** or **function** keyword is omitted. Some examples of procedural type declarations follow:

```

type
  Proc      = procedure;
  SwapProc  = procedure(var X,Y: integer);
  StrProc   = procedure(S: string);
  MathFunc  = function(X: real): real;
  DeviceFunc = function(var F: text): integer;
  MaxFunc   = function(A,B: real; F: MathFunc): real;

```

The parameter names in a procedural type declaration are purely decorative—they have no effect on the meaning of the declaration.

**Note:** Turbo Pascal does not allow you to declare functions that return procedural type values; a function result value must be a string, real, integer, char, boolean, pointer, or a user-defined enumeration.

## Procedural Variables

Once a procedural type has been defined, it becomes possible to declare variables of that type. Such variables are called *procedural variables*. For example, given the preceding type declarations, the following variables can be declared:

```

var
  P: SwapProc;
  F: MathFunc;

```

Like an integer variable that can be assigned an integer value, a procedural variable can be assigned a *procedural value*. Such a value can of course be another procedural variable, but it can also be a procedure or a function identifier. In this context, a procedure or function declaration can be viewed as a special kind of constant declaration, the value of the constant being the procedure or function. For example, given the following procedure and function declarations,

```

{$F+}

procedure Swap(var A,B: integer);
var
  Temp: integer;
begin
  Temp := A; A := B; B := Temp;
end;

function Tan(Angle: real): real;
begin
  Tan := Sin(Angle) / Cos(Angle);
end;

{$F-}

```

The variables *P* and *F* declared previously can now be assigned values:

```
P := Swap;  
F := Tan;
```

Following these assignments, the call *P*(*I*,*J*) is equivalent to *Swap*(*I*,*J*), and *F*(*X*) is equivalent to *Tan*(*X*).

As in any other assignment operation, the variable on the left and the value on the right must be assignment-compatible. To be considered assignment-compatible, procedural types must have the same number of parameters, and parameters in corresponding positions must be of identical types; finally, the result types of functions must be identical. As mentioned previously, parameter names are of no significance when it comes to procedural-type compatibility.

In addition to being of a compatible type, a procedure or function must satisfy the following requirements if it is to be assigned to a procedural variable:

- It must be compiled in the {\$F+} state.
- It cannot be
  - a standard procedure or function.
  - a nested procedure or function.
  - an inline procedure or function.
  - an interrupt procedure or function.

The easiest way to satisfy the {\$F+} requirement is simply to place a {\$F+} compiler directive at the beginning of the source text (or to set the O/C/Force Far Calls switch to On in the IDE).

Standard procedures and functions are the procedures and functions declared by the *System* unit, such as *WriteLn*, *ReadLn*, *Chr*, and *Ord*. To use a standard procedure or function with a procedural variable, you will have to write a “shell” around it. For example, given the procedural type

```
type  
  IntProc = procedure(N: integer);
```

the following is an assignment-compatible procedure to write an integer:

```
procedure WriteInt(Number: integer);  
begin  
  Write(Number);  
end;
```

Nested procedures and function cannot be used with procedural variables. A procedure or function is nested when it is declared within another procedure or function. In the following example, *Inner* is nested within *Outer*, and *Inner* cannot therefore be assigned to a procedural variable.

```

program Nested;
procedure Outer;
procedure Inner;
begin
    Writeln('Inner is nested');
end;
begin
    Inner;
end;
begin
    Outer;
end.

```

The use of procedural types is not restricted to simple procedural variables. Like any other type, a procedural type can participate in the declaration of a structured type, as demonstrated by the following declarations:

```

type
    GotoProc = procedure (X,Y: integer);
    ProcList = array[1..10] of GotoProc;
    WindowPtr = ^WindowRec;
    WindowRec = record
        Next: WindowPtr;
        Header: string[31];
        Top,Left,Bottom,Right: integer;
        SetCursor: GotoProc;
    end;

var
    P: ProcList;
    W: WindowPtr;

```

Given the preceding declarations, the following statements are valid procedure calls:

```

P[3](1,1);
W^.SetCursor(10,10);

```

When a procedural value is assigned to a procedural variable, what physically takes place is that the address of the procedure is stored in the variable. In fact, a procedural variable is much like a pointer variable, except that instead of pointing to data, it points to a procedure or function. Like a pointer, a procedural variable occupies 4 bytes (two words), containing a memory address. The first word stores the offset part of the address, and the second word stores the segment part.

## Procedural Type Parameters

Since procedural types are allowed in any context, it is possible to declare procedures or functions that take procedures or functions as parameters.

The following program demonstrates the use of a procedural type parameter to output three tables of different arithmetic functions:

```

program Tables;

type
  Func = function(X,Y: integer): integer;

  {$F+}

function Add(X,Y: integer): integer;
begin
  Add := X + Y;
end;

function Multiply(X,Y: integer): integer;
begin
  Multiply := X * Y;
end;

function Funny(X,Y: integer): integer;
begin
  Funny := (X+Y) * (X-Y);
end;

  {$F-}

procedure PrintTable(W,H: integer; Operation: Func);
var
  X,Y: integer;
begin
  for Y := 1 to H do
  begin
    for X := 1 to W do Write(Operation(X,Y):5);
    Writeln;
  end;
  Writeln;
end;

begin
  PrintTable(10,10,Add);
  PrintTable(10,10,Multiply);
  PrintTable(10,10,Funny);
end.

```

When run, the *Tables* program outputs three tables. The second one looks like this:

1	2	3	4	5	6	7	8	9	10
2	4	6	8	10	12	14	16	18	20
3	6	9	12	15	18	21	24	27	30
4	8	12	16	20	24	28	32	36	40
5	10	15	20	25	30	35	40	45	50
6	12	18	24	30	36	42	48	54	60
7	14	21	28	35	42	49	56	63	70

8	16	24	32	40	48	56	64	72	80
9	18	27	36	45	54	63	72	81	90
10	20	30	40	50	60	70	80	90	100

Procedural type parameters are particularly useful in situations where a certain common action is to be carried out on a set of procedures or functions. In this case, the *PrintTable* procedure represents the common action to be carried out on the *Add*, *Multiply*, and *Funny* functions.

If a procedure or function is to be passed as a parameter, it must conform to the same type-compatibility rules as in an assignment. Thus, such procedures and functions must be compiled with *{F+}*, they cannot be built-in routines, they cannot be nested, and they cannot be declared with the *inline* or *interrupt* attributes.

## Procedural Types in Expressions

In general, the use of a procedural variable in a statement or an expression denotes a call of the procedure or function stored in the variable. There is however one exception: When Turbo Pascal sees a procedural variable on the left-hand side of an assignment statement, it knows that the right-hand side has to represent a procedural value. For example, consider the following program:

```
{F+}

type
  IntFunc = function: integer;

var
  F: IntFunc;
  N: integer;

function ReadInt: integer;
var
  I: integer;
begin
  Read(I);
  ReadInt := I;
end;

begin
  F := ReadInt;           { Assign procedural value }
  N := ReadInt;           { Assign function result }
end.
```

The first statement in the main program assigns the procedural value (address of) *ReadInt* to the procedural variable *F*, where the second statement calls *ReadInt*, and assigns the returned value to *N*. The distinction



between getting the procedural value or calling the function is made by the type of the variable being assigned (*F* or *N*).

Unfortunately, there are situations where the compiler cannot determine the desired action from the context. For example, in the following statement, there is no obvious way the compiler can know if it should compare the procedural value in *F* to the procedural value of *ReadInt*, to determine if *F* currently points to *ReadInt*, or whether it should call *F* and *ReadInt*, and then compare the returned values.

```
if F = ReadInt then WriteLn('Equal');
```

However, standard Pascal syntax specifies that the occurrence of a function identifier in an expression denotes a call to that function, so the effect of the preceding statement is to call *F* and *ReadInt*, and then compare the returned values. To compare the procedural value in *F* to the procedural value of *ReadInt*, the following construct must be used:

```
if @F = @ReadInt then Writeln('Equal');
```

When applied to a procedural variable or a procedure or function identifier, the address (@) operator prevents the compiler from calling the procedure, and at the same time converts the argument into a pointer. Thus, *@F* converts *F* into an untyped pointer variable that contains an address, and *@ReadInt* returns the address of *ReadInt*; the two pointer values can then be compared to determine if *F* currently refers to *ReadInt*.

**Note:** To get the memory address of a procedural variable, rather than the address stored in it, a double address (@@) operator must be used. For example, where *@P* means convert *P* into an untyped pointer variable, *@@P* means return the physical address of the variable *P*.

Turbo Pascal fully supports variable typecasts involving procedural types. For example, given the declarations

```
type
  Func = function(X: integer): integer;
var
  F: Func;
  P: Pointer;
  N: integer;
```

you can construct the following assignments:

<i>F</i> := <i>Func</i> ( <i>P</i> );	{ Assign procedural value in <i>P</i> to <i>F</i> }
<i>Func</i> ( <i>P</i> ) := <i>F</i> ;	{ Assign procedural value in <i>F</i> to <i>P</i> }
<i>@F</i> := <i>P</i> ;	{ Assign pointer value in <i>P</i> to <i>F</i> }
<i>P</i> := <i>@F</i> ;	{ Assign pointer value in <i>F</i> to <i>P</i> }
<i>N</i> := <i>F</i> ( <i>N</i> );	{ Call function via <i>F</i> }
<i>N</i> := <i>Func</i> ( <i>P</i> )( <i>N</i> );	{ Call function via <i>P</i> }


In particular, notice that the address operator (@), when applied to a procedural variable, can be used on the left-hand side of an assignment. Also, notice the typecast on the last line to call a function via a pointer variable.



# Programs and Units


## Program Syntax

A Turbo Pascal program takes the form of a procedure declaration except for its heading and an optional **uses** clause.



## The Program Heading


The program heading specifies the program's name and its parameters.



The program heading, if present, is purely decorative and is ignored by the compiler.

## The Uses Clause

The **uses** clause identifies all units used by the program, including units used directly and units used by those units.



The *System* unit is always used automatically. *System* implements all low-level, run-time support routines to support such features as file I/O, string handling, floating point, dynamic memory allocation, and others.

Apart from *System*, Turbo Pascal implements many standard units, such as *Printer*, *Dos*, and *Crt*. These are not used automatically; you must include them in your **uses** clause, for instance,

```
uses Dos,Crt;           { Can now access facilities in Dos and Crt }
```

The standard units are described in Chapter 12, "Standard Units."

To locate a unit specified in a **uses** clause, the compiler first checks the resident units—those units loaded into memory at startup from the TURBO.TPL file. If the unit is not among the resident units, the compiler assumes it must be on disk. The name of the file is assumed to be the unit name with extension .TPU. It is first searched for in the current directory, and then in the directories specified with the O/D/Unit Directories menu command or in a /U directive on the TPC command line. For instance, the construct


```
uses Memory;
```

where *Memory* is not a resident unit, causes the compiler to look for the file MEMORY.TPU in the current directory, and then in each of the unit directories.

When the Compile/Make and Compile/Build commands compile the units specified in a **uses** clause, the source files are searched for in the same way as the .TPU files, and the name of a given unit's source file is assumed to be the unit name with extension .PAS.

## Unit Syntax

Units are the basis of modular programming in Turbo Pascal. They are used to create libraries that you can include in various programs without making the source code available, and to divide large programs into logically related modules.



## The Unit Heading

---

The unit heading specifies the unit's name.




The unit name is used when referring to the unit in a **uses** clause. The name must be unique—two units with the same name cannot be used at the same time.

## The Interface Part

---

The interface part declares constants, types, variables, procedures, and functions that are *public*, that is, available to the host (the program or unit using the unit). The host can access these entities as if they were declared in a block that encloses the host.




Unless a procedure or function is **inline**, the interface part only lists the procedure or function heading. The block of the procedure or function follows in the implementation part.

## The Implementation Part

---

The implementation part defines the block of all public procedures and functions. In addition, it declares constants, types, variables, procedures, and functions that are *private*, that is, not available to the host.

implementation part




In effect, the procedure and function declarations in the interface part are like **forward** declarations, although the **forward** directive is not specified. Therefore, these procedures and functions can be defined and referenced in any sequence in the implementation part.

**Note:** Procedure and function headings can be duplicated from the interface part. You don't have to specify the formal parameter list, but if you do, the compiler will issue a compile-time error if the interface and implementation declarations don't match.

## *The Initialization Part*

The initialization part is the last part of a unit. It consists either of the reserved word **end** (in which case the unit has no initialization code) or of a statement part to be executed in order to initialize the unit.



The initialization parts of units used by a program are executed in the same order that the units appear in the **uses** clause.

## *Indirect Unit References*

The **uses** clause in a module (program or unit) need only name the units used directly by that module. Consider the following example:

```
program Prog;  
uses Unit2;
```

```

const a = b;
begin end.

unit Unit2;
interface
uses Unit1;
const b = c;
implementation
end.

unit Unit1;
interface
const c = 1;
implementation
const d = 2;
end.

```

In the above example, *Unit2* is directly dependent on *Unit1*, and *Prog* is directly dependent on *Unit2*. Furthermore, *Prog* is indirectly dependent on *Unit1* (through *Unit2*), even though none of the identifiers declared in *Unit1* are available to *Prog*.

In order to compile a module, Turbo Pascal must be able to locate all units upon which the module depends (directly or indirectly). So, to compile *Prog* above, the compiler must be able to locate both *Unit1* and *Unit2*, or else an error occurs.

When changes are made in the interface part of a unit, other units using the unit must be recompiled. However, if changes are only made to the implementation or the initialization part, other units that use the unit *need not* be recompiled. In the preceding example, if the interface part of *Unit1* is changed (for example,  $c = 2$ ) *Unit2* must be recompiled; changing the implementation part (for example,  $d = 1$ ) doesn't require recompilation of *Unit2*.

When a unit is compiled, Turbo Pascal computes a *unit version number*, which is basically a checksum of the interface part. In the preceding example, when *Unit2* is compiled, the current version number of *Unit1* is saved in the compiled version of *Unit2*. When *Prog* is compiled, the version number of *Unit1* is checked against the version number stored in *Unit2*. If the version numbers do not match, indicating that a change was made in the interface part of *Unit1* since *Unit2* was compiled, the compiler shows an error or recompiles *Unit2*, depending on the mode of compilation.

## Circular Unit References

---

Placing a **uses** clause in the implementation section of a unit allows you to further hide the inner details of the unit, since units used in the implemen-



tation section are not visible to users of the unit. More importantly, however, it also enables you to construct mutually dependent units.

The following program demonstrates how two units can “use” each other. The main program, *Circular*, uses a unit named *Display*. *Display* contains one routine in its interface section, *WriteXY*, which takes three parameters: an  $(x, y)$  coordinate pair and a text message to display. If the  $(x, y)$  coordinates are onscreen, *WriteXY* moves the cursor to  $(x, y)$  and displays the message there; otherwise, it calls a simple error-handling routine.

So far, there’s nothing fancy here—*WriteXY* is taking the place of *Write*. Here’s where the circular unit reference enters in: How is the error-handling routine going to display its error message? By using *WriteXY* again. Thus you have *WriteXY*, which calls the error-handling routine *ShowError*, which in turn calls *WriteXY* to put an error message onscreen. If your head is spinning in circles, let’s look at the source code to this example, so you can see that it’s really not that tricky.

The main program, *Circular*, clears the screen and makes three calls to *WriteXY*:

```
program Circular;
{ Display text using WriteXY }

uses
  Crt, Display;

begin
  ClrScr;
  WriteXY(1, 1, 'Upper left corner of screen');
  WriteXY(100, 100, 'Way off the screen');
  WriteXY(81 - Length('Back to reality'), 15, 'Back to reality');
end.
```

Look at the  $(x, y)$  coordinates of the second call to *WriteXY*. It’s hard to display text at (100, 100) on an 80x25 line screen. Next, let’s see how *WriteXY* works. Here’s the source to the *Display* unit, which contains the *WriteXY* procedure. If the  $(x, y)$  coordinates are valid, it displays the message; otherwise, *WriteXY* displays an error message:

```
unit Display;
{ Contains a simple video display routine }

interface

procedure WriteXY(X, Y : integer; Message : string);

implementation
uses
  Crt, Error;

procedure WriteXY(X, Y : integer; Message : string);
begin
```

```

    if (X in [1..80]) and (Y in [1..25]) then
    begin
        GoToXY(X, Y);
        Write(Message);
    end
    else
        ShowError('Invalid WriteXY coordinates');
    end;
end.

```

The *ShowError* procedure called by *WriteXY* is declared in the following code in the *Error* unit. *ShowError* always displays its error message on the 25th line of the screen:

```

unit Error;
{ Contains a simple error-reporting routine }

interface

procedure ShowError(ErrMsg : string);

implementation

uses
    Display;

procedure ShowError(ErrMsg : string);
begin
    WriteXY(1, 25, 'Error: ' + ErrMsg);
end;

end.

```

Notice that the **uses** clause in the **implementation** sections of both *Display* and *Error* refer to each other. These two units can refer to each other in their **implementation** sections because Turbo Pascal can compile complete **interface** sections for both. In other words, the Turbo Pascal compiler will accept a reference to partially compiled unit *A* in the **implementation** section of unit *B*, as long as both *A* and *B*'s **interface** sections do not depend upon each other (and thus follow Pascal's strict rules for declaration order).

## Sharing Other Declarations

What if you want to modify *WriteXY* and *ShowError* to take an additional parameter that specifies a rectangular window onscreen:

```

procedure WriteXY(SomeWindow : WindRec;
                  X, Y : integer;
                  Message : string);

procedure ShowError(SomeWindow : WindRec;
                   ErrMsg : string);

```

Remember these two procedures are in separate units. Even if you declared *WindData* in the **interface** of one, there would be no legal way to make that declaration available to the **interface** of the other. The solution is to declare a third module that contains only the definition of the window record:

```
unit WindData;
interface
type
  WinDRec = record
    X1, Y1, X2, Y2 : integer;
    ForeColor,
    BackColor      : byte;
    Active          : boolean;
  end;
implementation
end.
```

In addition to modifying the code to *WriteXY* and *ShowError* to make use of the new parameter, the **interface** sections of both the *Display* and *Error* units can now “use” *WindData*. This approach is legal because unit *WindData* has no dependencies in its **uses** clause, and units *Display* and *Error* refer to each other only in their respective **implementation** sections.

## Input and Output

This chapter briefly describes the standard (or built-in) input and output (I/O) procedures and functions of Turbo Pascal; for more detailed information, refer to Chapter 16.

### An Introduction to I/O

A Pascal file variable is any variable whose type is a file type. There are three classes of Pascal files: *typed*, *text*, and *untyped*. The syntax for writing file types is given in the section “Structured Types” in Chapter 3.

Before a file variable can be used, it must be associated with an external file through a call to the *Assign* procedure. An external file is typically a named disk file, but it can also be a device, such as the keyboard or the display. The external file stores the information written to the file or supplies the information read from the file.

Once the association with an external file is established, the file variable must be “opened” to prepare it for input and/or output. An existing file can be opened via the *Reset* procedure, and a new file can be created and opened via the *Rewrite* procedure. Text files opened with *Reset* are read-only, and text files opened with *Rewrite* and *Append* are write-only. Typed files and untyped files always allow both reading and writing regardless of whether they were opened with *Reset* or *Rewrite*.

The standard text-file variables *Input* and *Output* are opened automatically when program execution begins. *Input* is a read-only file associated with the keyboard and *Output* is a write-only file associated with the display.

Every file is a linear sequence of components, each of which has the component type (or record type) of the file. Each component has a component number. The first component of a file is considered to be component zero.

Files are normally accessed *sequentially*; that is, when a component is read using the standard procedure *Read* or written using the standard procedure *Write*, the current file position moves to the next numerically-ordered file component. However, typed files and untyped files can also be accessed randomly via the standard procedure *Seek*, which moves the current file position to a specified component. The standard functions *FilePos* and *FileSize* can be used to determine the current file position and the current file size.

When a program completes processing a file, the file must be closed using the standard procedure *Close*. After closing a file completely, its associated external file is updated. The file variable can then be associated with another external file.

By default, all calls to standard I/O procedures and functions are automatically checked for errors: If an error occurs, the program terminates, displaying a run-time error message. This automatic checking can be turned on and off using the *{I+}* and *{I-}* compiler directives. When I/O checking is off—that is, when a procedure or function call is compiled in the *{I-}* state—an I/O error does not cause the program to halt. To check the result of an I/O operation, you must instead call the standard function *IOResult*.

## Standard Procedures and Functions for All Files

---

Here's a summary of the procedures and functions you can use in all files.

### *Procedures*

<b>Assign</b>	Assigns the name of an external file to a file variable.
<b>ChDir</b>	Changes the current directory.
<b>Close</b>	Closes an open file.
<b>Erase</b>	Erases an external file.
<b>GetDir</b>	Returns the current directory of a specified drive.
<b>MkDir</b>	Creates a subdirectory.
<b>Rename</b>	Renames an external file.

<b>Reset</b>	Opens an existing file.
<b>Rewrite</b>	Creates and opens a new file.
<b>Rmdir</b>	Removes an empty subdirectory.

## **Functions**

<b>Eof</b>	Returns the end-of-file status of a file.
<b>IOResult</b>	Returns an integer value that is the status of the last I/O function performed.

# **Standard Procedures and Functions for Text Files**

---

This section summarizes input and output using file variables of the standard type *Text*. Note that in Turbo Pascal the type *Text* is distinct from the type *file* of *char*.

When a text file is opened, the external file is interpreted in a special way: It is considered to represent a sequence of characters formatted into lines, where each line is terminated by an end-of-line marker (a carriage-return character, possibly followed by a line-feed character).

For text files, there are special forms of *Read* and *Write* that allow you to read and write values that are not of type *char*. Such values are automatically translated to and from their character representation. For example, *Read(f,i)*, where *i* is a type integer variable, will read a sequence of digits, interpret that sequence as a decimal integer, and store it in *i*.

As noted previously there are two standard text-file variables, *Input* and *Output*. The standard file variable *Input* is a read-only file associated with the operating system's standard input file (typically the keyboard), and the standard file variable *Output* is a write-only file associated with the operating system's standard output file (typically the display). *Input* and *Output* are automatically opened before a program begins execution, as if the following statements were executed:

```
Assign(Input,''); Reset(Input);
Assign(Output,''); Rewrite(Output);
```

Likewise, *Input* and *Output* are automatically closed after a program finishes executing.

**Note:** If a program uses the *Crt* standard unit, *Input* and *Output* will no longer by default refer to the standard input and standard output files. (For

further details, refer to the description of the *Crt* unit in Chapter 12, "Standard Units").

Some of the standard procedures and functions listed in this section need not have a file variable explicitly given as a parameter. If the file parameter is omitted, *Input* or *Output* will be assumed by default, depending on whether the procedure or function is input- or output-oriented. For instance, *Read(x)* corresponds to *Read(Input,x)* and *Write(x)* corresponds to *Write(Output,x)*.

If you do specify a file when calling one of the procedures or functions in this section, the file must have been associated with an external file using *Assign*, and opened using *Reset*, *Rewrite*, or *Append*. An error message is generated if you pass a file that was opened with *Reset* to an output-oriented procedure or function. Likewise, it's an error to pass a file that was opened with *Rewrite* or *Append* to an input-oriented procedure or function.

### ***Procedures***

<b>Append</b>	Opens an existing file for appending.
<b>Flush</b>	Flushes the buffer of an output file.
<b>Read</b>	Reads one or more values from a text file into one or more variables.
<b>Readln</b>	Does what a <i>Read</i> does and then skips to the beginning of the next line in the file.
<b>SetTextBuf</b>	Assigns an I/O buffer to a text file.
<b>Write</b>	Writes one or more values to a text file.
<b>Writeln</b>	Does the same as a <i>Write</i> , and then writes an end-of-line marker to the file.

### ***Functions***

<b>Eoln</b>	Returns the end-of-line status of a file.
<b>SeekEof</b>	Returns the end-of-file status of a file.
<b>SeekEoln</b>	Returns the end-of-line status of a file.

# Standard Procedures and Functions for Untyped Files

---

Untyped files are low-level I/O channels primarily used for direct access to any disk file regardless of type and structuring. An untyped file is declared with the word *file* and nothing more, for example:

```
var  
DataFile: file;
```

For untyped files, the *Reset* and *Rewrite* procedures allow an extra parameter to specify the record size used in data transfers.

For historical reasons, the default record size is 128 bytes. The preferred record size is 1, because that is the only value that correctly reflects the exact size of any file (no partial records are possible when the record size is 1).

Except for *Read* and *Write*, all typed file standard procedures and functions are also allowed on untyped files. Instead of *Read* and *Write*, two procedures called *BlockRead* and *BlockWrite* are used for high-speed data transfers.

**BlockRead** Reads one or more records into a variable.

**BlockWrite** Writes one or more records from a variable.

With the exception of text files, the following procedures and functions may be used on a file variable of any type:

**FilePos** Returns the current file position of a file.

**FileSize** Returns the current size of a file.

**Seek** Moves the current position of a file to a specified component.

**Truncate** Truncates the file size at the current file position.

## The FileMode Variable

---

The *FileMode* variable defined by the *System* unit determines the access code to pass to DOS when typed and untyped files (not text files) are opened using the *Reset* procedure.

The default *FileMode* is 2, which allows both reading and writing. Assigning another value to *FileMode* causes all subsequent *Resets* to use that mode.



The range of valid *FileMode* values depends on the version of DOS in use. However, for all versions, the following modes are defined:

- 0: Read only
- 1: Write only
- 2: Read/Write

DOS version 3.x defines additional modes, which are primarily concerned with file-sharing on networks. (For further details on these, please refer to your DOS Programmer's reference manual.)

**Note:** New files created using *Rewrite* are always opened in Read/Write mode, corresponding to *FileMode* = 2.

## Devices in Turbo Pascal

---

Turbo Pascal and the DOS operating system regard external hardware, such as the keyboard, the display, and the printer, as *devices*. From the programmer's point of view, a device is treated as a file, and is operated on through the same standard procedures and functions as files.

Turbo Pascal supports two kinds of devices: DOS devices and text file devices.

### *DOS Devices*

---

DOS devices are implemented through reserved file names that have a special meaning attached to them. DOS devices are completely transparent—in fact, Turbo Pascal is not even aware when a file variable refers to a device instead of a disk file. For example, the program

```
var
  Lst: Text;
begin
  Assign(Lst, 'LPT1'); Rewrite(Lst);
  Writeln(Lst, 'Hello World...');
  Close(Lst);
end.
```

will write the string *Hello World...* on the printer, even though the syntax for doing so is exactly the same as for a disk file.

The devices implemented by DOS are used for obtaining or presenting legible input or output. Therefore, DOS devices are normally used only in connection with text files. On rare occasions, untyped files can also be useful for interfacing with DOS devices.

Each of the DOS devices is described in the next section. Other DOS implementations can provide additional devices, and still others cannot provide all the ones described here.

## The CON Device

CON refers to the CONsole device, in which output is sent to the display, and input is obtained from the keyboard. The *Input* and *Output* standard files and all files assigned an empty name refer to the CON device when input and/or output is not redirected.

Input from the CON device is line-oriented and uses the line-editing facilities described in the DOS manual. Characters are read from a line buffer, and when the buffer becomes empty, a new line is input.

An end-of-file character is generated by pressing *Ctrl-Z*, after which the *Eof* function will return True.

## The LPT1, LPT2, and LPT3 Devices

The line printer devices are the three possible printers you can use. If only one printer is connected, it is usually referred to as LPT1, for which the synonym PRN can also be used.

The line printer devices are output-only devices—an attempt to *Reset* a file assigned to one of these generates an immediate end-of-file.

**Note:** The standard unit *Printer* declares a text-file variable called *Lst*, and makes it refer to the LPT1 device. To easily write something on the printer from one of your programs, include *Printer* in the program's *uses* clause, and use *Write(Lst,...)* and *Writeln(Lst,...)* to produce your output.

## The COM1 and COM2 Devices

The communication port devices are the two serial communication ports. The synonym AUX can be used instead of COM1.

## The NUL Device

The null device ignores anything written to it, and generates an immediate end-of-file when read from. You should use this when you don't want to create a particular file, but the program requires an input or output file name.

## *Text File Devices*

---

Text file devices are used to implement devices unsupported by DOS or to make available another set of features other than those provided by a similar DOS device. A good example of a text file device is the CRT device implemented by the *Crt* standard unit. Its main function is to provide an interface to the display and the keyboard, just like the CON device in DOS. However, the CRT device is much faster and supports such invaluable features as color and windows (for further details on the CRT device, see Chapter 12, "Standard Units").

Contrary to DOS devices, text file devices have no reserved file names; in fact, they have no file names at all. Instead, a file is associated with a text file device through a customized *Assign* procedure. For instance, the *Crt* standard unit implements an *AssignCrt* procedure that associates text files with the CRT device.

In addition to the CRT device, Turbo Pascal allows you to write your own text file device drivers. A full description of this is given in the section "Text File Device Drivers" on page 210 of Chapter 15, "Inside Turbo Pascal."

## Standard Procedures and Functions

This chapter briefly describes all the standard (built-in) procedures and functions in Turbo Pascal, except for the I/O procedures and functions discussed in Chapter 10, "Input and Output." Additional procedures and functions are provided by the standard units described in Chapter 12, "Standard Units." For more detailed information, refer to Chapter 16, "Turbo Pascal Reference Lookup."

Standard procedures and functions are predeclared. Since all predeclared entities act as if they were declared in a block surrounding the program, no conflict arises from a declaration that redefines the same identifier within the program.

### Flow Control Procedures

---

- Exit** Exits immediately from the current block.
- Halt** Stops program execution and returns to the operating system.
- RunError** Stops program execution and generates a run-time error.

### Dynamic Allocation Procedures and Functions

---

These procedures and functions are used to manage the heap—a memory area that occupies all or some of the free memory left when a program is executed. A complete discussion of the techniques used to manage the heap

is given in the section "The Heap Manager" on page 181 of Chapter 15, "Inside Turbo Pascal."

### ***Procedures***

<b>Dispose</b>	Disposes a dynamic variable.
<b>FreeMem</b>	Disposes a dynamic variable of a given size.
<b>GetMem</b>	Creates a new dynamic variable of a given size and sets a pointer variable to point to it.
<b>Mark</b>	Records the state of the heap in a pointer variable.
<b>New</b>	Creates a new dynamic variable and sets a pointer variable to point to it.
<b>Release</b>	Returns the heap to a given state.

### ***Functions***

<b>MaxAvail</b>	Returns the size of the largest contiguous free block in the heap, corresponding to the size of the largest dynamic variable that can be allocated at the time of the call to <i>MaxAvail</i> .
<b>MemAvail</b>	Returns the number of free bytes of heap storage available.

## **Transfer Functions**

---

The procedures *Pack* and *Unpack*, as defined in standard Pascal, are not implemented by Turbo Pascal.

<b>Chr</b>	Returns a character of a specified ordinal number.
<b>Ord</b>	Returns the ordinal number of an ordinal-type value.
<b>Round</b>	Rounds a type real value to a type longint value.
<b>Trunc</b>	Truncates a type real value to a type longint value.

## **Arithmetic Functions**

---

**Note:** When compiling in numeric processing mode,  $\{\$N+\}$ , the return values of the floating-point routines in the *System* unit (*Sqrt*, *Pi*, *Sin*, and so on) are of type extended instead of real:

```
 $\{\$N+\}$   
begin
```

```

        Writeln(Pi);                                { 3.14159265358979E+0000 }
    end.
    {$N-}
    begin
        Writeln(Pi)                                { 3.1415926536E+00 }
    end.

```

**Abs** Returns the absolute value of the argument.

**ArcTan** Returns the arctangent of the argument.

**Cos** Returns the cosine of the argument.

**Exp** Returns the exponential of the argument.

**Frac** Returns the fractional part of the argument.

**Int** Returns the integer part of the argument.

**Ln** Returns the natural logarithm of the argument.

**Pi** Returns the value of *Pi* (3.1415926535897932385).

**Sin** Returns the sine of the argument.

**Sqr** Returns the square of the argument.

**Sqrt** Returns the square root of the argument.

## Ordinal Procedures and Functions

---

### *Procedures*

**Dec** Decrements a variable.

**Inc** Increments a variable.

### *Functions*

**Odd** Tests if the argument is an odd number.

**Pred** Returns the predecessor of the argument.

**Succ** Returns the successor of the argument.

## String Procedures and Functions

---

### *Procedures*

- Delete**     Deletes a substring from a string.
- Insert**     Inserts a substring into a string.
- Str**         Converts a numeric value to its string representation.
- Val**         Converts the string value to its numeric representation.

### *Functions*

- Concat**     Concatenates a sequence of strings.
- Copy**        Returns a substring of a string.
- Length**     Returns the dynamic length of a string.
- Pos**         Searches for a substring in a string.

## Pointer and Address Functions

---

- Addr**        Returns the address of a specified object.
- CSeg**        Returns the current value of the CS register.
- DSeg**        Returns the current value of the DS register.
- Ofs**         Returns the offset of a specified object.
- Ptr**         Converts a segment base and an offset address to a pointer-type value.
- Seg**         Returns the segment of a specified object.
- SPtr**        Returns the current value of the SP register.
- SSeg**        Returns the current value of the SS register.

## Miscellaneous Procedures and Functions

---

### *Procedures*

- FillChar**     Fills a specified number of contiguous bytes with a specified value.

<b>Move</b>	Copies a specified number of contiguous bytes from a source range to a destination range.
<b>Randomize</b>	Initializes the built-in random generator with a random value.

### ***Functions***

<b>Hi</b>	Returns the high-order byte of the argument.
<b>Lo</b>	Returns the low-order byte of the argument.
<b>ParamCount</b>	Returns the number of parameters passed to the program on the command line.
<b>ParamStr</b>	Returns a specified command-line parameter.
<b>Random</b>	Returns a random number.
<b>SizeOf</b>	Returns the number of bytes occupied by the argument.
<b>Swap</b>	Swaps the high- and low-order bytes of the argument.
<b>UpCase</b>	Converts a character to uppercase.





## Standard Units

Chapter 11, "Standard Procedures and Functions," describes all the built-in procedures and functions of Turbo Pascal, which can be referred to without explicitly requesting them (as standard Pascal specifies). It's through Turbo Pascal's standard units, though, that you'll get the most programming power (see Chapter 16, "Turbo Pascal Reference Lookup," for more information).

Standard units are no different from the units you can write yourself. The following eight standard units are available to you:

- Crt** Exploits the full power of your PC's display and keyboard, including screen mode control, extended keyboard codes, color, windows, and sound.
- Dos** Supports numerous DOS functions, including date-and-time control, directory search, and program execution.
- Graph** A powerful graphics package with device-independent graphics support for CGA, EGA, VGA, HERC, IBM 3270 PC, MCGA, AT&T 6300, and IBM 8514.
- Graph3** Implements Turbo Pascal 3.0 Turtlegraphics.
- Overlay** Implements 5.0's powerful overlay manager (refer to Chapter 13, "Overlays").
- Printer** Allows you to easily access your printer.
- System** Turbo Pascal's run-time library. This unit is automatically used by any unit or program.
- Turbo3** Provides an even higher degree of compatibility with Turbo Pascal 3.0.

To use one of the standard units, simply include its name in your `uses` clause, for instance:

```
uses Dos, Crt, Graph;
```

The standard units usually all reside in the TURBO.TPL library, which is automatically loaded when you start up Turbo Pascal. To save memory, you can move seldom-used units, such as *Turbo3* and *Graph3*, out of the TURBO.TPL file by using the TPUMOVER utility.

## Standard Unit Dependencies

Both the compatibility units, *Turbo3* and *Graph3*, depend on facilities made available by the *Crt* unit. So, when using *Turbo3* and *Graph3*, you must first specify *Crt* in your `uses` clause. Table 12.1 lists the standard units.

Table 12.1: Standard Units

Unit	Uses
Crt	None
Dos	None
Graph	None
Graph3	Crt
Overlay	None
Printer	None
System	None
Turbo3	Crt

We purposefully didn't indicate in the table that all units use the *System* unit; that's because *System* is always used implicitly, and need never be specified in a `uses` clause.

## The System Unit

The *System* unit is, in fact, Turbo Pascal's run-time library. It implements low-level, run-time support routines for all built-in features, such as file I/O, string handling, 8087 emulation, floating point, overlay management, and dynamic memory allocation. The *System* unit is used automatically by any unit or program, and need never be referred to in a `uses` clause.

The procedures and functions provided by *System* are described in Chapters 10, "Input and Output," and 11, "Standard Procedures and Functions." A number of predeclared variables are also available, including:

```

const
    OvrCodeList: word = 0;           { Overlay code segment list }
    OvrHeapSize: word = 0;           { Initial overlay buffer size }
    OvrDebugPtr: pointer = nil;      { Overlay debugger hook }
    OvrHeapOrg: word = 0;            { Overlay buffer origin }
    OvrHeapPtr: word = 0;            { Overlay buffer pointer }
    OvrHeapEnd: word = 0;            { Overlay buffer end }
    OvrLoadList: word = 0;           { Loaded overlays list }
    OvrDosHandle: word = 0;          { Overlay DOS handle }
    OvrEmsHandle: word = 0;          { Overlay EMS handle }
    HeapOrg: pointer = nil;          { Heap origin }
    HeapPtr: pointer = nil;          { Heap pointer }
    FreePtr: pointer = nil;          { Free list pointer }
    FreeMin: word = 0;               { Minimum free list size }
    HeapError: pointer = nil;        { Heap error function }
    ExitProc: pointer = nil;         { Exit procedure }
    ExitCode: integer = 0;           { Exit code }
    ErrorAddr: pointer = nil;        { Run-time error address }
    PrefixSeg: word = 0;             { Program segment prefix }
    StackLimit: word = 0;            { Minimum stack pointer }
    InOutRes: integer = 0;           { I/O result buffer }
    RandSeed: longint = 0;           { Random seed }
    FileMode: byte = 2;              { File open mode }
    Test8087: byte = 0;              { 8087 test result }

var
    Input: text;                     { Input standard file }
    Output: text;                     { Output standard file }
    SaveInt00: pointer;               { Saved interrupt $00 }
    SaveInt02: pointer;               { Saved interrupt $02 }
    SaveInt1B: pointer;               { Saved interrupt $1B }
    SaveInt23: pointer;               { Saved interrupt $23 }
    SaveInt24: pointer;               { Saved interrupt $24 }
    SaveInt34: pointer;               { Saved interrupt $34 }
    SaveInt35: pointer;               { Saved interrupt $35 }
    SaveInt36: pointer;               { Saved interrupt $36 }
    SaveInt37: pointer;               { Saved interrupt $37 }
    SaveInt38: pointer;               { Saved interrupt $38 }
    SaveInt39: pointer;               { Saved interrupt $39 }
    SaveInt3A: pointer;               { Saved interrupt $3A }
    SaveInt3B: pointer;               { Saved interrupt $3B }
    SaveInt3C: pointer;               { Saved interrupt $3C }
    SaveInt3D: pointer;               { Saved interrupt $3D }
    SaveInt3E: pointer;               { Saved interrupt $3E }
    SaveInt3F: pointer;               { Saved interrupt $3F }
    SaveInt75: pointer;               { Saved interrupt $75 }

```

The *Overlay* unit uses *OvrCodeList*, *OvrHeapSize*, *OvrDebugPtr*, *OvrHeapOrg*, *OvrHeapPtr*, *OvrHeapEnd*, *OvrLoadList*, *OvrDosHandle*, and *OvrEmsHandle* to implement Turbo Pascal's overlay manager. The overlay buffer resides between the stack segment and the heap, and *OvrHeapOrg* and *OvrHeapEnd*

contain its starting and ending segment addresses. The default size of the overlay buffer corresponds to the size of the largest overlay in the program; if the program has no overlays, the size of the overlay buffer is zero. The size of the overlay buffer can be increased through a call to the *OvrSetBuf* routine in the *Overlay* unit; in that case, the size of the heap is decreased accordingly, by moving *HeapOrg* upwards.

The heap manager uses *HeapOrg*, *HeapPtr*, *FreePtr*, *FreeMin*, and *HeapError* to implement Turbo Pascal's dynamic memory allocation routines. The heap manager is described in full in Chapter 15, "Inside Turbo Pascal."

The *ExitProc*, *ExitCode*, and *ErrorAddr* variables implement exit procedures. This is also described in Chapter 15, "Inside Turbo Pascal."

*PrefixSeg* is a word variable containing the segment address of the Program Segment Prefix (PSP) created by DOS when the program was executed. For a complete description of the PSP, refer to your DOS manual.

*StackLimit* contains the offset of the bottom of the stack in the stack segment, corresponding to the lowest value the SP register is allowed to assume before it is considered a stack overflow. By default, *StackLimit* is zero, but in a program compiled with  $\{ \$N+, E+ \}$ , the 8087 emulator will set it to 224 to reserve workspace at the bottom of the stack segment if no 8087 is present in the system.

The built-in I/O routines use *InOutRes* to store the value that the next call to the *IOResult* standard function will return.

*RandSeed* stores the built-in random number generator's seed. By assigning a specific value to *RandSeed*, the *Random* function can be made to generate a specific sequence of random numbers over and over. This is useful in applications that deal with data encryption, statistics, and simulations.

The *FileMode* variable allows you to change the access mode in which typed and untyped files are opened (by the *Reset* standard procedure). For further details, refer to Chapter 10, "Input and Output."

*Test8087* stores the result of the coprocessor autodetection logic, which is executed at startup in a program compiled with  $\{ \$N+ \}$ . For further details, refer to Chapter 14, "Using the 8087."

*Input* and *Output* are the standard I/O files required by every Pascal implementation. By default, they refer to the standard input and output files in DOS. For further details, refer to Chapter 10, "Input and Output."

The *System* unit takes over several interrupt vectors. Before installing its own interrupt handling routines, *System* stores the old vectors in the *SaveIntXX* variables.

Note that the *System* unit contains an INT 24 handler for trapping critical errors. In a Turbo Pascal program, a DOS critical error is treated like any

other I/O error: In the  $\{I+\}$  state, the program halts with a run-time error, and, in the  $\{I-\}$  state, *IOResult* returns a nonzero value.

Here's a skeleton program that restores the original vector, and thereby the original critical error-handling logic:

```
program Restore;
uses Dos;
begin
  SetIntVec($24, SaveInt24);
  ...
end.
```

The *SwapVectors* routine in the *Dos* unit swaps the contents of the *SaveIntXX* variables with the current contents of the interrupt vectors. *SwapVectors* should be called just before and just after a call to the *Exec* routine, to ensure that the *Exec*'d process does not use any interrupt handlers installed by the current process, and vice versa. For more information, refer to page 384 for the entry on *SwapVectors* in Chapter 16 of the *Reference Guide*, "Turbo Pascal Reference Lookup."

## The Printer Unit

---

The *Printer* unit is a very small unit designed to make life easier when you're using the printer from within a program. *Printer* declares a text file called *Lst*, and associates it with the LPT1 device. Using *Printer* saves you the trouble of declaring, assigning, opening, and closing a text file yourself. Here's an example of a short program using *Printer*:

```
program HelloPrinter;
uses Printer;
begin
  Writeln(Lst, 'Hello Printer...');
end.
```

## The Dos Unit

---

The *Dos* unit implements a number of very useful operating system and file-handling routines. None of the routines in the *Dos* unit are defined by standard Pascal, so they have been placed in their own module.

For a complete description of DOS operations, refer to the *IBM DOS Technical Manual*.

## Constants, Types, and Variables

---

Each of the constants, types, and variables defined by the *Dos* unit are briefly discussed in this section. For more detailed information, see the descriptions of the procedures and functions that depend on these objects in Chapter 16, "Turbo Pascal Reference Lookup."

### Flags Constants

The following constants test individual flag bits in the Flags register after a call to *Intr* or *MsDos*:

```
const
  FCarry    = $0001;
  FParity   = $0004;
  FAuxiliary = $0010;
  FZero     = $0040;
  FSign     = $0080;
  FOverflow = $0800;
```

For instance, if *R* is a register's record, the tests

```
R.Flags and FCarry <> 0
R.Flags and FZero = 0
```

are True respectively if the Carry flag is set and if the Zero flag is clear.

### File Mode Constants

The file-handling procedures use these constants when opening and closing disk files. The mode fields of Turbo Pascal's file variables will contain one of the values specified below.

```
const
  fmClosed = $D7B0;
  fmInput  = $D7B1;
  fmOutput = $D7B2;
  fmInOut  = $D7B3;
```

### File Record Types

The record definitions used internally by Turbo Pascal are also declared in the *Dos* unit. *FileRec* is used for both typed and untyped files, while *TextRec* is the internal format of a variable of type text.

```

type
{ Typed and untyped files }
  FileRec = record
    Handle: word;
    Mode: word;
    RecSize: word;
    Private: array[1..26] of byte;
    UserData: array[1..16] of byte;
    Name: array[0..79] of char;
  end;

{ Textfile record }
  TextBuf = array[0..127] of char;
  TextRec = record
    Handle      : word;
    Mode        : word;
    BufSize     : word;
    Private     : word;
    BufPos      : word;
    BufEnd      : word;
    BufPtr      : ^TextBuf;
    OpenFunc    : pointer;
    InOutFunc   : pointer;
    FlushFunc   : pointer;
    CloseFunc   : pointer;
    UserData    : array[1..16] of byte;
    Name        : array[0..79] of char;
    Buffer       : TextBuf;
  end;

```

## File Attribute Constants

These constants test, set, and clear file attribute bits in connection with the *GetFAttr*, *SetFAttr*, *FindFirst*, and *FindNext* procedures:

```

const
  ReadOnly  = $01;
  Hidden    = $02;
  SysFile   = $04;
  VolumeID  = $08;
  Directory = $10;
  Archive   = $20;
  AnyFile   = $3F;

```

The constants are additive, that is, the statement

```
FindFirst('*.*', ReadOnly + Directory, S);
```



will locate all normal files as well as read-only files and subdirectories in the current directory. The *AnyFile* constant is simply the sum of all attributes.

## The Registers Type

The *Intr* and *MsDos* procedures use variables of type *Registers* to specify the input register contents and examine the output register contents of a software interrupt.

```
type
  Registers = record
    case integer of
      0: (AX, BX, CX, DX, BP, SI, DI, DS, ES, Flags: word);
      1: (AL, AH, BL, BH, CL, CH, DL, DH: byte);
    end;
```

Notice the use of a variant record to map the 8-bit registers on top of their 16-bit equivalents.

## The DateTime Type

Variables of *DateTime* type are used in connection with the *UnpackTime* and *PackTime* procedures to examine and construct 4-byte, packed date-and-time values for the *GetFTime*, *SetFTime*, *FindFirst*, and *FindNext* procedures.

```
type
  DateTime = record
    Year, Month, Day, Hour, Min, Sec: word;
  end;
```

Valid ranges are *Year* 1980..2099, *Month* 1..12, *Day* 1..31, *Hour* 0..23, *Min* 0..59, and *Sec* 0..59.

## The SearchRec Type

The *FindFirst* and *FindNext* procedures use variables of type *SearchRec* to scan directories.

```
type
  SearchRec = record
    Fill: array[1..21] of byte;
    Attr: byte;
    Time: longint;
    Size: longint;
```

```

        Name: string[12];
    end;

```

The information for each file found by one of these procedures is reported back in a *SearchRec*. The *Attr* field contains the file's attributes (constructed from file attribute constants), *Time* contains its packed date and time (use *UnpackTime* to unpack), *Size* contains its size in bytes, and *Name* contains its name. The *Fill* field is reserved by DOS and should never be modified.

## The File-Handling String Types

These string types are defined by the *Dos* unit to handle file names and paths in connection with the string procedure *FSplit*:

```

ComStr  = string[127];           { Command-line string }
PathStr  = string[79];           { Full file path string }
DirStr   = string[67];           { Drive and directory string }
NameStr  = string[8];            { File-name string }
ExtStr   = string[4];            { File-extension string }

```

## The DosError Variable

*DosError* is used by many of the routines in the *Dos* unit to report errors.

```
var DosError: integer;
```

The values stored in *DosError* are DOS error codes. A value of 0 indicates no error; other possible error codes include:

```

2 = File not found
3 = Path not found
5 = Access denied
6 = Invalid handle
8 = Not enough memory
10 = Invalid environment
11 = Invalid format
18 = No more files

```

## Interrupt Support Procedures

---

Here's a brief listing of the interrupt support procedures:

<b>GetIntVec</b>	Returns the address stored in a specified interrupt vector.
<b>Intr</b>	Executes a specified software interrupt.

<b>MsDos</b>	Executes a DOS function call.
<b>SetIntVec</b>	Sets a specified interrupt vector to a specified address.

## ***Date and Time Procedures***

---

<b>GetDate</b>	Returns the current date set in the operating system.
<b>GetFTime</b>	Returns the date and time a file was last written.
<b>GetTime</b>	Returns the current time set in the operating system.
<b>PackTime</b>	Converts a <i>DateTime</i> record into a 4-byte, packed date-and-time character longint used by <i>SetFTime</i> . The fields of the <i>DateTime</i> record are not range-checked.
<b>SetDate</b>	Sets the current date in the operating system.
<b>SetFTime</b>	Sets the date and time a file was last written.
<b>SetTime</b>	Sets the current time in the operating system.
<b>UnpackTime</b>	Converts a 4-byte, packed date-and-time character longint returned by <i>GetFTime</i> , <i>FindFirst</i> , or <i>FindNext</i> into an unpacked <i>DateTime</i> record.

## ***Disk Status Functions***

---

<b>DiskFree</b>	Returns the number of free bytes of a specified disk drive.
<b>DiskSize</b>	Returns the total size in bytes of a specified disk drive.

## ***File-Handling Procedures and Functions***

---

### ***Procedures***

<b>FindFirst</b>	Searches the specified (or current) directory for the first entry matching the specified file name and set of attributes.
<b>FindNext</b>	Returns the next entry that matches the name and attributes specified in a previous call to <i>FindFirst</i> .
<b>FSplit</b>	Splits a file name into its three component parts (directory, file name, and extension).

<b>GetFAttr</b>	Returns the attributes of a file.
<b>SetFAttr</b>	Sets the attributes of a file.

### ***Functions***

<b>FExpand</b>	Takes a file name and returns a fully qualified file name (drive, directory, and extension).
<b>FSearch</b>	Searches for a file in a list of directories.

## ***Process-Handling Procedures and Functions***

---

### ***Procedures***

<b>Exec</b>	Executes a specified program with a specified command line.
<b>Keep</b>	<i>Keep</i> (or <i>Terminate Stay Resident</i> ) terminates the program and makes it stay in memory.
<b>SwapVectors</b>	Swaps all saved interrupt vectors with the current vectors.

### ***Functions***

<b>DosExitCode</b>	Returns the exit code of a subprocess.
--------------------	--

## ***Environment-Handling Functions***

---

<b>EnvCount</b>	Returns the number of strings contained in the DOS environment.
<b>EnvStr</b>	Returns a specified environment string.
<b>GetEnv</b>	Returns the value of a specified environment variable.

## ***Miscellaneous Procedures and Function***

---

### ***Procedures***

<b>GetCBreak</b>	Returns the state of <i>Ctrl-Break</i> checking in DOS.
------------------	---

<b>GetVerify</b>	Returns the state of the verify flag in DOS.
<b>SetCBreak</b>	Sets the state of <i>Ctrl-Break</i> checking in DOS.
<b>SetVerify</b>	Sets the state of the verify flag in DOS.

## ***Function***

<b>DosVersion</b>	Returns the DOS version number.
-------------------	---------------------------------

# **The Crt Unit**

---

The *Crt* unit implements a range of powerful routines that give you full control of your PC's features, such as screen mode control, extended keyboard codes, colors, windows, and sound. *Crt* can only be used in programs that run on IBM PCs, ATs, PS/2s, and true compatibles.

One of the major advantages to using *Crt* is the added speed and flexibility of screen output operations. Programs that do not use the *Crt* unit send their screen output through DOS, which adds a lot of overhead. With the *Crt* unit, output is sent directly to the BIOS or, for even faster operation, directly to video memory.

## ***The Input and Output Files***

---

The initialization code of the *Crt* unit assigns the *Input* and *Output* standard text files to refer to the CRT instead of to DOS's standard input and output files. This corresponds to the following statements being executed at the beginning of a program:

```
AssignCrt(Input); Reset(Input);
AssignCrt(Output); Rewrite(Output);
```

This means that I/O redirection of the *Input* and *Output* files is no longer possible unless these files are explicitly assigned back to standard input and output by executing

```
Assign(Input, ''); Reset(Input);
Assign(Output, ''); Rewrite(Output);
```

## ***Windows***

---

*Crt* supports a simple yet powerful form of windows. The *Window* procedure lets you define a window anywhere on the screen. When you write in

such a window, the window behaves exactly as if you were using the entire screen, leaving the rest of the screen untouched. In other words, the screen outside the window is not accessible. Inside the window, lines can be inserted and deleted, the cursor wraps around at the right edge, and the text scrolls when the cursor reaches the bottom line.

All screen coordinates, except the ones used to define a window, are relative to the current window, and screen coordinates (1,1) correspond to the upper left corner of the screen.

The default window is the entire screen.

Turbo Pascal also supports screen modes for EGA (43 line) and VGA (50 line) (see the *TextMode* description in Chapter 16).

## Special Characters

When writing to *Output* or to a file that has been assigned to the CRT, the following control characters have special meanings:

- #7 Bell—emits a beep from the internal speaker.
- #8 Backspace—moves the cursor left one character. If the cursor is already at the left edge of the current window, nothing happens.
- #10 Line feed—moves the cursor one line down. If the cursor is already at the bottom of the current window, the window scrolls up one line.
- #13 Carriage return—returns the cursor to the left edge of the current window.

All other characters will appear on the screen when written.

## Line Input

When reading from *Input* or from a text file that has been assigned to *Crt*, text is input one line at a time. The line is stored in the text file's internal buffer, and when variables are read, this buffer is used as the input source. Whenever the buffer has been emptied, a new line is input.

When entering lines, the following editing keys are available:

- |                  |  |
|------------------|--|
| <i>BackSpace</i> | Deletes the last character entered.  |
| <i>Esc</i>       | Deletes the entire input line.   |
| <i>Enter</i>     | Terminates the input line and stores the end-of-line marker (carriage return/line feed) in the buffer. |

<i>Ctrl-S</i>	Same as <i>BackSpace</i>
<i>Ctrl-D</i>	Recalls one character from the last input line.
<i>Ctrl-A</i>	Same as <i>Esc</i> .
<i>Ctrl-F</i>	Recalls the last input line.
<i>Ctrl-Z</i>	Terminates the input line and generates an end-of-file marker.

*Ctrl-Z* will only generate an end-of-file marker if the *CheckEOF* variable has been set to True; it is False by default.

To test keyboard status and input single characters under program control, use the *KeyPressed* and *ReadKey* functions.

## *Constants, Types, and Variables*

---

Each of the constants, types, and variables defined by the *Crt* unit are briefly discussed in this section.

### **Crt Mode Constants**

The following constants are used as parameters to the *TextMode* procedure:

```
const
  BW40 = 0;           { 40x25 B/W on color adapter }
  BW80 = 2;           { 80x25 B/W on color adapter }
  Mono = 7;           { 80x25 B/W on monochrome adapter }
  C040 = 1;           { 40x25 color on color adapter }
  C080 = 3;           { 80x25 color on color adapter }
  Font8x8 = 256;      { For EGA/VGA 43 and 50 line }
  C40 = C040;         { For 3.0 compatibility }
  C80 = C080;         { For 3.0 compatibility }
```

*BW40*, *C040*, *BW80*, and *C080* represent the four color text modes supported by the IBM PC Color/Graphics Adapter (CGA). The *Mono* constant represents the single black-and-white text mode supported by the IBM PC Monochrome Adapter. *Font8x8* represents EGA/VGA 43- and 50-line modes. The *C40* and *C80* constants are for 3.0 compatibility. *LastMode* returns to the last active text mode after using graphics.

### **Text Color Constants**

The following constants are used in connection with the *TextColor* and *TextBackground* procedures:

**const**

```
Black      = 0;
Blue       = 1;
Green      = 2;
Cyan       = 3;
Red        = 4;
Magenta    = 5;
Brown      = 6;
LightGray  = 7;
DarkGray   = 8;
LightBlue  = 9;
LightGreen = 10;
LightCyan  = 11;
LightRed   = 12;
LightMagenta = 13;
Yellow     = 14;
White      = 15;
Blink      = 128;
```

Colors are represented by the numbers between 0 and 15; to easily identify each color, you can use these constants instead of numbers. In the color text modes, the foreground of each character is selectable from 16 colors, and the background from 8 colors. The foreground of each character can also be made to blink.

## Crt Variables

Here are the variables in *Crt*:

**var**

```
CheckBreak : boolean;
CheckEof    : boolean;
CheckSnow   : boolean;
DirectVideo : boolean;
LastMode    : word;
TextAttr    : byte;
WindMin     : word;
WindMax     : word;
```

### *CheckBreak*

Enables and disables checks for *Ctrl-Break*.

```
var CheckBreak: boolean;
```

When *CheckBreak* is True, pressing *Ctrl-Break* will abort the program when it next writes to the display. When *CheckBreak* is False, pressing *Ctrl-Break* has no effect. *CheckBreak* is True by default. (At run time, *Crt* stores the old *Ctrl-Break* interrupt vector, \$1B, in a global pointer variable called *SaveInt1B*.)



## ***CheckEOF***

Enables and disables the end-of-file character:

```
var CheckEOF: boolean;
```

When *CheckEOF* is *True*, an end-of-file character is generated if you press *Ctrl-Z* while reading from a file assigned to the screen. When *CheckEOF* is *False*, pressing *Ctrl-Z* has no effect. *CheckEOF* is *False* by default.

## ***CheckSnow***

Enables and disables “snow-checking” when storing characters directly in video memory.

```
var CheckSnow: boolean;
```

On most CGAs, interference will result if characters are stored in video memory outside the horizontal retrace intervals. This does not occur with Monochrome Adapters or EGAs.

When a color text mode is selected, *CheckSnow* is set to *True*, and direct video-memory writes will occur only during the horizontal retrace intervals. If you are running on a newer CGA, you may want to set *CheckSnow* to *False* at the beginning of your program and after each call to *TextMode*. This will disable snow-checking, resulting in significantly higher output speeds.

*CheckSnow* has no effect when *DirectVideo* is *False*.

## ***DirectVideo***

Enables and disables direct memory access for *Write* and *WriteLn* statements that output to the screen.

```
var DirectVideo: boolean;
```

When *DirectVideo* is *True*, *Writes* and *WriteLns* to files associated with the CRT will store characters directly in video memory instead of calling the BIOS to display them. When *DirectVideo* is *False*, all characters are written through BIOS calls, which is a significantly slower process.

*DirectVideo* always defaults to *True*. If, for some reason, you want characters displayed through BIOS calls, set *DirectVideo* to *False* at the beginning of your program and after each call to *TextMode*.

## ***LastMode***

Each time *TextMode* is called, the current video mode is stored in *LastMode*. In addition, *LastMode* is initialized at program startup to the then-active video mode.

```
var LastMode: word;
```

## ***TextAttr***

Stores the currently selected text attributes.

```
var TextAttr: byte;
```

The text attributes are normally set through calls to *TextColor* and *TextBackground*. However, you can also set them by directly storing a value in *TextAttr*. The color information is encoded in *TextAttr* as follows:

7	6	5	4	3	2	1	0
B	b	b	b	f	f	f	f

where *ffff* is the 4-bit foreground color, *bbb* is the 3-bit background color, and *B* is the blink-enable bit. If you use the color constants for creating *TextAttr* values, note that the background color can only be selected from the first 8 colors, and that it must be multiplied by 16 to get it into the correct bit positions. The following assignment selects blinking yellow characters on a blue background:

```
TextAttr := Yellow + Blue * 16 + Blink;
```

## ***WindMin and WindMax***

Store the screen coordinates of the current window.

```
var WindMin, WindMax : word;
```

These variables are set by calls to the *Window* procedure. *WindMin* defines the upper left corner, and *WindMax* defines the lower right corner. The *X* coordinate is stored in the low byte, and the *Y* coordinate is stored in the high byte. For example, *Lo(WindMin)* produces the *X* coordinate of the left edge, and *Hi(WindMax)* produces the *Y* coordinate of the bottom edge. The upper left corner of the screen corresponds to (*X,Y*) = (0,0). Note, however, that for coordinates passed to *Window* and *GotoXY*, the upper left corner is at (1,1).

## ***Procedures***

<b>AssignCrt</b>	Associates a text file with the CRT.
<b>ClrEol</b>	Clears all characters from the cursor position to the end of the line without moving the cursor.
<b>ClrScr</b>	Clears the screen and places the cursor in the upper left-hand corner.
<b>Delay</b>	Delays a specified number of milliseconds.
<b>DelLine</b>	Deletes the line containing the cursor and moves all lines below that line one line up. The bottom line is cleared.
<b>GotoXY</b>	Positions the cursor. X is the horizontal position. Y is the vertical position.
<b>HighVideo</b>	Selects high-intensity characters.
<b>InsLine</b>	Inserts an empty line at the cursor position.
<b>LowVideo</b>	Selects low-intensity characters.
<b>NormVideo</b>	Selects normal characters.
<b>NoSound</b>	Turns off the internal speaker.
<b>Sound</b>	Starts the internal speaker.
<b>TextBackground</b>	Selects the background color.
<b>TextColor</b>	Selects the foreground character color.
<b>TextMode</b>	Selects a specific text mode.
<b>Window</b>	Defines a text window on the screen.

## ***Functions***

<b>KeyPressed</b>	Returns True if a key has been pressed on the keyboard, and False otherwise.
<b>ReadKey</b>	Reads a character from the keyboard.
<b>WhereX</b>	Returns the X-coordinate of the current cursor position, relative to the current window. X is the horizontal position.
<b>WhereY</b>	Returns the Y-coordinate of the current cursor position, relative to the current window. Y is the vertical position.

# The Graph Unit

---

The *Graph* unit implements a complete library of more than 50 graphics routines that range from high-level calls, like *SetViewPort*, *Circle*, *Bar3D*, and *DrawPoly*, to bit-oriented routines, like *GetImage* and *PutImage*. Several fill and line styles are supported, and there are several fonts that may be magnified, justified, and oriented horizontally or vertically.

To compile a program that uses the *Graph* unit, you'll need your program's source code, the compiler, and access to the standard units in *TURBO.TPL* and the *Graph* unit in *GRAPH.TPU*. To run a program that uses the *Graph* unit, in addition to your *.EXE* program, you'll need one or more of the graphics drivers (*.BGI* files, see the next section). In addition, if your program uses any stroked fonts, you'll need one or more font (*.CHR*) files as well.

(Pursuant to the terms of the license agreement, you can distribute the *.CHR* and *.BGI* files along with your programs.)

## Drivers

---

Graphics drivers are provided for the following graphics adapters (and true compatibles):

- |        |                 |
|--------|-----------------|
| ■ CGA  | ■ Hercules      |
| ■ MCGA | ■ AT&T 400 line |
| ■ EGA  | ■ 3270 PC       |
| ■ VGA  | ■ IBM 8514      |

Each driver contains code and data and is stored in a separate file on disk. At run time, the *InitGraph* procedure identifies the graphics hardware, loads and initializes the appropriate graphics driver, puts the system into graphics mode, and then returns control to the calling routine. The *CloseGraph* procedure unloads the driver from memory and restores the previous video mode. You can switch back and forth between text and graphics modes using the *RestoreCrtMode* and *SetGraphMode* routines. To load the driver files yourself or link them into your *.EXE*, refer to *RegisterBGIDriver* in Chapter 16.

*Graph* supports computers with dual monitors. When *Graph* is initialized by calling *InitGraph*, the correct monitor will be selected for the graphics driver and mode requested. When terminating a graphics program, the previous video mode will be restored. If autodetection of graphics hardware is requested on a dual monitor system, *InitGraph* will select the monitor and graphics card that will produce the highest quality graphics output.

CGA.BGI	Driver for IBM CGA, MCGA
EGAVGA.BGI	Driver for IBM EGA, VGA
HERC.BGI	Driver for Hercules monochrome
ATT.BGI	Driver for AT&T 6300 (400 line)
PC3270.BGI	Driver for IBM 3270 PC
IBM8514.BGI	Driver for IBM 8514

## IBM 8514 Support

Turbo Pascal supports the IBM 8514 graphics card, which is a new, high-resolution graphics card capable of resolutions up to  $1024 \times 768$  pixels, and a color palette of 256 colors from a list of 256K colors. The driver file name is IBM8514.BGI.

Turbo Pascal cannot properly autodetect the IBM 8514 graphics card (the autodetection logic recognizes it as VGA). Therefore, to use the IBM 8514 card, the *GraphDriver* variable must be assigned the value IBM8514 (which is defined in the *Graph* unit) when *InitGraph* is called. You should not use *DetectGraph* (or *Detect* with *InitGraph*) with the IBM 8514 unless you want the emulated VGA mode.

The supported modes of the IBM 8514 card are IBM8514LO (640×480 pixels), and IBM8514HI (1024×768 pixels). Both mode constants are defined in the interface for GRAPH.TPU.

The IBM 8514 uses three 6-bit values to define colors. There is a 6-bit Red, Green, and Blue component for each defined color. To allow you to define colors for the IBM 8514, a new routine was added to the BGI library. The routine is defined in GRAPH.TPU as follows:

```
procedure SetRGBPalette(ColorNum, Red, Green, Blue : word);
```

The argument *ColorNum* defines the palette entry to be loaded. *ColorNum* is an integer from 0-255 (decimal). The arguments *Red*, *Green*, and *Blue* define the component colors of the palette entry. Only the lower byte of these values is used, and out of this byte, only the 6 most-significant bits are loaded in the palette.

The other palette manipulation routines of the graphics library may not be used with the IBM 8514 driver (that is, *SetAllPalette*, *SetPalette*, *GetPalette*).

For compatibility with the balance of the IBM graphics adapters, the BGI driver defines the first 16 palette entries of the IBM 8514 to the default colors of the EGA/VGA. These values can be used as is, or changed using the *SetRGBPalette* routine.


The *FloodFill* routine will not work with the IBM 8514 driver.

These same restrictions apply when also using the VGA in 256-color mode.

## Coordinate System

---

By convention, the upper left corner of the graphics screen is (0,0). The *x* values, or columns, increment to the right. The *y* values, or rows, increment downward. Thus, in 320×200 mode on a CGA, the screen coordinates for each of the four corners with a specified point in the middle of the screen would look like this:



## Current Pointer

---

Many graphics systems support the notion of a current pointer (CP). The CP is similar in concept to a text mode cursor except that the CP is not visible.

```
Write('ABC');
```

In text mode, the preceding *Write* statement will leave the cursor in the column immediately following the letter C. If the C is written in column 80, then the cursor will wrap around to column 1 of the next line. If the C is written in column 80 on the 25th line, the entire screen will scroll up one line, and the cursor will be in column 1 of line 25.

```
MoveTo(0,0)  
LineTo(20,20)
```

In graphics mode, the preceding *LineTo* statement will leave the CP at the last point referenced (20,20). The actual line output would be clipped to the current viewport if clipping is active. Note that the CP is never clipped.

The *MoveTo* command is the equivalent of *GoToXY*. It's only purpose is to move the CP. Only the commands that use the CP move the CP: *InitGraph*,

*MoveTo*, *MoveRel*, *LineTo*, *LineRel*, *OutText*, *SetGraphMode*,\* *GraphDefaults*,\* *ClearDevice*,\* *SetViewPort*,\* and *ClearViewPort*\*.

**Note:** The procedures with an asterisk (\*) after their names in the preceding list move the CP to (0,0.)

## *Text*

---

An 8×8 bit-mapped font and several “stroked” fonts are included for text output while in graphics mode. A bit-mapped character is defined by an 8×8 matrix of pixels. A stroked font is defined by a series of vectors that tell the graphics system how to draw the font.

The advantage to using a stroked font is apparent when you start to draw large characters. Since a stroked font is defined by vectors, it will still retain good resolution and quality when the font is enlarged.

When a bit-mapped font is enlarged, the matrix is multiplied by a scaling factor and, as the scaling factors becomes larger, the characters’ resolution becomes coarser. For small characters, the bit-mapped font should be sufficient, but for larger text you will want to select a “stroked” font.

The justification of graphics text is controlled by the *SetTextJustify* procedure. Scaling and font selection is done with the *SetTextStyle* procedure. Graphics text is output by calling either the *OutText* or *OutTextXY* procedures. Inquiries about the current text settings are made by calling the *GetTextSettings* procedure. The size of stroked fonts can be customized by the *SetUserCharSize* procedure.

Stroked fonts are each kept in a separate file on disk with a .CHR file extension. Font files can be loaded from disk automatically by the *Graph* unit at run time (as described), or they can also be linked in or loaded by the user program and “registered” with the *Graph* unit.

A special utility, BINOBJ.EXE, is provided that converts a font file (or any binary data file, for that matter) to an .OBJ file that can be linked into a unit or program using the {\$L} compiler directive. This makes it possible for a program to have all its font files built into the .EXE file. (Read the comments at the beginning of the GRLINK.PAS sample program on the distribution disks.)

## *Figures and Styles*

---

All kinds of support routines are provided for drawing and filling figures, including points, lines, circles, arcs, ellipses, rectangles, polygons, bars, 3-D

bars, and pie slices. Use *SetLineStyle* to control whether lines are thick or thin, or whether they are solid, dotted, or built using your own pattern.

Use *SetFillStyle* and *SetFillPattern*, *FillPoly* and *FloodFill* to fill a region or a polygon with cross-hatching or other intricate patterns.

## *Viewports and Bit Images*

---

The *Viewport* procedure makes all output commands operate in a rectangular region on the screen. Plots, lines, figures—all graphics output—are viewport-relative until the viewport is changed. Other routines are provided to clear a viewport and read the current viewport definitions. If clipping is active, all graphics output is clipped to the current port. Note that the CP is never clipped.

*GetPixel* and *PutPixel* are provided for reading and plotting pixels. *GetImage* and *PutImage* can be used to save and restore rectangular regions on the screen. They support the full complement of *BitBlt* operations (copy, xor, or, and, not).

## *Paging and Colors*

---

There are many other support routines, including support for multiple graphic pages (EGA, VGA, and Hercules only; especially useful for doing animation), palettes, colors, and so on.

## *Error-Handling*

---

Internal errors in the *Graph* unit are returned by the function *GraphResult*. *GraphResult* returns an error code that reports the status of the last graphics operation. The following error return codes are defined:

- 0: No error
- -1: (BGI) graphics not installed (use *InitGraph*)
- -2: Graphics hardware not detected
- -3: Device driver file not found
- -4: Invalid device driver file
- -5: Not enough memory to load driver
- -6: Out of memory in scan fill
- -7: Out of memory in flood fill
- -8: Font file not found
- -9: Not enough memory to load font



- -10: Invalid graphics mode for selected driver
- -11: Graphics error
- -12: Graphics I/O error
- -13: Invalid font file
- -14: Invalid font number

The following routines set *GraphResult*:

<i>Bar</i>	<i>ImageSize</i>	<i>SetFillPattern</i>
<i>Bar3D</i>	<i>InitGraph</i>	<i>SetFillStyle</i>
<i>ClearViewPort</i>	<i>InstallUserDriver</i>	<i>SetGraphBufSize</i>
<i>CloseGraph</i>	<i>InstallUserFont</i>	<i>SetGraphMode</i>
<i>DetectGraph</i>	<i>PieSlice</i>	<i>SetLineStyle</i>
<i>DrawPoly</i>	<i>RegisterBGIdriver</i>	<i>SetPalette</i>
<i>FillPoly</i>	<i>RegisterBGIfont</i>	<i>SetTextJustify</i>
<i>FloodFill</i>	<i>SetAllPalette</i>	<i>SetTextStyle</i>
<i>GetGraphMode</i>		

Note that *GraphResult* is reset to zero after it has been called. Therefore, the user should store the value of *GraphResult* into a temporary variable and then test it. The following return code constants are defined:

```
const
{ GraphResult error return codes }
grOk           = 0;
grNoInitGraph  = -1;
grNotDetected  = -2;
grFileNotFound = -3;
grInvalidDriver = -4;
grNoLoadMem    = -5;
grNoScanMem    = -6;
grNoFloodMem   = -7;
grFontNotFound = -8;
grNoFontMem    = -9;
grInvalidMode  = -10;
grError        = -11;
grIOError      = -12;
grInvalidFont  = -13;
grInvalidFontNum = -14;
```

## Getting Started

---

Here's a simple graphics program:

```
1 program GraphTest;
2 uses
3   Graph;
4 var
```

```

5   GraphDriver : integer;
6   GraphMode   : integer;
7   ErrorCode   : integer;
8   begin
9     GraphDriver := Detect;                { Set flag: do detection }
10    InitGraph(GraphDriver, GraphMode, 'C:\DRIVERS');
11    ErrorCode := GraphResult;
12    if ErrorCode <> grOk then                { Error? }
13      begin
14        Writeln('Graphics error: ', GraphErrorMsg(ErrorCode));
15        Writeln('Program aborted...');
16        Halt(1);
17      end;
18      Rectangle(0, 0, GetMaxX, GetMaxY);    { Draw full screen box }
19      SetTextJustify(CenterText, CenterText); { Center text }
20      SetTextStyle(DefaultFont, HorizDir, 3);
21      OutTextXY(GetMaxX div 2, GetMaxY div 2, { Center of screen }
22        'Borland Graphics Interface (BGI)');
23      Readln;
24      CloseGraph;
25 end. { GraphTest }

```

The program begins with a call to *InitGraph*, which autodetects the hardware and loads the appropriate graphics driver (located in C:\DRIVERS). If no graphics hardware is recognized or an error occurs during initialization, an error message is displayed and the program terminates. Otherwise, a box is drawn along the edge of the screen and text is displayed in the center of the screen.

**Note:** Neither the AT&T 400 line card nor the IBM 8514 graphics adapter is autodetected. You can still use these drivers by overriding autodetection and passing *InitGraph* the driver code and a valid graphics mode. To use the AT&T driver, for example, replace lines 9 and 10 in the preceding example with the following three lines of code:

```

GraphDriver := ATT400;
GraphMode := ATT400Hi;
InitGraph(GraphDriver, GraphMode, 'C:\DRIVERS');

```

This instructs the graphics system to load the AT&T 400 line driver located in C:\DRIVERS and set the graphics mode to 640 by 400.

Here's another example that demonstrates how to switch back and forth between graphics and text modes:

```

1  program GraphTest;
2  uses
3    Graph;
4  var
5    GraphDriver : integer;
6    GraphMode   : integer;
7    ErrorCode   : integer;
8  begin
9    GraphDriver := Detect;                { Set flag: do detection }
10   InitGraph(GraphDriver, GraphMode, 'C:\DRIVERS');
11   ErrorCode := GraphResult;
12   if ErrorCode <> grOk then              { Error? }
13   begin
14     Writeln('Graphics error: ', GraphErrorMsg(ErrorCode));
15     Writeln('Program aborted...');
16     Halt(1);
17   end;
18   OutText('In Graphics mode. Press <RETURN>');
19   Readln;
20   RestoreCRTMode;
21   Write('Now in text mode. Press <RETURN>');
22   Readln;
23   SetGraphMode(GraphMode);
24   OutText('Back in Graphics mode. Press <RETURN>');
25   Readln;
26   CloseGraph;
27 end. { GraphTest }

```

Note that the *SetGraphMode* call on line 23 resets all the graphics parameters (palette, current pointer, foreground, and background colors, and so on) to the default values.

The call to *CloseGraph* restores the video mode that was detected initially by *InitGraph* and frees the heap memory that was used to hold the graphics driver.

## User-Written Heap Management Routines

Two heap management routines are used by the *Graph* unit: *GraphGetMem* and *GraphFreeMem*. *GraphGetMem* allocates memory for graphics device drivers, stroked fonts, and a scan buffer. *GraphFreeMem* deallocates the memory allocated to the drivers. The standard routines take the following form:

```

procedure GraphGetMem(var P : pointer; Size : word);
{ Allocate memory for graphics }

procedure GraphFreeMem(var P : pointer; Size : word);
{ Deallocate memory for graphics }

```

Two pointers are defined by *Graph* that by default point to the two standard routines described here. The pointers are defined as follows:

```
var
  GraphGetMemPtr : pointer;           { Pointer to memory allocation routine }
  GraphFreeMemPtr : pointer          { Pointer to memory deallocation routine }
```

The heap management routines referenced by *GraphGetMemPtr* and *GraphFreeMemPtr* are called by the *Graph* unit to allocate and deallocate memory for three different purposes:

- a multi-purpose graphics buffer whose size can be set by a call to *SetGraphBufSize* (default = 4K)
- a device driver that is loaded by *InitGraph* (\*.BGI files)
- a stroked font file that is loaded by *SetTextStyle* (\*.CHR files)

The graphics buffer is always allocated on the heap. The device driver is allocated on the heap unless your program loads or links one in and calls *RegisterBGIDriver*, and the font file is allocated on the heap when you select a stroked font using *SetTextStyle*—unless your program loads or links one in and calls *RegisterBGIfont*.

Upon initialization of the *Graph* unit, these pointers point to the standard graphics allocation and deallocation routines that are defined in the implementation section of the *Graph* unit. You can insert your own memory management routines by assigning these pointers the address of your routines. The user-defined routines must have the same parameter lists as the standard routines and must be *far* procedures. The following is an example of user-defined allocation and deallocation routines; notice the use of *MyExitProc* to automatically call *CloseGraph* when the program terminates:

```
program UserHeapManagement;
{ Illustrates how the user can steal the heap }
{ management routines used by the Graph unit. }

uses
  Graph;

var
  GraphDriver, GraphMode : integer;
  ErrorCode               : integer;   { Used to store GraphResult return code }
  PreGraphExitProc        : pointer;   { Used to save original exit proc }

{$F+} { User routines must be far call model }
procedure MyGetMem(var P : pointer; Size : word);
{ Allocate memory for graphics device drivers, fonts, and scan buffer }
begin
  GetMem(P, Size)
end; { MyGetMem }

procedure MyFreeMem(var P : pointer; Size : word);
```

```

{ Deallocate memory for graphics device drivers, fonts, and scan buffer }
begin
  if P <> nil then                                { Don't free Nil pointers! }
  begin
    FreeMem(P, Size);
    P := nil;
  end;
end; { MyFreeMem }

procedure MyExitProc;
{ Always gets called when program terminates }
begin
  ExitProc := PreGraphExitProc;                  { Restore original exit proc }
  CloseGraph;                                     { Do heap clean up }
end; { MyExitProc }
{$F-}

begin
  { Install clean-up routine }
  PreGraphExitProc := ExitProc;
  ExitProc := @MyExitProc;

  GraphGetMemPtr := @MyGetMem;                    { Control memory allocation }
  GraphFreeMemPtr := @MyFreeMem;                  { Control memory deallocation }

  GraphDriver := Detect;
  InitGraph(GraphDriver, GraphMode, '');
  ErrorCode := GraphResult;
  if ErrorCode <> grOk then
  begin
    Writeln('Graphics error: ', GraphErrorMsg(ErrorCode));
    Readln;
    Halt(1);
  end;
  Line(0, 0, GetMaxX, GetMaxY);
  OutTextXY(1, 1, 'Press <Return>:');
  Readln;
end. { UserHeapManagment }

```

## ***Graph Unit Constants, Types and Variables***

---

### **Constants**

The following error values are returned by *GraphResult*:

```

const
    grOk           = 0;
    grNoInitGraph  = -1;
    grNotDetected  = -2;
    grFileNotFound = -3;
    grInvalidDriver = -4;
    grNoLoadMem    = -5;
    grNoScanMem    = -6;
    grNoFloodMem   = -7;
    grFontNotFound = -8;
    grNoFontMem    = -9;
    grInvalidMode  = -10;
    grError        = -11; { generic error }
    grIOerror      = -12;
    grInvalidFont  = -13;
    grInvalidFontNum = -14;

```

Use these driver and mode constants with *InitGraph*, *DetectGraph*, and *GetModeRange*:

```

const
    Detect           = 0; { Requests autodetection }
    CGA             = 1;
    MCGA           = 2;
    EGA            = 3;
    EGA64          = 4;
    EGAMono        = 5;
    IBM8514        = 6;
    HercMono       = 7;
    ATT400         = 8;
    VGA            = 9;
    PC3270         = 10;
    CurrentDriver   = -128; { Passed to GetModeRange }

    CGAC0          = 0; { 320x200 palette 0: LightGreen, LightRed, Yellow; 1 page }
    CGAC1          = 1; { 320x200 palette 1: LightCyan, LightMagenta, White; 1 page }
    CGAC2          = 2; { 320x200 palette 2: Green, Red, Brown; 1 page }
    CGAC3          = 3; { 320x200 palette 3: Cyan, Magenta, LightGray; 1 page }
    CGAHi          = 4; { 640x200 1 page }
    MCGAC0         = 0; { 320x200 palette 0: LightGreen, LightRed, Yellow; 1 page }
    MCGAC1         = 1; { 320x200 palette 1: LightCyan, LightMagenta, White; 1 page }
    MCGAC2         = 2; { 320x200 palette 2: Green, Red, Brown; 1 page }
    MCGAC3         = 3; { 320x200 palette 3: Cyan, Magenta, LightGray; 1 page }
    MCGAMed        = 4; { 640x200 1 page }
    MCGAHi         = 5; { 640x480 1 page }
    EGALo          = 0; { 640x200 16 color 4 page }
    EGAHi          = 1; { 640x350 16 color 2 page }
    EGA64Lo        = 0; { 640x200 16 color 1 page }
    EGA64Hi        = 1; { 640x350 4 color 1 page }
    EGAMonoHi      = 3; { 640x350 64K on card, 1 page; 256K on card, 2 page }
    HercMonoHi     = 0; { 720x348 2 page }

```

```

ATT400C0 = 0; { 320x200 palette 0: LightGreen, LightRed, Yellow; 1 page }
ATT400C1 = 1; { 320x200 palette 1: LightCyan, LightMagenta, White; 1 page }
ATT400C2 = 2; { 320x200 palette 2: Green, Red, Brown; 1 page }
ATT400C3 = 3; { 320x200 palette 3: Cyan, Magenta, LightGray; 1 page }
ATT400Med = 4; { 640x200 1 page }
ATT400Hi = 5; { 640x400 1 page }
VGALo = 0; { 640x200 16 color 4 page }
VGAMed = 1; { 640x350 16 color 2 page }
VGAHi = 2; { 640x480 16 color 1 page }
PC3270Hi = 0; { 720x350 1 page }
IBM8514LO = 0; { 640x480 256 colors }
IBM8514HI = 1; { 1024x768 256 colors }

```

Use these color constants with *SetPalette* and *SetAllPalette*:

```

const
  Black      = 0;
  Blue       = 1;
  Green      = 2;
  Cyan       = 3;
  Red        = 4;
  Magenta    = 5;
  Brown      = 6;
  LightGray  = 7;
  DarkGray   = 8;
  LightBlue  = 9;
  LightGreen = 10;
  LightCyan  = 11;
  LightRed   = 12;
  LightMagenta = 13;
  Yellow     = 14;
  White      = 15;

```

These color constants can be used with *SetRGBPalette* to select the standard EGA colors on an IBM 8514 graphics adapter:

```

const
  EGABlack      = 0; { dark colors }
  EGABlue       = 1;
  EGAGreen      = 2;
  EGACyan       = 3;
  EGARed        = 4;
  EGAMagenta    = 5;
  EGABrown      = 20;
  EGALightgray  = 7;
  EGADarkgray   = 56; { light colors }
  EGALightblue  = 57;
  EGALightgreen = 58;
  EGALightcyan  = 59;
  EGALightred   = 60;
  EGALightmagenta = 61;

```

```
EGAYellow      = 62;
EGAWhite       = 63;
```

Use these line style constants with *GetLineSettings* and *SetLineStyle*:

```
const
SolidLn      = 0;
DottedLn     = 1;
CenterLn     = 2;
DashedLn     = 3;
UserBitLn    = 4;                                { User-defined line style }
NormWidth    = 1;
ThickWidth    = 3;
```

Use these font control constants with *GetTextSettings* and *SetTextStyle*:

```
const
DefaultFont  = 0;                                { 8x8 bit mapped font }
TriplexFont  = 1;                                { "Stroked" fonts }
SmallFont    = 2;
SansSerifFont = 3;
GothicFont   = 4;

HorizDir     = 0;                                { Left to right }
VertDir      = 1;                                { Bottom to top }

UserCharSize = 0;                                { User-defined char size }
```

These constants control horizontal and vertical justification for *SetTextJustify*:

```
const
LeftText     = 0;
CenterText   = 1;
RightText    = 2;

BottomText   = 0;
{ CenterText = 1; already defined above }
TopText      = 2;
```

Use these constants with *SetViewport* to control clipping. With clipping on, graphics output is clipped at the viewport boundaries:

```
const
ClipOn = true;
ClipOff = false;
```

These constants may be used with *Bar3D* to specify whether a 3-D top should be drawn on top of the bar (allows for stacking bars and only drawing a top on the topmost bar):

```
const
TopOn = true;
TopOff = false;
```



These fill pattern constants are used by *GetFillSettings* and *SetFillStyle*. Use *SetFillPattern* to define your own fill pattern; then call

```
SetFillStyle(UserFill, SomeColor)
```

and make your fill pattern the active style:

```
const
  EmptyFill      = 0; { Fills area in background color }
  SolidFill      = 1; { Fills area in solid fill color }
  LineFill       = 2; { --- fill }
  LtSlashFill    = 3; { /// fill }
  SlashFill      = 4; { /// fill with thick lines }
  BkSlashFill    = 5; { \\ \\ fill with thick lines }
  LtBkSlashFill  = 6; { \\ \\ fill }
  HatchFill      = 7; { Light hatch fill }
  XHatchFill     = 8; { Heavy cross hatch fill }
  InterleaveFill = 9; { Interleaving line fill }
  WideDotFill    = 10; { Widely spaced dot fill }
  CloseDotFill   = 11; { Closely spaced dot fill }
  UserFill       = 12; { User-defined fill }
```

Use these BitBlt operators with both *PutImage* and *SetWriteMode*:

```
const
  CopyPut        = 0; { MOV }
  XORPut         = 1; { XOR }
```

These BitBlt operators are used by *PutImage* only:

```
const
  OrPut          = 2; { OR }
  AndPut         = 3; { AND }
  NotPut         = 4; { NOT }
```

This constant is used by *GetPalette*, *GetDefaultPalette*, *SetAllPalette*, and to define the *PaletteType* record:

```
const
  MaxColors = 15;
```

## Types

This record is used by *GetPalette*, *GetDefaultPalette*, and *SetAllPalette*:

```
type
  PaletteType = record
    Size : byte;
    Colors : array[0..MaxColors] of shortint;
  end;
```

This record is used by by *GetLineSettings*:

```

type
  LineSettingsType = record
    LineStyle : word;
    Pattern   : word;
    Thickness : word;
  end;

```

This record is used by *GetTextSettings*:

```

type
  TextSettingsType = record
    Font       : word;
    Direction  : word;
    CharSize   : word;
    Horiz      : word;
    Vert       : word;
  end;

```

This record is used by *GetFillSettings*:

```

type
  FillSettingsType = record
    Pattern : word;
    Color   : word;
  end;

```

This record is used by *GetFillPattern* and *SetFillPattern*:

```

type
  FillPatternType = array[1..8] of byte; { User-defined fill style }

```

This type is defined for your convenience. Note that both fields are of type integer (not word):

```

type
  PointType = record
    X, Y : integer;
  end;

```

This record is used by *GetViewSettings* to report the status of the current viewport:

```

type
  ViewPortType = record
    x1, y1, x2, y2 : integer;
    Clip           : boolean;
  end;

```

This record is used by *GetArcCoords* and can be used to retrieve information about the last call to *Arc* or *Ellipse*:

```

type
  ArcCoordsType = record
    X, Y      : integer;
    Xstart, Ystart : integer;
    Xend, Yend  : integer;
  end;

```

## Variables

These variables initially point to the Graph unit's heap management routines. If your program does its own heap management, assign the addresses of your allocation and deallocation routines to *GraphGetMemPtr* and *GraphFreeMemPtr* respectively:

```

GraphGetMemPtr : pointer;           { Allows user to steal heap allocation }
GraphFreeMemPtr : pointer;         { Allows user to steal heap deallocation }

```

## Procedures

<b>Arc</b>	Draws a circular arc from start angle to end angle, using (x,y) as the center point.
<b>Bar</b>	Draws a bar using the current fill style and color.
<b>Bar3D</b>	Draws a 3-D bar using the current fill style and color.
<b>Circle</b>	Draws a circle using (x,y) as the center point.
<b>ClearDevice</b>	Clears the currently selected output device and homes the current pointer.
<b>ClearViewPort</b>	Clears the current viewport.
<b>CloseGraph</b>	Shuts down the graphics system.
<b>DetectGraph</b>	Checks the hardware and determines which graphics driver and mode to use.
<b>DrawPoly</b>	Draws the outline of a polygon using the current line style and color.
<b>Ellipse</b>	Draws an elliptical arc from start angle to end angle, using (X,Y) as the center point.
<b>FillEllipse</b>	Draws a filled ellipse using (X,Y) as a center point and <i>XRradius</i> and <i>YRradius</i> as the horizontal and vertical axes.
<b>FillPoly</b>	Fills a polygon, using the scan converter.

<b>FloodFill</b>	Fills a bounded region using the current fill pattern and fill color.
<b>GetArcCoords</b>	Allows the user to inquire about the coordinates of the last <i>Arc</i> command.
<b>GetAspectRatio</b>	Returns the effective resolution of the graphics screen from which the aspect ratio ( <i>Xasp:Yasp</i> ) can be computed.
<b>GetFillPattern</b>	Returns the last fill pattern set by a call to <i>SetFillPattern</i> .
<b>GetFillSettings</b>	Allows the user to inquire about the current fill pattern and color as set by <i>SetFillStyle</i> or <i>SetFillPattern</i> .
<b>GetImage</b>	Saves a bit image of the specified region into a buffer.
<b>GetLineSettings</b>	Returns the current line style, line pattern, and line thickness as set by <i>SetLineStyle</i> .
<b>GetModeRange</b>	Returns the lowest and highest valid graphics mode for a given driver.
<b>GetPalette</b>	Returns the current palette and its size.
<b>GetTextSettings</b>	Returns the current text font, direction, size, and justification as set by <i>SetTextStyle</i> and <i>SetTextJustify</i> .
<b>GetViewSettings</b>	Allows the user to inquire about the current viewport and clipping parameters.
<b>GraphDefaults</b>	Homes the current pointer (CP) and resets the graphics system.
<b>InitGraph</b>	Initializes the graphics system and puts the hardware into graphics mode.
<b>Line</b>	Draws a line from the ( <i>x1, y1</i> ) to ( <i>x2, y2</i> ).
<b>LineRel</b>	Draws a line to a point that is a relative distance from the current pointer (CP).
<b>LineTo</b>	Draws a line from the current pointer to ( <i>x, y</i> ).
<b>MoveRel</b>	Moves the current pointer (CP) a relative distance from its current position.
<b>MoveTo</b>	Moves the current graphics pointer (CP) to ( <i>x, y</i> ).
<b>OutText</b>	Sends a string to the output device at the current pointer.

<b>OutTextXY</b>	Sends a string to the output device.
<b>PieSlice</b>	Draws and fills a pie slice, using (X,Y) as the center point and drawing from start angle to end angle.
<b>PutImage</b>	Puts a bit image onto the screen.
<b>PutPixel</b>	Plots a pixel at <i>x,y</i> .
<b>Rectangle</b>	Draws a rectangle using the current line style and color.
<b>RestoreCrtMode</b>	Restores the original screen mode before graphics is initialized.
<b>Sector</b>	Draws and fills an elliptical sector.
<b>SetActivePage</b>	Set the active page for graphics output.
<b>SetAllPalette</b>	Changes all palette colors as specified.
<b>SetAspectRatio</b>	Changes the default aspect ratio.
<b>SetBkColor</b>	Sets the current background color using the palette.
<b>SetColor</b>	Sets the current drawing color using the palette.
<b>SetFillPattern</b>	Selects a user-defined fill pattern.
<b>SetFillStyle</b>	Sets the fill pattern and color.
<b>SetGraphBufSize</b>	Allows you to change the size of the buffer used for scan and flood fills.
<b>SetGraphMode</b>	Sets the system to graphics mode and clears the screen.
<b>SetLineStyle</b>	Sets the current line width and style.
<b>SetPalette</b>	Changes one palette color as specified by <i>ColorNum</i> and <i>Color</i> .
<b>SetRGBPalette</b>	Allows you to modify palette entries for the IBM 8514 and the VGA drivers.
<b>SetTextJustify</b>	Sets text justification values used by <i>OutText</i> and <i>OutTextXY</i> .
<b>SetTextStyle</b>	Sets the current text font, style, and character magnification factor.
<b>SetUserCharSize</b>	Lets you change the character width and height for stroked fonts.
<b>SetViewPort</b>	Sets the current output viewport or window for graphics output.

<b>SetVisualPage</b>	Sets the visual graphics page number.
<b>SetWriteMode</b>	Sets the writing mode (copy or XOR) for lines drawn by <i>DrawPoly</i> , <i>Line</i> , <i>LineRel</i> , <i>LineTo</i> , and <i>Rectangle</i> .

### ***Functions***

<b>GetBkColor</b>	Returns the current background color.
<b>GetColor</b>	Returns the current drawing color.
<b>GetDefaultPalette</b>	Returns the default hardware palette in a record of <i>PaletteType</i> .
<b>GetDriverName</b>	Returns a string containing the name of the current driver.
<b>GetGraphMode</b>	Returns the current graphics mode.
<b>GetMaxColor</b>	Returns the highest color that can be passed to <i>SetColor</i> .
<b>GetMaxMode</b>	Returns the maximum mode number for the currently loaded driver.
<b>GetMaxX</b>	Returns the rightmost column ( <i>x</i> resolution) of the current graphics driver and mode.
<b>GetMaxY</b>	Returns the bottommost row ( <i>y</i> resolution) of the current graphics driver and mode.
<b>GetModeName</b>	Returns a string containing the name of the specified graphics mode.
<b>GetPaletteSize</b>	Returns the size of the palette color lookup table.
<b>GetPixel</b>	Gets the pixel value at <i>X,Y</i> .
<b>GetX</b>	Returns the <i>X</i> coordinate of the current position (CP).
<b>GetY</b>	Returns the <i>Y</i> coordinate of the current position (CP).
<b>GraphErrorMsg</b>	Returns an error message string for the specified <i>ErrorCode</i> .
<b>GraphResult</b>	Returns an error code for the last graphics operation.
<b>ImageSize</b>	Returns the number of bytes required to store a rectangular region of the screen.

<b>InstallUserDriver</b>	Installs a vendor-added device driver to the BGI device driver table.
<b>InstallUserFont</b>	Installs a new font file that is not built into the BGI system.
<b>RegisterBGIdriver</b>	Registers a valid BGI driver with the graphics system.
<b>RegisterBGIfont</b>	Registers a valid BGI font with the graphics system.
<b>TextHeight</b>	Returns the height of a string in pixels.
<b>TextWidth</b>	Returns the width of a string in pixels.

For a detailed description of each procedure or function, refer to Chapter 16, "Turbo Pascal Reference Lookup."

## The Turbo3 Unit

---

Every routine in this unit is duplicated or improved upon in other standard units. The *Turbo3* unit is provided for backward compatibility only. By using *Turbo3*, you gain more 3.0-compatibility, but lose direct access to important new features built into some of the standard routines duplicated here. (Note that you can still call these standard routines by using the unit override syntax; for example, *Turbo3's* *MemAvail* calls the *System.MemAvail* function even if you are using the *Turbo3* unit in your program. For more information about referring to routines with the same name in other units, look at Chapter 4 in the *User's Guide*, "Units and Related Mysteries.")

**Note:** The routines that follow are *not* described in Chapter 16. For more detailed information about *Turbo3* routines, refer to your Turbo Pascal 3.0 reference manual.

## Interface Section

---

Here's a look at the interface section of the *Turbo3* unit:

```

unit Turbo3;
interface
uses Crt;
var
  Kbd      : Text;
  CBreak  : boolean absolute CheckBreak;

function MemAvail: integer;
function MaxAvail: integer;
function LongFileSize(var F): real;

```

```

function LongFilePos(var F): real;
procedure LongSeek(var F; Pos: real);
procedure HighVideo;
procedure NormVideo;
procedure LowVideo;
function IOResult : integer;

```

As you can see, there are two global variables, five functions, and four procedures declared in the *Turbo3* unit.

## Kbd

This is provided for Turbo Pascal 3.0 programs that read from the keyboard device; for example, *Read(Kbd, CharVar)*. Note that there is now a function in the *Crt* unit called *ReadKey* that should be used in place of *Read(Kbd, CharVar)*. Here are two programs that read a character and report whether an extended key was typed (*F1*, *F2*, *Left arrow*, and so on):

In version 3.0:

```

program TestKbd;
uses Crt, Turbo3;
var
  c : char;
begin
  Read(Kbd, c);
  if (c = #27) and KeyPressed then
    begin
      Read(Kbd, c);
      Writeln('Extended key: ', c);
    end
  else
    Writeln(c);
  end.

```

Notice that the *Kbd* device handler converts extended keys from (null + character) to (ESC + second character). Since *Esc* (#27) is a perfectly valid key to enter from the keyboard, a call to *KeyPressed* must be made to determine whether the #27 is the first key from an extended key or an actual *Esc* typed on the keyboard. If an *Esc* is typed, followed quickly by another character before the program detected the *Esc*, the two keys would be mistaken as an extended keystroke.

In version 5.0:

```

program TestReadKey;
uses Crt;
var
  c : char;

```



```

begin
  c := ReadKey;
  if (c = #0) then
    Writeln('Extended key: ', ReadKey);
  else
    Writeln(c);
end.

```

The code in 5.0 is smaller (and faster), and contains none of the ambiguity about the leading character of an extended keystroke. (It is impossible to generate a null character from the keyboard except when using the extended keys.)

## CBreak

*CBreak* has been renamed to *CheckBreak* in version 5.0. Backward compatibility is achieved by giving *CBreak* the same address as *CheckBreak*, which is declared in the *Crt* unit. The statement *CBreak := False* turns off *Ctrl-Break* checking; *CBreak := True* turns it back on.

## Procedures

<b>HighVideo</b>	Sets the video attribute to yellow on black (color systems) or white on black (black and white, mono systems).
<b>LongSeek</b>	Moves the current position of a file to a specified component. Uses a real number parameter to specify the component number.
<b>LowVideo</b>	Sets the video attribute to <i>LightGray</i> on black.
<b>NormVideo</b>	Same as <i>HighVideo</i> . Sets the video attribute to yellow on black (color systems) or white on black (black and white, mono systems).

## Functions

<b>IOResult</b>	Returns an integer value that is the status of the last I/O operation performed. The <i>Turbo3 IOResult</i> function returns 3.0-compatible return codes wherever possible.
<b>LongFilePos</b>	Returns the current file position of a file. The value returned is a real number.
<b>LongFileSize</b>	Returns the size of the file. The value returned is a real number.

<b>MaxAvail</b>	Returns the size of the largest contiguous free block in the heap (in paragraphs).
<b>MemAvail</b>	Returns the number of free paragraphs of heap storage available.

## The Graph3 Unit

---

The *Graph3* unit is a direct implementation of the turtlegraphics driver provided by Turbo Pascal 3.0. In Turbo Pascal 3.0, the turtlegraphics driver was made up of two files, GRAPH.P and GRAPH.BIN that supported the IBM CGA and compatibles. GRAPH.P actually defines the external machine code routines contained in GRAPH.BIN.

*Graph3* combines Turbo Pascal 3.0's GRAPH.P and GRAPH.BIN into a single unit, still retaining the same functionality. The only modification you need to make to a Turbo Pascal 3.0 program that uses the turtlegraphics driver is to remove the {\$I GRAPH.P} compiler directive, replacing it with a reference to *Crt* and *Graph3* in your program's uses clause.

**Note:** The routines that follow are *not* described in Chapter 16. For more detailed information about *Graph3* routines, refer to your Turbo Pascal 3.0 reference manual.

Here are *Graph3*'s constants:

```
const
  North = 0;
  East  = 90;
  South = 180;
  West  = 270;
```

### Procedures

<b>Arc</b>	Draws an arc using the given parameters.
<b>Back</b>	Moves the turtle backward by the given distance. (Turtlegraphics)
<b>Circle</b>	Draws a circle.
<b>ClearScreen</b>	Clears the active window and homes the turtle. (Turtlegraphics)
<b>ColorTable</b>	Defines a color translation table that lets the current color of any given point determine the new color of that point when it is redrawn.

<b>Draw</b>	Draws a line between the specified endpoints and in the specified color.
<b>FillPattern</b>	Fills a rectangular area with the current pattern using the specified color.
<b>FillScreen</b>	Fills the entire active window with the indicated color.
<b>FillShape</b>	Fills an area of any shape with the specified color.
<b>Forwd</b>	Moves the turtle forward by the given distance. (Turtlegraphics)
<b>GetDotColor</b>	Returns the color value of the dot at the indicated location.
<b>GetPic</b>	Copies the contents of an area on the screen into a buffer; the contents can later be restored using <i>PutPic</i> .
<b>GraphBackground</b>	Sets background color of screen.
<b>GraphColorMode</b>	Sets you in 320x200 color graphics mode.
<b>GraphMode</b>	Sets you in 320x200 black-and-white graphics mode.
<b>GraphWindow</b>	Lets you define an area of the screen as the active window in any of the graphics modes.
<b>Heading</b>	Returns the current heading of the turtle. (Turtlegraphics)
<b>HideTurtle</b>	Hides the turtle. (Turtlegraphics)
<b>HiRes</b>	Sets screen in 640x200 high-resolution graphics mode.
<b>HiResColor</b>	Selects the color used for drawing in high-resolution graphics.
<b>Home</b>	Puts the turtle in its home position. (Turtlegraphics)
<b>NoWrap</b>	Disables "wrapping" for the turtle. (Turtlegraphics)
<b>Palette</b>	Activates the color palette specified.
<b>Pattern</b>	Defines an 8x8 pattern to be used by <i>FillPattern</i> .
<b>PenDown</b>	Puts the turtle's pen "down" so that any movement of the turtle results in drawing. (Turtlegraphics)

<b>PenUp</b>	Puts the turtle's pen "up" so that the turtle can be moved without drawing. (Turtlegraphics)
<b>Plot</b>	Plots a point at the specified coordinates and in the specified color.
<b>PutPic</b>	Copies the contents of a buffer.
<b>SetHeading</b>	Turns the turtle to the specified angle. (Turtlegraphics)
<b>SetPenColor</b>	Sets the color used for the turtle's pen. (Turtlegraphics)
<b>SetPosition</b>	Moves the turtle to the given coordinates without drawing a line. (Turtlegraphics)
<b>ShowTurtle</b>	Makes the turtle visible. (Turtlegraphics)
<b>TurnLeft</b>	Turns the turtle's heading to the left (counterclockwise). (Turtlegraphics)
<b>TurnRight</b>	Turns the turtle's heading to the right (clockwise). (Turtlegraphics)
<b>TurtleDelay</b>	Sets a delay between each step of the turtle. (Turtlegraphics)
<b>TurtleThere</b>	Tests if the turtle is visible and in the active window. (Turtlegraphics)
<b>TurtleWindow</b>	Defines an area of the screen as the active turtle graphics screen. (Turtlegraphics)
<b>Wrap</b>	Forces wraparound when the turtle attempts to move past the boundaries of the active window. (Turtlegraphics)
<b>XCor</b>	Returns the current X-coordinate of the turtle. (Turtlegraphics)
<b>YCor</b>	Returns the current Y-coordinate of the turtle. (Turtlegraphics)



## Overlays

*Overlays* are parts of a program that share a common memory area. Only the parts of the program that are required for a given function reside in memory at the same time; they can overwrite each other during execution.

Overlays can significantly reduce a program's total run-time memory requirements. In fact, with overlays you can execute programs that are much larger than the total available memory, since only parts of the program reside in memory at any given time.

Turbo Pascal manages overlays at the unit level; this is the smallest part of a program that can be made into an overlay. When an overlaid program is compiled, Turbo Pascal generates an overlay file (extension .OVR) in addition to the executable file (extension .EXE). The .EXE file contains the static (non-overlaid) parts of the program, and the .OVR file contains all the overlaid units that will be swapped in and out of memory during program execution.

Except for a few programming rules, an overlaid unit is identical to a non-overlaid unit. In fact, as long as you observe these rules, you don't even need to recompile a unit to make it into an overlay. The decision of whether or not a unit is overlaid is made by the program that uses the unit.

When an overlay is loaded into memory, it is placed in the overlay buffer, which resides in memory between the stack segment and the heap. By default, the size of the overlay buffer is as small as possible, but it may be easily increased at run-time by allocating additional space from the heap. Like the data segment and the minimum heap size, the default overlay buffer size is allocated when the .EXE is loaded. If enough memory isn't available, an error message will be displayed by DOS (Program too big to fit in memory) or by the IDE (Not enough memory to run program).

One very important option of the overlay manager is the ability to load the overlay file into expanded memory when sufficient space is available. Turbo Pascal supports version 3.2 or later of the Lotus/Intel/Microsoft Expanded Memory Specification (EMS) for this purpose. Once placed into EMS, the overlay file is closed, and subsequent overlay loads are reduced to fast in-memory transfers.

## The Overlay Unit

---

Turbo Pascal's overlay manager is implemented by the *Overlay* standard unit. The buffer management techniques used by the *Overlay* unit are very advanced, and always guarantee optimal performance in the available memory. For example, the overlay manager always keeps as many overlays as possible in the overlay buffer, to reduce the chance of having to read an overlay from disk. Once an overlay is loaded, a call to one of its routines executes just as fast as a call to a non-overlaid routine. Furthermore, when the overlay manager needs to dispose of an overlay to make room for another, it attempts to first dispose of overlays that are inactive (ones that have no active routines at that point in time).

To implement its advanced overlay management techniques, Turbo Pascal requires that you observe two important rules when writing overlaid programs:

- All overlaid units must include a `{O+}` directive, which causes the compiler to ensure that the generated code can be overlaid.
- At any call to an overlaid procedure or function, you must guarantee that all currently active procedures and functions use the FAR call model.

Both rules are explained further in a section entitled "Designing Overlaid Programs," beginning on page 164. For now, just note that you can easily satisfy these requirements by placing a `{O+,F+}` compiler directive at the beginning of all overlaid units, and a `{F+}` compiler directive at the beginning of all other units and the main program.

**Note:** Failing to observe the FAR call requirement in an overlaid program will cause unpredictable and possibly catastrophic results when the program is executed.

The `{O unitname}` compiler directive is used in a program to indicate which units to overlay. This directive must be placed after the program's `uses` clause, and the `uses` clause must name the *Overlay* standard unit before any of the overlaid units. An example follows:

```
program Editor;  
  
  {F+}                                { Force FAR calls for all procedures & functions }
```

#### **uses**

```
Overlay, Crt, Dos, EdInOut, EdFormat, EdPrint, EdFind, EdMain;  
{ $O EdInOut }  
{ $O EdFormat }  
{ $O EdPrint }  
{ $O EdFind }  
{ $O EdMain }
```

**Note:** The compiler reports an error if you attempt to overlay a unit that wasn't compiled in the `{ $O+ }` state. Of the standard units, the only one that can be overlaid is *Dos*; the other standard units, *System*, *Overlay*, *Crt*, *Graph*, *Turbo3*, and *Graph3*, cannot be overlaid. In addition, programs containing overlaid units must be compiled to disk; the compiler reports an error if you attempt to compile such programs to memory.

## ***Constants and Variables***

---

The constants and variables defined by the *Overlay* unit are briefly discussed in this section.

### **The OvrResult Variable**

Before returning, each of the procedures in the *Overlay* unit stores a result code in the *OvrResult* variable.

```
var OvrResult: Integer;
```

The possible return codes are defined in the constant declaration in the next section. In general, a value of zero indicates success.

The *OvrResult* variable resembles the *IOResult* standard function except that *OvrResult* is *not* set to zero once it is accessed. Thus, there is no need to copy *OvrResult* into a local variable before it is examined.

### **Result Codes**

Errors in the *Overlay* unit are reported through the *OvrResult* variable. The following result codes are defined:



```

const
  ovrOk = 0;                                { Success }
  ovrError = -1;                             { Overlay manager error }
  ovrNotFound = -2;                          { Overlay file not found }
  ovrNoMemory = -3;                          { Not enough memory for overlay buffer }
  ovrIOError = -4;                           { Overlay file I/O error }
  ovrNoEMSDriver = -5;                       { EMS driver not installed }
  ovrNoEMSMemory = -6;                       { Not enough EMS memory }

```

## Procedures and Functions

---

The *Overlay* unit defines the procedures *OvrInit*, *OvrInitEMS*, *OvrSetBuf*, and *OvrClearBuf*, and the function *OvrGetBuf*. Here is a brief description of each; for more detailed information, see Chapter 8, "Procedures and Functions."

### OvrInit

```
procedure OvrInit(FileName:string);
```

Initializes the overlay manager and opens the overlay file. If the *FileName* parameter does not specify a drive or a subdirectory, the overlay manager searches for the file in the current directory, in the directory that contains the .EXE file (if running under DOS 3.x), and in the directories specified in the DOS PATH environment variable. Possible error return codes are *ovrError* and *ovrNotFound*. In case of error, the overlay manager remains uninstalled, and an attempt to call an overlaid routine will produce run-time error 208.

**Note:** The *OvrInit* procedure *must* be called before any of the other overlay manager procedures.

### OvrInitEMS

```
procedure OvrInitEMS;
```

If possible, loads the overlay file into EMS. If successful, the overlay file is closed, and all subsequent overlay loads are reduced to fast in-memory transfers. Possible error return codes are *ovrError*, *ovrIOError*, *ovrNoEMSDriver*, and *ovrNoEMSMemory*. The overlay manager will continue to function if *OvrInitEMS* returns an error, but overlays will be read from disk.

**Note:** Using *OvrInitEMS* to place the overlay file in EMS does not eliminate the need for an overlay buffer. Overlays still have to be copied from EMS

into “normal” memory in the overlay buffer before they can be executed. However, since such in-memory transfers are significantly faster than disk reads, the need to increase the size of the overlay buffer becomes less apparent.

## OvrSetBuf

```
procedure OvrSetBuf(Size:longint);
```

Sets the size of the overlay buffer. The specified size must be larger than or equal to the initial size of the overlay buffer, and less than or equal to *MemAvail* plus the current size of the overlay buffer. If the specified size is larger than the current size, additional space is allocated from the beginning of the heap (thus decreasing the size of the heap). Likewise, if the specified size is less than the current size, excess space is returned to the heap. *OvrSetBuf* requires that the heap be empty; an error is returned if dynamic variables have already been allocated using *New* or *GetMem*. Possible error return codes are *ovrError* and *ovrNoMemory*. The overlay manager will continue to function if *OvrSetBuf* returns an error, but the size of the overlay buffer will remain unchanged.

## OvrGetBuf

```
function OvrGetBuf:longint;
```

Returns the current size of the overlay buffer. Initially, the overlay buffer is as small as possible, corresponding to the size of the largest overlay. A buffer of this size is automatically allocated when an overlaid program is executed. (Note: The initial buffer size may be larger than 64K, since it includes both code and fix-up information for the largest overlay.)

## OvrClearBuf

```
procedure OvrClearBuf;
```

Clears the overlay buffer. All currently loaded overlays are disposed from the overlay buffer, forcing subsequent calls to overlaid routines to reload the overlays from the overlay file (or from EMS). If *OvrClearBuf* is called from an overlay, that overlay will immediately be reloaded upon return from *OvrClearBuf*. The overlay manager never requires you to call *OvrClearBuf*; in fact, doing so will decrease performance of your application, since it forces overlays to be reloaded. *OvrClearBuf* is solely intended for special use, such as temporarily reclaiming the memory occupied by the overlay buffer.

# Designing Overlaid Programs

---

This section provides some important information on designing programs with overlays. Look it over carefully, since a number of the issues discussed are vital to well-behaved overlaid applications.

## Overlay Code Generation

---

Turbo Pascal only allows a unit to be overlaid if it was compiled with `{O+}`. In this state, the code generator takes special precautions when passing string and set constant parameters from one overlaid procedure or function to another. For example, if *UnitA* contains a procedure with the following header:

```
procedure WriteStr(S: string);
```

and if *UnitB* contains the statement

```
WriteStr('Hello world...');
```

then Turbo Pascal places the string constant 'Hello world...' in *UnitB*'s code segment, and passes a pointer to it to the *WriteStr* procedure. However, if both units are overlaid, this would not work, since at the call to *WriteStr*, *UnitB*'s code segment may be overwritten by *UnitA*'s, thus rendering the string pointer invalid. The `{O+}` directive is used to avoid such problems; whenever Turbo Pascal detects a call from one unit compiled with `{O+}` to another unit compiled with `{O+}`, the compiler makes sure to copy all code-segment-based constants into stack temporaries before passing pointers to them.

The use of `{O+}` in a unit does not force you to overlay that unit. It just instructs Turbo Pascal to ensure that the unit can be overlaid, if so desired. If you develop units that you plan to use in overlaid as well as non-overlaid applications, then compiling them with `{O+}` ensures that you can indeed do both with just one version of the unit.

## The FAR Call Requirement

---

As mentioned previously, at any call to an overlaid procedure or function in another module, you *must* guarantee that all currently active procedures or functions use the FAR call model.

This is best illustrated by example: Assume that *OvrA* is a procedure in an overlaid unit, and that *MainB* and *MainC* are procedures in the main program. If the main program calls *MainC*, which calls *MainB*, which then calls *OvrA*, then at the call to *OvrA*, *MainB* and *MainC* are active (they have not

yet returned), and are thus required to use the FAR call model. Being declared in the main program, *MainB* and *MainC* would normally use the NEAR call model; in this case, though, a `{F+}` compiler directive must be used to force the FAR call model into effect.

The easiest way to satisfy the FAR call requirement is of course to place a `{F+}` directive at the beginning of the main program and each unit. Alternatively, you can change the default `$F` setting to `{F+}` using a `/F+` command-line directive (TPC.EXE) or the O/C/Force Far Calls menu command in the IDE. Compared to mixed NEAR and FAR calls, the added cost of FAR calls exclusively is usually quite limited: One extra word of stack space per active procedure, and one extra byte per call.

## *Initializing the Overlay Manager*

---

Here we'll take a look at some examples of how to initialize the overlay manager. The initialization code must be placed before the first call to an overlaid routine, and would typically be done at the beginning of the program's statement part.

The following piece of code shows just how little you need to initialize the overlay manager:

```
begin
  OvrInit('EDITOR.OVR');
end;
```

No error checks are made, so if there is not enough memory for the overlay buffer or if the overlay file was not found, run-time error 208 (Overlay manager not installed) will occur when you attempt to call an overlaid routine.

Here's another simple example that expands on the previous one:

```
begin
  OvrInit('EDITOR.OVR');
  OvrInitEMS;
end;
```

In this case, provided there is enough memory for the overlay buffer and that the overlay file can be located, the overlay manager checks to see if EMS memory is available and, if so, loads the overlay file into EMS.

As mentioned previously, the initial overlay buffer size is as small as possible, or rather, just big enough to contain the largest overlay. This may prove adequate for some applications, but imagine a situation where a particular function of a program is implemented through two or more units, each of which are overlaid. If the total size of those units is larger

than the largest overlay, a substantial amount of swapping will occur if the units make frequent calls to each other.

Obviously, the solution is to increase the size of the overlay buffer so that enough memory is available at any given time to contain all overlays that make frequent calls to each other. The following code demonstrates the use of *OvrSetBuf* to increase the overlay buffer size:

```
const
  OvrMaxSize = 80000;
begin
  OvrInit('EDITOR.OVR');
  OvrInitEMS;
  OvrSetBuf(OvrMaxSize);
end;
```

There is no general formula for determining the ideal overlay buffer size. Only an intimate knowledge of the application and a bit of experimenting will provide a suitable value.

**Note:** Using *OvrInitEMS* to place the overlay file in EMS does not eliminate the need for an overlay buffer. Overlays must still be copied from EMS into "normal" memory in the overlay buffer before they can be executed. However, since as such in-memory transfers are significantly faster than disk reads, the need to increase the size of the overlay buffer becomes less apparent.

Remember, *OvrSetBuf* will expand the overlay buffer by shrinking the heap. Therefore, the heap must be empty or *OvrSetBuf* will have no effect. If you are using the *Graph* unit, make sure you call *OvrSetBuf* before you call *InitGraph*, which allocates memory on the heap.

Here's a rather elaborate example of overlay manager initialization with full error-checking:

```
const
  OvrMaxSize = 80000;
var
  OvrName: string[79];
  Size: LongInt;
begin
  OvrName:='EDITOR.OVR';
  repeat
    OvrInit(OvrName);
    if OvrResult=ovrNotFound then
      begin
        WriteLn('Overlay file not found: ',OvrName,'.');
        Write('Enter correct overlay file name: ');
        ReadLn(OvrName);
      end;
  until OvrResult<>ovrNotFound;
```

```

if OvrResult<>ovrOk then
begin
  WriteLn('Overlay manager error.');
```

```

  Halt(1);
end;
OvrInitEMS;
if OvrResult<>OvrOK then
begin
  case OvrResult of
    ovrIOError:   Write('Overlay file I/O error');
```

```

    ovrNoEMSDriver: Write('EMS driver not installed');
```

```

    ovrNoEMSMemory: Write('Not enough EMS memory');
```

```

  end;
  Write('. Press Enter...');
```

```

  ReadLn;
end;
OvrSetBuf(OvrMaxSize);
end;

```

First, if the default overlay file name is not correct, the user is repeatedly prompted for a correct file name.

Next, a check is made for other errors that might have occurred during initialization. If an error is detected, the program halts, since errors in *OvrInit* are fatal. (If they are ignored, a run-time error will occur upon the first call to an overlaid routine.)

Assuming successful initialization, a call to *OvrInitEMS* is made to load the overlay file into EMS if possible. In case of error, a diagnostic message is displayed, but the program is not halted. Instead, it will just continue to read overlays from disk.

Finally, *OvrSetBuf* is called to set the overlay buffer size to a suitable value, determined through analysis and experimentation with the particular application. Errors from *OvrSetBuf* are ignored, although *OvrResult* might return an error code of -3 (*OvrNoMemory*). If there is not enough memory, the overlay manager will just continue to use the minimum buffer that was allocated when the program started.

## Initialization Sections in Overlaid Units

---

Like static units, overlaid units may have an initialization section. Although overlaid initialization code is no different from normal overlaid code, the overlay manager must be initialized first so it can load and execute overlaid units.

Referring to the earlier *Editor* program, assume that the *EdInOut* and *EdMain* units have initialization code. This requires that *OvrInit* is called

before *EdInOut*'s initialization code, and the only way to do that is to create an additional non-overlaid unit, which goes before *EdInOut* and calls *OvrInit* in its initialization section:

```
unit EdInit;
interface
implementation
uses Overlay;
const
    OvrMaxSize = 80000;
begin
    OvrInit('EDITOR.OVR');
    OvrInitEMS;
    OvrSetBuf(OvrMaxSize);
end.
```

The *EdInit* unit must be listed in the program's **uses** clause before any of the overlaid units:

```
program Editor;
{$F+}

uses
    Overlay, Crt, Dos, EdInit, EdInOut, EdFormat, EdPrint, EdFind, EdMain;

{$O EdInOut}
{$O EdFormat}
{$O EdPrint}
{$O EdFind}
{$O EdMain}
```

In general, although initialization code in overlaid units is indeed possible, it should be avoided for a number of reasons.

First, the initialization code, even though it is only executed once, is a part of the overlay, and will occupy overlay buffer space whenever the overlay is loaded. Second, if a number of overlaid units have initialization code, each of them will have to be read into memory when the program starts.

A much better approach is to gather all the initialization code into an overlaid initialization unit, which is called once at the beginning of the program, and then never referenced again.

## *What Not to Overlay*

---

Certain units cannot be overlaid. In particular, don't try to overlay the following:

- Units compiled in the {\$O-} state. The compiler reports an error if you attempt to overlay a unit that wasn't compiled with {\$O+}. Such non-overlay units include *System*, *Overlay*, *Crt*, *Graph*, *Turbo3*, and *Graph3*.
- Units that contain interrupt handlers. Due to the non-reentrant nature of the DOS operating system, units that implement **interrupt** procedures should not be overlaid. An example of such a unit is the *Crt* standard unit, which implements a *Ctrl-Break* interrupt handler.
- BGI drivers or fonts registered with calls to *RegisterBGIdriver* or *RegisterBGIfont*.

Calling overlaid routines via procedure pointers is fully supported by Turbo Pascal's overlay manager. Examples of the use of procedure pointers include exit procedures and text file device drivers.

Likewise, passing overlaid procedures and functions as procedural parameters, and assigning overlaid procedures and functions to procedural type variables is fully supported.

## Debugging Overlays

---

Most debuggers have very limited overlay debugging capabilities, if any at all. Not so with Turbo Pascal and Turbo Debugger. The integrated debugger fully supports single-stepping and breakpoints in overlays in a manner completely transparent to you. By using overlays, you can easily engineer and debug huge applications—all from inside the IDE or by using Turbo Debugger.

## External Routines in Overlays

---

Like normal Pascal procedures and functions, **external** assembly language routines must observe certain programming rules to work correctly with the overlay manager.

If an assembly language routine makes calls to *any* overlaid procedures or functions, the assembly language routine must use the FAR model, and it must set up a stack frame using the BP register. For example, assuming that *OtherProc* is an overlaid procedure in another unit, and that the assembly language routine *ExternProc* calls it, then *ExternProc* must be FAR and set up a stack frame as the following demonstrates:

ExternProc	PROC	FAR
PUSH	bp	;Save BP
mov	bp,sp	;Set up stack frame
SUB	sp,LocalSize	;Allocate local variables



```

...
CALL    OtherProc      ;Call another overlaid unit
...
mov     sp,bp          ;Dispose local variables
pop     bp             ;Restore BP
RET     ParamSize      ;Return
ExternProc      ENDP

```

where *LocalSize* is the size of the local variables, and *ParamSize* is the size of the parameters. If *LocalSize* is zero, the two lines to allocate and dispose local variables can be omitted.

These requirements are the same if *ExternProc* makes *indirect* references to overlaid procedures or functions. For example, if *OtherProc* makes calls to overlaid procedures or functions, but is not itself overlaid, *ExternProc* must still use the FAR model and still has to set up a stack frame.

In the case where an assembly language routine doesn't make any direct or indirect references to overlaid procedures or functions, there are no special requirements; the assembly language routine is free to use the NEAR model and it does not have to set up a stack frame.

Overlaid assembly language routines should *not* create variables in the code segment, since any modifications made to an overlaid code segment are lost when the overlay is disposed. Likewise, pointers to objects based in an overlaid code segment cannot be expected to remain valid across calls to other overlays, since the overlay manager freely moves around and disposes overlaid code segments.

## Using the 8087

There are two kinds of numbers you can work with in Turbo Pascal: integers (shortint, integer, longint, byte, word) and reals (real, single, double, extended, comp). Reals are also known as floating-point numbers. The 8086 processor is designed to easily handle integer values, but it takes considerably more time and effort to handle reals. To improve floating-point performance, the 8086 family of processors has a corresponding family of math coprocessors, the 8087s.

The 8087 is a special hardware numeric processor that can be installed in your PC. It executes floating-point instructions very quickly, so if you use floating point a lot, you'll probably want a coprocessor.

Turbo Pascal provides optimal floating-point performance whether or not you have an 8087.

- For programs running on any PC, with or without an 8087, Turbo Pascal provides the real type and an associated library of software routines that handle floating-point operations. The real type occupies 6 bytes of memory, providing a range of  $2.9 \times 10^{-39}$  to  $1.7 \times 10^{38}$  with 11 to 12 significant digits. The software floating-point library is optimized for speed and size, trading in some of the fancier features provided by the 8087 processor.
- If you need the added precision and flexibility of the 8087, you can instruct Turbo Pascal to produce code that uses the 8087 chip. This gives you access to four additional real types (single, double, extended, and comp), and an extended floating-point range of  $3.4 \times 10^{-4951}$  to  $1.1 \times 10^{4932}$  with 19 to 20 significant digits.

You switch between the two different models of floating-point code generation using the \$N compiler directive or the O/C/Numeric

Processing command. The default state is {\$N-}, and in this state, the compiler uses the 6-byte floating-point library, allowing you to operate only on variables of type real. In the {\$N+} state, the compiler generates code for the 8087, giving you increased precision and access to the four additional real types.

**Note:** When compiling in numeric processing mode, {\$N+}, the return values of the floating-point routines in the *System* unit (*Sqrt*, *Pi*, *Sin*, and so on) are of type extended instead of real:

```
{ $N+ }
begin
  Writeln(Pi);                                { 3.14159265358979E+0000 }
end.

{ $N- }
begin
  Writeln(Pi)                                { 3.1415926536E+00 }
end.
```

Even if you don't have an 8087 in your machine, you can instruct Turbo Pascal to include a run-time library that emulates the numeric coprocessor. In that case, if an 8087 is present, it is used. If it's not present, it is emulated by the run-time library, at the cost of running somewhat slower.

The \$E compiler directive and the O/C/Emulation menu are used to enable and disable 8087 emulation. The default state is {\$E+}, and in this state, the full 8087 emulator is automatically included in programs that use the 8087. In the {\$E-} state, a substantially smaller floating-point library is used, and the final .EXE file can only be run on machines with an 8087.

**Note:** The \$E compiler directive has no effect if used in a unit; it only applies to the compilation of a program. Furthermore, if the program is compiled in the {\$N-} state, and if all the units used by the program were compiled with {\$N-}, then an 8087 run-time library is not required, and the \$E compiler directive is ignored.

The remainder of this chapter discusses special issues concerning Turbo Pascal programs that use the 8087 coprocessor.

## The 8087 Data Types

---

For programs that use the 8087, Turbo Pascal provides four floating-point types in addition to the type real.

- The single type is the smallest format you can use with floating-point numbers. It occupies 4 bytes of memory, providing a range of  $1.5 \times 10^{-45}$  to  $3.4 \times 10^{38}$  with 7 to 8 significant digits.

- The double type occupies 8 bytes of memory, providing a range of  $5.0 \times 10^{-324}$  to  $1.7 \times 10^{308}$  with 15 to 16 significant digits.
- The extended type is the largest floating-point type supported by the 8087. It occupies 10 bytes of memory, providing a range of  $3.4 \times 10^{-4932}$  to  $1.1 \times 10^{4932}$  with 19 to 20 significant digits. Any arithmetic involving real-type values is performed with the range and precision of the extended type.
- The comp type stores integral values in 8 bytes, providing a range of  $-2^{63}+1$  to  $2^{63}-1$ , which is approximately  $-9.2 \times 10^{18}$  to  $9.2 \times 10^{18}$ . Comp may be compared to a double-precision longint, but it is considered a real type because all arithmetic done with comp uses the 8087 coprocessor. Comp is well suited for representing monetary values as integral values of cents or mils (thousandths) in business applications.

Whether or not you have an 8087, the 6-byte real type is always available, so you need not modify your source code when switching to the 8087, and you can still read data files generated by programs that use software floating point.

Note, however, that 8087 floating-point calculations on variables of type real are slightly slower than on other types. This is because the 8087 cannot directly process the real format—instead, calls must be made to library routines to convert real values to extended before operating on them. If you are concerned with optimum speed and never need to run on a system without an 8087, you may want to use the single, double, extended, and comp types exclusively.

## Extended Range Arithmetic

---

The extended type is the basis of all floating-point computations with the 8087. Turbo Pascal uses the extended format to store all non-integer numeric constants and evaluates all non-integer numeric expressions using extended precision. The entire right side of the following assignment, for instance, will be computed in extended before being converted to the type on the left side:

```
{N+}
var
  X,A,B,C : real;
begin
  X := (B + Sqrt(B * B - A * C)) / A;
end;
```

With no special effort by the programmer, Turbo Pascal performs computations using the precision and range of the extended type. The added

precision means smaller round-off errors, and the additional range means overflow and underflow are less common.

You can go beyond Turbo Pascal's automatic *extended* capabilities. For example, you can declare variables used for intermediate results to be of type extended. The following example computes a sum of products:

```
var
  Sum : single;
  X,Y : array[1..100] of single;
  I   : integer;
  T   : extended;                                { For intermediate results }
begin
  T := 0.0;
  for I := 1 to 100 do T := T + X[I] * Y[I];
  Sum := T;
end;
```

Had *T* been declared single, the assignment to *T* would have caused a round-off error at the limit of single precision at each loop entry. But because *T* is extended, all round-off errors are at the limit of extended precision, except for the one resulting from the assignment of *T* to *Sum*. Fewer round-off errors mean more accurate results.

You can also declare formal value parameters and function results to be of type extended. This avoids unnecessary conversions between numeric types, which can result in loss of accuracy. For example,

```
function Area(Radius: extended): extended;
begin
  Area := Pi * Radius * Radius;
end;
```

## Comparing Reals

---

Because real-type values are approximations, the results of comparing values of different real types are not always as expected. For example, if *X* is a variable of type single and *Y* is a variable of type double, then the following statements will output False:

```
X := 1/3;
Y := 1/3;
Writeln(X = Y);
```

The reason is that *X* is accurate only to 7 to 8 digits, where *Y* is accurate to 15 to 16 digits, and when both are converted to extended, they will differ after 7 to 8 digits. Similarly, the statements

```
X := 1/3;
```

```
Writeln(X = 1/3);
```

will output *False*, since the result of  $1/3$  in the *Writeln* statement is calculated with 20 significant digits.

## The 8087 Evaluation Stack

---

The 8087 coprocessor has an internal evaluation stack that can be up to eight levels deep. Accessing a value on the 8087 stack is much faster than accessing a variable in memory; so to achieve the best possible performance, Turbo Pascal uses the 8087's stack for storing temporary results.

In theory, very complicated real-type expressions can cause an 8087 stack overflow. However, this is not likely to occur, since it would require the expression to generate more than eight temporary results.

A more tangible danger lies in recursive function calls. If such constructs are not coded correctly, they can very well cause an 8087 stack overflow.

Consider the following procedure that calculates Fibonacci numbers using recursion:

```
function Fib(N: integer): extended;
begin
  if N = 0 then
    Fib := 0.0
  else
    if N = 1 then
      Fib := 1.0
    else
      Fib := Fib(N-1) + Fib(N-2);
end;
```

A call to this version of *Fib* will cause an 8087 stack overflow for values of *N* larger than 8. The reason is that the calculation of the last assignment requires a temporary on the 8087 stack to store the result of *Fib(N-1)*. Each recursive invocation allocates one such temporary, causing an overflow the ninth time. The correct construct in this case is

```
function Fib(N: integer): extended;
var
  F1, F2: extended;
begin
  if N = 0 then
    Fib := 0.0
  else
    if N = 1 then
      Fib := 1.0
    else
      F1 := Fib(N-1);
      F2 := Fib(N-2);
      Fib := F1 + F2;
```

```

begin
  F1 := Fib(N-1); F2 := Fib(N-2);
  Fib := F1 + F2;
end;
end;

```

The temporary results are now stored in variables allocated on the 8086 stack. (The 8086 stack can of course also overflow, but this would typically require significantly more recursive calls.)

## Writing Reals with the 8087

---

In the  $\{N+\}$  state, the *Write* and *Writeln* standard procedures output four digits, not two, for the exponent in a floating-point decimal string to provide for the extended numeric range. Likewise, the *Str* standard procedure returns a four-digit exponent when floating-point format is selected.

## Units Using the 8087

---

Units that use the 8087 can only be used by other units or programs that are compiled in the  $\{N+\}$  state.

The fact that a unit uses the 8087 is determined by whether it contains 8087 instructions—not by the state of the  $\$N$  compiler directive at the time of its compilation. This makes the compiler more forgiving in cases where you accidentally compile a unit (that doesn't use the 8087) in the  $\{N+\}$  state.

## Detecting the 8087

---

The Turbo Pascal 8087 run-time library built into your program (compiled with  $\{N+\}$ ) includes startup code that automatically detects the presence of an 8087 chip. If an 8087 is available, then the program will use it. If one is not present, the program will use the emulation run-time library. If the program was compiled in the  $\{E-\}$  state, and an 8087 could not be detected at startup, the program displays `Numeric coprocessor required`, and terminates.

There are some instances in which you might want to override this default autodetection behavior. For example, your own system may have an 8087, but you want to verify that your program will work as intended on systems without a coprocessor. Or your program may need to run on a PC-compatible system, but that particular system returns incorrect information

to the autodetection logic (saying that an 8087 is present when it's not, or vice versa).

Turbo Pascal provides an option for overriding the startup code's default autodetection logic; this option is the 87 environment variable.

You set the 87 environment variable at the DOS prompt with the SET command, like this:

```
SET 87=Y
```

or

```
SET 87=N
```

Setting the 87 environment variable to *N* (for no) tells the startup code that you do not want to use the 8087, even though it might be present in the system. Conversely, setting the 87 environment variable to *Y* (for yes) means that the coprocessor is there, and you want the program to use it. **Beware:** If you set 87=Y when, in fact, there is no 8087 available, your program will either crash or hang!

If the 87 environment variable has been defined (to any value) but you want to undefine it, enter

```
SET 87=
```

at the DOS prompt and then press *Enter* immediately.

If an 87=Y entry is present in the DOS environment, or if the autodetection logic succeeds in detecting a coprocessor, the startup code executes further checks to determine what kind of coprocessor it is (8087, 80287, or 80387). This is required so that Turbo Pascal can correctly handle certain incompatibilities that exist between the different coprocessors.

The result of the autodetection and the coprocessor classification is stored in the *Test8087* variable (which is declared by the *System* unit). The following values are defined:

```
0 = No coprocessor detected
1 = 8087 detected
2 = 80287 detected
3 = 80387 detected
```

Your program may examine the *Test8087* variable to determine the characteristics of the system it is running on. In particular, *Test8087* may be examined to determine whether floating-point instructions are being emulated or truly executed.



## *Using 8087 Emulation in Assembly Language*

---

When linking in object files using *(\$L filename)* directives, make sure that these object files were compiled with the 8087 emulation enabled. For example, if you are using 8087 instructions in assembly language **external** procedures, make sure to enable emulation when you assemble the .ASM files into .OBJ files. Otherwise, the 8087 instructions cannot be emulated on machines without an 8087. Use Turbo Assembler's */E* command-line switch to enable emulation.

## Inside Turbo Pascal

In this chapter, we provide technical information for advanced Turbo Pascal programmers. We'll cover such topics as memory maps, the heap manager, internal data formats, calling conventions, and more.

Figure 15.1 (on page 180) depicts the memory map of a Turbo Pascal program.

The Program Segment Prefix (PSP) is a 256-byte area built by MS-DOS when the .EXE file is loaded. The segment address of PSP is stored in the predeclared word variable *PrefixSeg*.

Each module (which includes the main program and each unit) has its own code segment. The main program occupies the first code segment; the code segments that follow it are occupied by the units (in reverse order from how they are listed in the **uses** clause), and the last code segment is occupied by the run-time library (the *System* unit). The size of a single code segment cannot exceed 64K, but the total size of the code is limited only by the available memory.




Figure 15.1: Turbo Pascal Memory Map

The data segment (addressed through DS) contains all typed constants followed by all global variables. The DS register is never changed during program execution. The size of the data segment cannot exceed 64K.

On entry to the program, the stack segment register (SS) and the stack pointer (SP) are loaded so that SS:SP points to the first byte past the stack

segment. The SS register is never changed during program execution, but SP can move downward until it reaches the bottom of the segment. The size of the stack segment cannot exceed 64K; the default size is 16K, but this can be changed with a \$M compiler directive.

The overlay buffer is used by the *Overlay* standard unit to store overlaid code. The default size of the overlay buffer corresponds to the size of the largest overlay in the program; if the program has no overlays, the size of the overlay buffer is zero. The size of the overlay buffer can be increased through a call to the *OvrSetBuf* routine in the *Overlay* unit; in that case, the size of the heap is decreased accordingly, by moving *HeapOrg* upwards.

The heap stores *dynamic variables*, that is, variables allocated through calls to the *New* and *GetMem* standard procedures. It occupies all or some of the free memory left when a program is executed. The actual size of the heap depends on the minimum and maximum heap values, which can be set with the \$M compiler directive. Its size is guaranteed to be at least the minimum heap size and never more than the maximum heap size. If the minimum amount of memory is not available, the program will not execute. The default heap minimum is 0 bytes, and the default heap maximum is 640 Kb; this means that by default the heap will occupy all remaining memory.

As you might expect, the heap manager (which is part of Turbo Pascal's run-time library) manages the heap. It is described in detail in the following section.

## The Heap Manager

---

The heap is a stack-like structure that grows from low memory in the heap segment. The bottom of the heap is stored in the variable *HeapOrg*, and the top of the heap, corresponding to the bottom of free memory, is stored in the variable *HeapPtr*. Each time a dynamic variable is allocated on the heap (via *New* or *GetMem*), the heap manager moves *HeapPtr* upward by the size of the variable, in effect stacking the dynamic variables on top of each other.

*HeapPtr* is always normalized after each operation, thus forcing the offset part into the range \$0000 to \$000F. The maximum size of a single variable that can be allocated on the heap is 65519 bytes (corresponding to \$10000 minus \$000F), since every variable must be completely contained in a single segment.

## Disposal Methods

The dynamic variables stored on the heap are disposed of in one of two ways: (1) through *Dispose* or *FreeMem* or (2) through *Mark* and *Release*. The simplest scheme is that of *Mark* and *Release*; for example, if the following statements are executed:

```
New(Ptr1);  
New(Ptr2);  
Mark(P);  
New(Ptr3);  
New(Ptr4);  
New(Ptr5);
```

the layout of the heap will then look like Figure 15.2.




Figure 15.2: Disposal Method Using Mark and Release

The *Mark(P)* statement marks the state of the heap just before *Ptr3* is allocated (by storing the current *HeapPtr* in *P*). If the statement *Release(P)* is executed, the heap layout becomes like that of Figure 15.3, effectively disposing of all pointers allocated since the call to *Mark*.




Figure 15.3: Heap Layout with `Release(P)` Executed

**Note:** Executing `Release(HeapOrg)` completely disposes of the entire heap because `HeapOrg` points to the bottom of the heap.

For applications that dispose of pointers in exactly the reverse order of allocation, the *Mark* and *Release* procedures are very efficient. Yet most programs tend to allocate and dispose of pointers in a more random manner, requiring the more-sophisticated management technique implemented by *Dispose* and *FreeMem*. These procedures allow an application to dispose of any pointer at any time.

When a dynamic variable that is not the topmost variable on the heap is disposed of through *Dispose* or *FreeMem*, the heap becomes fragmented. Assuming that the same statement sequence has been executed, then after executing `Dispose(Ptr3)`, a "hole" is created in the middle of the heap (see Figure 15.4).




Figure 15.4: Creating a "Hole" in the Heap

If at this time *New(Ptr3)* has been executed, it would again occupy the same memory area. On the other hand, executing *Dispose(Ptr4)* enlarges the free block, since *Ptr3* and *Ptr4* were neighboring blocks (see Figure 15.5).




Figure 15.5: Enlarging the Free Block

Finally, executing *Dispose(Ptr5)* first creates an even bigger free block, and then lowers *HeapPtr*. This, in effect, releases the free block, since the last valid pointer is now *Ptr2* (see Figure 15.6).




Figure 15.6: Releasing the Free Block

The heap is now in the same state as it would be after executing *Release(P)*, as shown in Figure 15.3. However, the free blocks created and destroyed in the process were tracked for possible reuse.

## The Free List

The addresses and sizes of the free blocks generated by *Dispose* and *FreeMem* operations are kept on a *free list*, which grows downward from high memory in the heap segment. Whenever a dynamic variable is allocated, the free list is checked before the heap is expanded. If a free block of adequate size (greater than or equal to the size of the requested block size) exists, it is used.

**Note:** The *Release* procedure always clears the free list, thus causing the heap manager to “forget” about any free blocks that might exist below the heap pointer. If you mix calls to *Mark* and *Release* with calls to *Dispose* and *FreeMem*, you must ensure that no such free blocks exist.

The free list pointer is stored in a variable called *FreePtr*. Although declared to be of type *pointer*, *FreePtr* is actually a pointer to an array of free-list records, as indicated by the *FreeListP* type:

```
type
  FreeRec   = record
    OrgPtr, EndPtr: pointer;
  end;
  FreeList = array[0..8190] of FreeRec;
```



```
FreeListP = ^FreeList;
```

The *OrgPtr* and *EndPtr* fields of each record define the origin and end of each free block. (*EndPtr* is in fact a pointer to the first byte after the block.) Both are normalized pointers. The number of entries in the *FreeList* array is calculated from

```
FreeCount = (8192 - Ofc(FreePtr^) div 8) mod 8192
```

This means that there can be up to 8191 entries in the free list. When the offset part of *FreePtr* is 0, the free list is empty. *FreePtr* can be compared to the stack pointer in the sense that it grows downward, and that all bytes from *FreePtr* to the end of the heap segment are part of the “free stack.”

**Note:** Trying to dispose of a pointer when the free list is full causes a run-time error. However, a full free list is a highly unlikely situation—it would require 8191 completely noncontiguous blocks to be disposed of and not reused.

*FreePtr* also serves to mark the top of free memory in the heap (the bottom of which is pointed to by *HeapPtr*). Note, though, that when the offset part of *FreePtr* is 0, \$1000 must be added to the segment part to produce the true top-of-heap pointer. (In fact, the segment part of *FreePtr* always contains the segment address of top-of-memory minus \$1000.)

When disposing of a range of noncontiguous pointers, the free list grows (expands downward) to make room for an entry for each block. As long as there is enough room between *HeapPtr* and *FreePtr*, this presents no problem. However, when the heap is almost full, there may not be enough room to cater to the larger free list, in which case a run-time error will occur.

In particular, imagine that the free list is empty and that the heap is almost full. In that situation, disposing of a range of pointers other than the topmost pointer will cause a block expansion of the free list.

To prevent, or foresee, such problems, the heap manager provides a word variable *FreeMin* that can be set to control the minimum allowable size of the memory region between *HeapPtr* and *FreePtr*. You cannot use *New* or *GetMem* to allocate a variable that would make the size of that region less than *FreeMin*. Likewise, *MemAvail* and *MaxAvail* will subtract *FreeMin* from the size of that region before returning their results.

The value stored in *FreeMin* is in bytes. To ensure room for a specific number of free-list entries, multiply that number by 8 and store it in *FreeMin*.

A final note on the free list concerns a potential problem with “granularity.” The granularity of Turbo Pascal’s heap manager is 1 byte; that is, if you allocate 1 byte, it will only occupy that 1 byte. In most situations, and

especially when using *Mark* and *Release* or when not disposing of anything at all, this guarantees optimum use of the memory available. However, it can also be deceiving.

When randomly allocating and disposing of a lot of blocks of differing sizes, such as line records in a text-processing program, a number of very small free blocks can result and possibly cause the free list to overflow. As an example, assume a block of 50 bytes is allocated and disposed of, thus becoming an entry on the free list. If the next allocation request is for a block of 49 bytes, that block will be reused, leaving a 1-byte free block entry on the free list. Until one of the neighboring blocks are disposed of (thereby merging the 1-byte block into a bigger block), the 1-byte block is very unlikely to become reallocated. Thus, it will occupy a free-list entry for a long time, if not for the program's duration.

If a free list overflow occurs because of this, you can introduce a "resolution factor" to round upward the size specified by each call to *GetMem* and *FreeMem* to a factor of some number. In general, the higher the number, the less likely unusable free blocks will occur. To do this you would write your own *GetMem* and *FreeMem* routines that would modify the *Size* parameter and then call *System.GetMem* or *System.FreeMem*:

```
procedure GetMem(var P : pointer; Size : word);
begin
  System.GetMem(P, (Size + 15) and $FFF0);           { 16 byte blocks }
end;

procedure FreeMem(var P : pointer; Size : word);
begin
  System.FreeMem(P, (Size + 15) and $FFF0);          { 16 byte blocks }
end;
```

## *The Heap Error Function*

---

The *HeapError* variable allows you to install a heap error function, which gets called whenever the heap manager cannot complete an allocation request. *HeapError* is a pointer that points to a function with the following header:

```
{F+} function HeapFunc(Size: word): integer; {F-}
```

Note that the {F+} compiler directive forces the heap error function to use the FAR call model.

The heap error function is installed by assigning its address to the *HeapError* variable:

```
HeapError:=@HeapFunc;
```

The heap error function gets called whenever a call to *New* or *GetMem* cannot complete the request. The *Size* parameter contains the size of the block that could not be allocated, and the heap error function should attempt to free a block of at least that size.

Depending on its success, the heap error function should return 0, 1, or 2. A return of 0 indicates failure, causing a run-time error to occur immediately. A return of 1 also indicates failure, but instead of a run-time error, it causes *New* or *GetMem* to return a nil pointer. Finally, a return of 2 indicates success and causes a retry (which could also cause another call to the heap error function).

The standard heap error function always returns 0, thus causing a run-time error whenever a call to *New* or *GetMem* cannot be completed. However, for many applications, the simple heap error function that follows is more appropriate:

```
($F+) function HeapFunc(Size: word) : integer; {$F-}  
begin  
    HeapFunc:=1;  
end;
```

When installed, this function causes *New* or *GetMem* to return nil when they cannot complete the request, instead of aborting the program.

## Internal Data Formats

---

### *Integer Types*

---

The format selected to represent an integer-type variable depends on its minimum and maximum bounds:

- If both bounds are within the range -128..127 (shortint), the variable is stored as a signed byte.
- If both bounds are within the range 0..255 (byte), the variable is stored as an unsigned byte.
- If both bounds are within the range -32768..32767 (integer), the variable is stored as a signed word.
- If both bounds are within the range 0..65535 (word), the variable is stored as an unsigned word.
- Otherwise, the variable is stored as a signed double word (longint).

## *Char Types*

---

A char, or a subrange of a char type, is stored as an unsigned byte.

## *Boolean Types*

---

A boolean type is stored as a byte that can assume the value of 0 (False) or 1 (True).

## *Enumerated Types*

---

An enumerated type is stored as an unsigned byte if the enumeration has 256 or fewer values; otherwise, it is stored as an unsigned word.

## *Floating-Point Types*

---

The floating-point types (real, single, double, extended, and comp) store the binary representations of a sign (+ or -), an *exponent*, and a *significand*. A represented number has the value


$$\pm \text{significand} \times 2^{\text{exponent}}$$

where the significand has a single bit to the left of the binary decimal point (that is,  $0 \leq \text{significand} < 2$ ).

**Note:** In the figures that follow, *msb* means most significant bit, and *lsb* means least significant bit. The leftmost items are stored at the highest addresses. For example, for a real-type value, *e* is stored in the first byte, *f* in the following five bytes, and *s* in the most significant bit of the last byte.

## *The Real Type*

A 6-byte (48-bit) *Real* number is divided into three fields:



The value  $v$  of the number is determined by

```


if 0 < e <= 255, then v = (-1)s * 2(e-129) * (1.f).
if e = 0, then v = 0.

```

**Note:** The real type cannot store denormals, NaNs, and infinities. Denormals become zero when stored in a real, and NaNs and infinities produce an overflow error if an attempt is made to store them in a real.

## The Single Type

A 4-byte (32-bit) *Single* number is divided into three fields:



The value  $v$  of the number is determined by


```

if 0 < e < 255,      then v = (-1)s * 2(e-127) * (1.f).
if e = 0 and f <> 0, then v = (-1)s * 2(-126) * (0.f).
if e = 0 and f = 0,  then v = (-1)s * 0.
if e = 255 and f = 0, then v = (-1)s * Inf.
if e = 255 and f <> 0, then v is a NaN.

```

## The Double Type

An 8-byte (64-bit) *Double* number is divided into three fields:



The value  $v$  of the number is determined by


```

if 0 < e < 2047,      then v = (-1)s * 2(e-1023) * (1.f).
if e = 0 and f > 0, then v = (-1)s * 2(-1022) * (0.f).
if e = 0 and f = 0, then v = (-1)s * 0.
if e = 2047 and f = 0, then v = (-1)s * Inf.
if e = 2047 and f > 0, then v is a NaN.

```

## The Extended Type

A 10-byte (80-bit) *Extended* number is divided into four fields:



The value  $v$  of the number is determined by


```

if 0 <= e < 32767,      then v = (-1)s * 2(e-16383) * (i.f).
if e = 32767 and f = 0, then v = (-1)s * Inf.
if e = 32767 and f > 0, then v is a NaN.

```

## The Comp Type

An 8-byte (64-bit) *Comp* number is divided into two fields:



The value  $v$  of the number is determined by

**if**  $s = 1$  **and**  $d = 0$ , **then**  $v$  is a NaN

Otherwise,  $v$  is the two's complement 64-bit value.

## Pointer Types

---

A pointer type is stored as a double word, with the offset part in the low word and the segment part in the high word. The pointer value `nil` is stored as a double-word zero.

## String Types

---

A string occupies as many bytes as its maximum length plus one. The first byte contains the current dynamic length of the string, and the following bytes contain the characters of the string. The length byte and the characters are considered unsigned values. Maximum string length is 255 characters plus a length byte (`string[255]`).

## Set Types

---

A set is a bit array, where each bit indicates whether an element is in the set or not. The maximum number of elements in a set is 256, so a set never occupies more than 32 bytes. The number of bytes occupied by a particular set is calculated as

$$\text{ByteSize} = (\text{Max} \text{ div } 8) - (\text{Min} \text{ div } 8) + 1$$

where *Min* and *Max* are the lower and upper bounds of the base type of that set. The byte number of a specific element *E* is

$$\text{ByteNumber} = (E \text{ div } 8) - (\text{Min} \text{ div } 8)$$

and the bit number within that byte is

$$\text{BitNumber} = E \bmod 8$$

where  $E$  denotes the ordinal value of the element.

## *Array Types*

---

An array is stored as a contiguous sequence of variables of the component type of the array. The components with the lowest indexes are stored at the lowest memory addresses. A multidimensional array is stored with the rightmost dimension increasing first.

## *Record Types*

---

The fields of a record are stored as a contiguous sequence of variables. The first field is stored at the lowest memory address. If the record contains variant parts, then each variant starts at the same memory address.

## *File Types*

---

File types are represented as records. Typed files and untyped files occupy 128 bytes, which are laid out as follows:

```
type
  FileRec = record
    Handle   : word;
    Mode     : word;
    RecSize  : word;
    Private  : array[1..26] of byte;
    UserData : array[1..16] of byte;
    Name     : array[0..79] of char;
  end;
```

Text files occupy 256 bytes, which are laid out as follows:

```
type
  TextBuf = array[0..127] of char;
  TextRec = record
    Handle   : word;
    Mode     : word;
    BufSize  : word;
    Private  : word;
    BufPos   : word;
    BufEnd   : word;
    BufPtr   : ^TextBuf;
```



```

    OpenFunc : pointer;
    InOutFunc: pointer;
    FlushFunc: pointer;
    CloseFunc: pointer;
    UserData : array[1..16] of byte;
    Name      : array[0..79] of char;
    Buffer     : TextBuf;
end;

```

*Handle* contains the file's handle (when open) as returned by MS-DOS.

The *Mode* field can assume one of the following "magic" values:

```

const
    fmClosed = $D7B0;
    fmInput  = $D7B1;
    fmOutput = $D7B2;
    fmInOut  = $D7B3;

```

*fmClosed* indicates that the file is closed. *fmInput* and *fmOutput* indicate that the file is a text file that has been reset (*fmInput*) or rewritten (*fmOutput*). *fmInOut* indicates that the file variable is a typed or an untyped file that has been reset or rewritten. Any other value indicates that the file variable has not been assigned (and thereby not initialized).

The *UserData* field is never accessed by Turbo Pascal, and is free for user-written routines to store data in.

*Name* contains the file name, which is a sequence of characters terminated by a null character (#0).

For typed files and untyped files, *RecSize* contains the record length in bytes, and the *Private* field is unused but reserved.

For text files, *BufPtr* is a pointer to a buffer of *BufSize* bytes, *BufPos* is the index of the next character in the buffer to read or write, and *BufEnd* is a count of valid characters in the buffer. *OpenFunc*, *InOutFunc*, *FlushFunc*, and *CloseFunc* are pointers to the I/O routines that control the file. The upcoming section entitled "Text File Device Drivers" provides information on that subject.

## *Procedural Types*

---

A procedural type is stored as a double word, with the offset part of the referenced procedure in the low word and the segment part in the high word.

# Calling Conventions

---

Parameters are transferred to procedures and functions via the stack. Before calling a procedure or function, the parameters are pushed onto the stack in their order of declaration. Before returning, the procedure or function removes all parameters from the stack.

The skeleton code for a procedure or function call looks like this:

```
PUSH  Param1
PUSH  Param2
:
PUSH  ParamX
CALL  ProcOrFunc
```

Parameters are passed either by *reference* or by *value*. When a parameter is passed by reference, a pointer that points to the actual storage location is pushed onto the stack. When a parameter is passed by value, the actual value is pushed onto the stack.

## Variable Parameters

---

Variable parameters (**var** parameters) are always passed by reference—a pointer points to the actual storage location.

## Value Parameters

---

Value parameters are passed by value or by reference depending on the type and size of the parameter. In general, if the value parameter occupies 1, 2, or 4 bytes, the value is pushed directly onto the stack. Otherwise a pointer to the value is pushed, and the procedure or function then copies the value into a local storage location.

**Note:** The 8086 does not support byte-sized PUSH and POP instructions, so byte-sized parameters are always transferred onto the stack as words. The low-order byte of the word contains the value, and the high-order byte is unused (and undefined).

An integer type or parameter is passed as a byte, a word, or a double word, using the same format as an integer-type variable. (For double words, the high-order word is pushed before the low-order word so that the low-order word ends up at the lowest address.)

A char-type parameter is passed as an unsigned byte.

A boolean-type parameter is passed as a byte with the value 0 or 1.

An enumerated-type parameter is passed as an unsigned byte if the enumeration has 256 or fewer values; otherwise it is passed as an unsigned word.

A real-type parameter (type real) is passed as 6 bytes on the stack, thus being an exception to the rule that only 1, 2, and 4 byte values are passed directly on the stack.

A floating-point type parameter (real, single, double, extended, and comp) is passed as 4, 6, 8, or 10 bytes on the stack, thus being an exception to the rule that only 1, 2, and 4-byte values are passed directly on the stack.

**Note:** Version 4.0 of Turbo Pascal passed 8087-type parameters (single, double, extended, and comp) on the internal stack of the 8087 numeric coprocessor. For reasons of compatibility with other languages, and to avoid 8087 stack overflows, Version 5.0 uses the 8086 stack.

A pointer-type parameter is passed as a double word (the segment part is pushed before the offset part so that the offset part ends up at the lowest address).

A string-type parameter is passed as a pointer to the value.

A set-type parameter is passed as a pointer to an "unpacked" set that occupies 32 bytes.

Arrays and records with 1, 2, or 4 bytes are passed directly onto the stack. Other arrays and records are passed as pointers to the value.

## ***Function Results***

---

Ordinal-type function results (integer, char, boolean, and enumeration types) are returned in the CPU registers: Bytes are returned in AL, words are returned in AX, and double words are returned in DX:AX (high-order word in DX, low-order word in AX).

Real-type function results (type real) are returned in the DX:BX:AX registers (high-order word in DX, middle word in BX, low-order word in AX).

8087-type function results (type single, double, extended, and comp) are returned in the 8087 coprocessor's top-of-stack register (ST(0)).

Pointer-type function results are returned in DX:AX (segment part in DX, offset part in AX).

For a string-type function result, the caller pushes a pointer to a temporary storage location before pushing any parameters, and the function returns a string value in that temporary location. The function must not remove the pointer.

## *NEAR and FAR Calls*

---

The 8086 CPU supports two kinds of call and return instructions: *NEAR* and *FAR*. The *NEAR* instructions transfer control to another location within the same code segment, and the *FAR* instructions allow a change of code segment.

A *NEAR CALL* instruction pushes a 16-bit return address (offset only) onto the stack, and a *FAR CALL* instruction pushes a 32-bit return address (both segment and offset). The corresponding *RET* instructions pop only an offset or both an offset and a segment.

Turbo Pascal will automatically select the correct call model based on the procedure's declaration. Procedures declared in the **interface** section of a unit are *FAR*—they can be called from other units. Procedures declared in a program or in the **implementation** section of a unit are *NEAR*—they can only be called from within that program or unit.

For some specific purposes, a procedure may be required to be *FAR*. For example, in an overlaid application, all procedures and functions are generally required to be *FAR*; likewise, if a procedure or function is to be assigned to a procedural variable, it has to be *FAR*. The *\$F* compiler directive is used to override the compiler's automatic call model selection. Procedures and functions compiled in the *{\$F+}* state are always *FAR*; in the *{\$F-}* state, Turbo Pascal automatically selects the correct model. The default state is *{\$F-}*.

## *Nested Procedures and Functions*

---

A procedure or function is said to be nested when it is declared within another procedure or function. By default, nested procedures and functions always use the *NEAR* call model, since they are only "visible" within a specific procedure or function in the same code segment. However, in an overlaid application, a *{\$F+}* directive is generally used to force all procedures and functions to be *FAR*, including those that are nested.

When calling a nested procedure or function, the compiler generates a *PUSH BP* instruction just before the *CALL*, in effect passing the caller's *BP* as an additional parameter. Once the called procedure has set up its own *BP*, the caller's *BP* is accessible as a word stored at *[BP+4]*, or at *[BP+6]* if the procedure is *FAR*. Using this link at *[BP+4]* or *[BP+6]*, the called procedure can access the local variables in the caller's stack frame. If the caller itself is also a nested procedure, it also has a link at *[BP+4]* or *[BP+6]*, and so on. The following example demonstrates how to access local variables from an *inline* statement in a nested procedure:

```

{$F-}
procedure PA;
var IntA: integer;
{$F+}
procedure B;
var IntB: integer;
{$F-}
procedure C;
var IntC: integer;
begin
  inline(
    $8B/$46/<IntC/      { MOV AX,[BP+IntC]      ;AX = IntC }
    $8B/$5E/$04/        { MOV BX,[BP+4]        ;BX = B's stack frame }
    $36/$8B/$47/<IntB/   { MOV AX,SS:[BX+IntB]   ;AX = IntB }
    $8B/$5E/$04/        { MOV BX,[BP+4]        ;BX = B's stack frame }
    $36/$8B/$5F/$06/     { MOV BX,SS:[BX+6]     ;BX = A's stack frame }
    $36/$8B/$47/<IntA); { MOV AX,SS:[BX+IntA]   ;AX = IntA }
  end;
begin end;
begin end;

```

**Note:** Nested procedures and functions cannot be declared with the **external** directive, and they cannot be procedural parameters.

## Entry and Exit Code

---

Each Pascal procedure and function begins and ends with standard entry and exit code that creates and removes its activation.

The standard entry code is

```

push bp           ;Save BP
mov bp,sp         ;Set up stack frame
sub sp,LocalSize  ;Allocate local variables

```

where *LocalSize* is the size of the local variables. The **SUB** instruction is only present if *LocalSize* is not 0. If the procedure's call model is **NEAR**, the parameters start at BP + 4; if it is **FAR**, they start at BP + 6.

The standard exit code is

```

mov sp,bp         ;Deallocate local variables
pop bp           ;Restore BP
ret ParamSize     ;Remove parameters and return

```

where *ParamSize* is the size of the parameters. The **RET** instruction is either a **NEAR** or a **FAR** return, depending on the procedure's call model.

## Register-Saving Conventions

---

Procedures and functions should preserve the BP, SP, SS, and DS registers. All other registers may be modified.

## Linking with Assembly Language

---

Procedures and functions written in assembly language can be linked with Turbo Pascal programs or units using the `$L` compiler directive. The assembly language source file must be assembled into an object file (extension `.OBJ`) using an assembler like Turbo Assembler. Multiple object files can be linked with a program or unit through multiple `$L` directives.

Procedures and functions written in assembly language must be declared as **external** in the Pascal program or unit, for example,

```
function LoCase(Ch: char): char; external;
```

In the corresponding assembly language source file, all procedures and functions must appear in a segment named **CODE**, and the names of the external procedures and functions must appear in **PUBLIC** directives. (**CSEG** is also accepted as a segment name in place of **CODE**.)

You must ensure that an assembly language procedure or function matches its Pascal definition with respect to call model (**NEAR** or **FAR**), number of parameters, types of parameters, and result type.

An assembly language source file can declare variables in a segment named **DATA**. Such variables are private to the assembly language source file and cannot be referenced from the Pascal program or unit. However, they reside in the same segment as the Pascal globals, and can be accessed through the **DS** segment register. (**DSEG** is also accepted as a segment name in place of **DATA**.)

All procedures, functions, and variables declared in the Pascal program or unit, and the ones declared in the **interface** section of the used units, can be referenced from the assembly language source file through **EXTRN** directives. Again, it is up to you to supply the correct type in the **EXTRN** definition.

When an object file appears in a `$L` directive, Turbo Pascal converts the file from the Intel relocatable object module format (`.OBJ`) to its own internal relocatable format. This conversion is possible only if certain rules are observed:

- All procedures and functions must be placed in a segment named **CODE**, and all private variables must be placed in a segment named **DATA**. All other segments are ignored, and so are **GROUP** directives. The segment

definitions can specify **BYTE** or **WORD** alignment; when linked, they are always word-aligned. The segment definitions can optionally specify **PUBLIC** (which is ignored), but they should not specify a class name. (CSEG is also accepted as a segment name in place of **CODE**, and DSEG is accepted as a segment name in place of **DATA**.)

- When declaring variables in the **DATA** or **DSEG** segment, always use a question mark (?) to specify the value, for instance:

```
Count    DW    ?  
Buffer   DB    128 DUP(?)
```

Turbo Pascal ignores any request to create initialized variables in the **DATA** or **DSEG** segment.

- When referring to **EXTRN** procedures and functions, do not specify an offset. For example, the following construct is not allowed:

```
EXTRN    MyProc : NEAR  
CALL     MyProc + 8
```

Note that this restriction does not apply to **EXTRN** variables.

- Byte-sized references to **EXTRN** symbols are not allowed. For example, this means that the assembly language **HIGH** and **LOW** operators cannot be used with **EXTRN** symbols.

## ***Turbo Assembler and Turbo Pascal***

---

Turbo Assembler (TASM) makes it much easier to program routines in assembly language and interface them into your Turbo Pascal programs. Turbo Assembler provides simplified segmentation, memory model, and language support for Turbo Pascal programmers.

Using **TPASCAL** with the **.MODEL** directive sets up Pascal calling conventions, defines the segment names, does the **PUSH BP** and **MOV BP,SP**, and it also sets up the return with **POP BP** and **RET N** (where *N* is the number of parameter bytes).

The **PROC** directive lets you define your parameters in the same order as they are defined in your Pascal program. If you are defining a function that returns a string, notice that the **PROC** directive has a **RETURNS** option that lets you access the temporary string pointer on the stack without affecting the number of parameter bytes added to the **RET** statement.

Here's an example coded to use the **.MODEL** and **PROC** directives:

```
.MODEL TPASCAL  
.CODE  
MyProc PROC    FAR i:BYTE,j:BYTE RETURNS result:DWORD  
PUBLIC MyProc
```

```

les    di,result      ;get address of temporary string
mov    al,i           ;get first parameter i
mov    bl,j           ;get second parameter j
.
.
.
ret

```

The Pascal function definition would look like this:

```
function MyProc(i,j : char) : string; external;
```

For more information about interfacing Turbo Assembler and Turbo Pascal, refer to Chapter 7 of the *Turbo Assembler User's Guide*.

## *Examples of Assembly Language Routines*

---

The following code is an example of a unit that implements two assembly language string-handling routines. The *UpperCase* function converts all characters in a string to uppercase, and the *StringOf* function returns a string of characters of a specified length.

```

unit Strings;
interface
function UpperCase(S: string): string;
function StringOf(Ch: char; Count: byte): string;
implementation
{$L STRS}
function UpperCase; external;
function StringOf; external;
end.

```

The assembly language file that implements the *UpperCase* and *StringOf* routines is shown next. It must be assembled into a file called STRS.OBJ before the *Strings* unit can be compiled. Note that the routines use the FAR call model because they are declared in the **interface** section of the unit.

```

CODE    SEGMENT BYTE PUBLIC
        ASSUME  CS:CODE
        PUBLIC  UpperCase,StringOf      ;Make them known

; function UpperCase(S: string): string

UpperRes    EQU     DWORD PTR [BP+10]
UpperStr     EQU     DWORD PTR [BP+6]

UpperCase    PROC FAR

        push    bp                ;Save BP
        mov     bp,sp             ;Set up stack frame
        push    ds                ;Save DS
        lds     si,UpperStr        ;Load string address

```



```

        les     di,UpperRes           ;Load result address
        cld                     ;Forward string-ops
        lodsb                    ;Load string length
        stosb                     ;Copy to result
        mov     cl,al              ;String length to CX
        xor     ch,ch
        jcxz    U3                 ;Skip if empty string
U1:     lodsb                    ;Load character
        cmp     al,'a'             ;Skip if not 'a'..'z'
        jb     U2
        cmp     al,'z'
        ja     U2
        sub     al,'a'-'a'         ;Convert to uppercase
U2:     stosb                     ;Store in result
        loop   U1                 ;Loop for all characters
U3:     pop     ds                 ;Restore DS
        pop     bp                 ;Restore BP
        ret     4                 ;Remove parameter and return

```

UpperCase        ENDP

**; procedure** StringOf(**var** S: **string**; Ch: char; Count: byte)

StrOfS            EQU     DWORD PTR [BP+10]

StrOfChar        EQU     BYTE PTR [BP+8]

StrOfCount       EQU     BYTE PTR [BP+6]

StringOf         PROC FAR

```

        push    bp                ;Save BP
        mov     bp,sp             ;Set up stack frame
        les     di,StrOfRes       ;Load result address
        mov     al,StrOfCount     ;Load count
        cld                     ;Forward string-ops
        stosb                     ;Store length
        mov     cl,al             ;Count to CX
        xor     ch,ch
        mov     al,StrOfChar      ;Load character
        rep     STOSB             ;Store string of characters
        pop     bp                ;Restore BP
        ret     8                 ;Remove parameters and return

```

StringOf        ENDP

CODE     ENDS

END

To assemble the example and compile the unit, use the following commands:

```

TASM STR5
TPC strings

```

The next example shows how an assembly language routine can refer to Pascal routines and variables. The Numbers program reads up to 100

integer values, and then calls an assembly language procedure to check the range of each of these values. If a value is out of range, the assembly language procedure calls a Pascal procedure to print it.

```

program Numbers;
{$L CHECK}
var
    Buffer : array[1..100] of integer;
    Count : integer;

procedure RangeError(N: integer);
begin
    Writeln('Range error: ',N);
end;

procedure CheckRange(Min,Max: integer); external;

begin
    Count := 0;
    while not Eof and (Count<100) do
        begin
            { Ends when you type Ctrl-Z or after 100 iterations }
            Count := Count+1; Readln(Buffer[Count]);
        end;
        CheckRange(-10,10);
    end.

```

The assembly language file that implements the *CheckRange* procedure is shown next. It must be assembled into a file called CHECK.OBJ before the Numbers program can be compiled. Note that the procedure uses the NEAR call model because it is declared in a program.

```

DATA    SEGMENT WORD PUBLIC
        EXTRN    Buffer:WORD,Count:WORD    ;Pascal variables
DATA    ENDS
CODE    SEGMENT BYTE PUBLIC
        ASSUME    CS:CODE,DS:Buffer
        EXTRN    RangeError:NEAR          ;Implemented in Pascal
        PUBLIC    CheckRange              ;Implemented here

CheckRange    PROC    NEAR

        mov     bx,sp                      ;Get parameters pointer
        mov     ax,ss:[BX+4]               ;Load Min
        mov     dx,ss:[BX+2]               ;Load Max
        xor     bx,bx                      ;Clear Data index
        mov     cx,count                   ;Load Count
        jcxz    SD4                        ;Skip if zero
SD1:     cmp     Buffer[BX],AX               ;Too small?
        jl      SD2                        ;Yes, jump
        cmp     Buffer[BX],DX               ;Too large?
        jle     SD3                        ;No, jump
SD2:     push    ax                        ;Save registers

```

```

        push    bx
        push    cx
        push    dx
        push    Buffer[BX]           ;Pass offending value to Pascal
        call    RangeError          ;Call Pascal procedure
        pop     dx                   ;Restore registers
        pop     cx
        pop     bx
        pop     ax
SD3:    inc     bx                   ;Point to next element
        inc     bx
        loop    SD1                 ;Loop for each item
SD4:    ret     4                   ;Clean stack and return

CheckRange    ENDP
CODE          ENDS
END

```

## Turbo Assembler Example

Here's a Turbo Assembler version of the previous assembly language example that takes advantage of TASM's support for Turbo Pascal:

```

.MODEL    TPASCAL                   ;Turbo Pascal code model
LOCALS    @@                       ;Define local labels prefix
.DATA                                           ;Data segment
EXTRN     Buffer:WORD,Count:WORD           ;Pascal variables

.CODE                                           ;Code segment
EXTRN     RangeError:NEAR                  ;Implemented in Pascal
PUBLIC    CheckRange                      ;Implemented here

CheckRange    PROC NEAR Min:WORD,Max:WORD

        mov     ax,Min                   ;Keep Min in AX
        mov     dx,Max                   ;Keep Max in DX
        xor     bx,BX                   ;Clear Buffer index
        mov     cx,Count                 ;Load Count
        jcxz    @@4                     ;Skip if zero
@@1:    cmp     ax,Buffer[BX]             ;Too small?
        jg      @@2                     ;Yes, goto CR2
        cmp     dx,Buffer[BX]             ;Too large?
        jge     @@3                     ;No, goto CR3
@@2:    push    ax                       ;Save registers
        push    bx
        push    cx
        push    dx
        push    Buffer[BX]               ;Pass offending value to Pascal
        call    RangeError              ;Call Pascal procedure
        pop     dx                       ;Restore registers
        pop     cx

```

```

        pop     bx
        pop     ax
@@3:    inc     bx                ;Point to next element
        inc     bx
        loop    @@1              ;Loop for each item
@@4:    ret
CheckRange    ENDP
END

```

Notice that with .MODEL TPASCAL Turbo Assembler automatically generates entry code before the first instruction, and generates exit code upon seeing the RET.

## Inline Machine Code

---

For very short assembly language subroutines, Turbo Pascal's **inline** statements and directives are very convenient. They allow you to insert machine code instructions directly into the program or unit text instead of through an object file.


### Inline Statements

---


An **inline** statement consists of the reserved word **inline** followed by one or more inline elements, separated by slashes and enclosed in parentheses:

```
inline(10/$2345/Count+1/Data-Offset);
```

Here's the syntax of an inline statement:



Each inline element consists of an optional size specifier, < or >, and a constant or a variable identifier, followed by zero or more offset specifiers (see the syntax that follows). An offset specifier consists of a + or a - followed by a constant.



Each inline element generates 1 byte or one word of code. The value is computed from the value of the first constant or the offset of the variable identifier, to which is added or subtracted the value of each of the constants that follow it.

An inline element generates 1 byte of code if it consists of constants only and if its value is within the 8-bit range (0..255). If the value is outside the 8-bit range or if the inline element refers to a variable, one word of code is generated (least-significant byte first).

The < and > operators can be used to override the automatic size selection we described earlier. If an inline element starts with a < operator, only the least-significant byte of the value is coded, even if it is a 16-bit value. If an inline element starts with a > operator, a word is always coded, even though the most-significant byte is 0. For example, the statement

```
inline(<$1234/>$44);
```

generates 3 bytes of code: \$34,\$44,\$00.

The value of a variable identifier in an inline element is the offset address of the variable within its base segment. The base segment of global variables—variables declared at the outermost level in a program or a unit—and typed constants is the data segment, which is accessible through the DS register. The base segment of local variables—variables declared within the current subprogram—is the stack segment. In this case the variable offset is relative to the BP register, which automatically causes the stack segment to be selected.

**Note:** Registers BP, SP, SS, and DS must be preserved by inline statements; all other registers can be modified.

The following example of an inline statement generates machine code for storing a specified number of words of data in a specified variable. When called, procedure *FillWord* stores *Count* words of the value *Data* in memory, starting at the first byte occupied by *Dest*.

```
procedure FillWord(var Dest;Count,Data: word);  
begin
```

```


inline(
    $C4/$BE/Dest/           { LES DI, Dest[BP] }
    $8B/$8E/Count/         { MOV CX, Count[BP] }
    $8B/$86/Data/          { MOV AX, Data[BP] }
    $FC/                   { CLD }
    $F3/$AB);               { REP STOSW }
end;

```

Inline statements can be freely mixed with other statements throughout the statement part of a block.

## Inline Directives

Inline directives let you write procedures and functions that expand into a given sequence of machine code instructions whenever they are called. These are comparable to macros in assembly language. The syntax for an inline directive is the same as that of an inline statement:



When a normal procedure or function is called (including one that contains inline statements), the compiler generates code that pushes the parameters (if any) onto the stack, and then generates a **CALL** instruction to call the procedure or function. However, when you call an inline procedure or function, the compiler generates code from the inline directive instead of the **CALL**. Here's a short example of two inline procedures:

```

procedure DisableInterrupts; inline($FA);      { CLI }
procedure EnableInterrupts; inline($FB);      { STI }

```

When *DisableInterrupts* is called, it generates 1 byte of code—a **CLI** instruction.

Procedures and functions declared with inline directives can have parameters; however, the parameters cannot be referred to symbolically in the inline directive (other variables can, though). Also, because such procedures and functions are in fact macros, there is no automatic entry and exit code, nor should there be any return instruction.

The following function multiplies two integer values, producing a longint result:

```

function LongMul(X,Y : integer): longint;
inline(
    $5A/                   { POP AX ;Pop X }
    $58/                   { POP DX ;Pop Y }
    $F7/$EA);              { IMUL DX ;DX : AX = X*Y }

```

Note the lack of entry and exit code and the missing return instruction. These are not required, because the 4 bytes are inserted into the instruction stream when *LongMul* is called.

Inline directives are intended for very short (less than 10 bytes) procedures and functions only.

Because of the macro-like nature of inline procedures and functions, they cannot be used as arguments to the @ operator and the *Addr*, *Ofs*, and *Seg* functions.

## Direct Memory and Port Access

---

### *The Mem, MemW, and MemL Arrays*

---

Turbo Pascal implements three predefined arrays, *Mem*, *MemW*, and *MemL*, which are used to directly access memory. Each component of *Mem* is a byte, each component of *MemW* is a word, and each component of *MemL* is a longint.

The *Mem* arrays use a special syntax for indexes: Two expressions of the integer-type word, separated by a colon, are used to specify the segment base and offset of the memory location to access. Some examples include

```
Mem[$0040:$0049] := 7;  
Data := MemW[Seg(V):Ofs(V)];  
MemLong := MemL[64:3*4];
```

The first statement stores the value 7 in the byte at \$0040:\$0049. The second statement moves the word value stored in the first 2 bytes of the variable *V* into the variable *Data*. The third statement moves the longint value stored at \$0040:\$000C into the variable *MemLong*.

### *The Port and PortW Arrays*

---

For access to the 80x86 CPU data ports, Turbo Pascal implements two predefined arrays, *Port* and *PortW*. Both are one-dimensional arrays, and each element represents a data port, whose port address corresponds to its index. The index type is the integer-type word. Components of the *Port* array are of type byte, and components of the *PortW* array are of type word.

When a value is assigned to a component of *Port* or *PortW*, the value is output to the selected port. When a component of *Port* or *PortW* is referenced in an expression, its value is input from the selected port. Some examples include:

```

Port[$20] := $20;
Port[Base] := Port[Base] xor Mask;
while Port[$B2] and $80 = 0 do { Wait };

```

Use of the *Port* and *PortW* arrays is restricted to assignment and reference in expressions only, that is, components of *Port* and *PortW* cannot be used as variable parameters. Furthermore, references to the entire *Port* or *PortW* array (reference without index) are not allowed.

## Interrupt Handling

---

The Turbo Pascal run-time library and the code generated by the compiler are fully interruptible. Also, most of the run-time library is reentrant, which allows you to write interrupt service routines in Turbo Pascal.

### Writing Interrupt Procedures

---

Interrupt procedures are declared with the **interrupt** directive. Every interrupt procedure must specify the following procedure header (or a subset of it, as explained later):

```

procedure IntHandler(Flags,CS,IP,AX,BX,CX,DX,SI,DI,DS,ES,BP: word);
interrupt;
begin
  :
  :
end;

```

As you can see, all the registers are passed as pseudo-parameters so you can use and modify them in your code. You can omit some or all of the parameters, starting with *Flags* and moving towards *BP*. It is an error to declare more parameters than are listed in the preceding example or to omit a specific parameter without also omitting the ones before it (although no error is reported). For example:

```

procedure IntHandler(DI,ES,BP : word); { Invalid call }
procedure IntHandler(SI,DI,DS,ES,BP : word); { Valid call }

```

On entry, an interrupt procedure automatically saves all registers (regardless of the procedure header) and initializes the DS register:

```

push  ax
push  bx
push  cx
push  dx
push  si
push  di

```



```

push    ds
push    es
push    bp
mov     bp,sp
sub     sp,LocalSize
mov     ax,SEG DATA
mov     ds,ax

```

Notice the lack of a STI instruction to enable further interrupts. You should code this yourself (if required) using an inline statement. The exit code restores the registers and executes an interrupt-return instruction:

```

mov     sp,bp
pop     bp
pop     es
pop     ds
pop     di
pop     si
pop     dx
pop     cx
pop     bx
pop     ax
iret

```

An interrupt procedure can modify its parameters. Changing the declared parameters will modify the corresponding register when the interrupt handler returns. This can be useful when you are using an interrupt handler as a user service, much like the DOS INT 21H services.

Interrupt procedures that handle hardware-generated interrupts should refrain from using any of Turbo Pascal's input and output or dynamic memory allocation routines, because they are not reentrant. Likewise, no DOS functions can be used, because DOS is not reentrant.

## Text File Device Drivers

---

As mentioned in Chapter 10, "Input and Output," Turbo Pascal allows you to define your own text file device drivers. A *text file device driver* is a set of four functions that completely implement an interface between Turbo Pascal's file system and some device.

The four functions that define each device driver are *Open*, *InOut*, *Flush*, and *Close*. The function header of each function is

```
function DeviceFunc(var F: TextRec): integer;
```

where *TextRec* is the text file record type defined in the earlier section, "File Types," on page 193. Each function must be compiled in the {\$F+} state to force it to use the FAR call model. The return value of a device interface

function becomes the value returned by *IOResult*. The return value of 0 indicates a successful operation.

To associate the device interface functions with a specific file, you must write a customized *Assign* procedure (like the *AssignCrt* procedure in the *Crt* unit). The *Assign* procedure must assign the addresses of the four device interface functions to the four function pointers in the text file variable. In addition, it should store the *fmClosed* "magic" constant in the *Mode* field, store the size of the text file buffer in *BufSize*, store a pointer to the text file buffer in *BufPtr*, and clear the *Name* string.

Assuming, for example, that the four device interface functions are called *DevOpen*, *DevInOut*, *DevFlush*, and *DevClose*, the *Assign* procedure might look like this:

```
procedure AssignDev(var F: Text);
begin
  with TextRec(F) do
    begin
      Mode      := fmClosed;
      BufSize   := SizeOf(Buffer);
      BufPtr    := @Buffer;
      OpenFunc  := @DevOpen;
      InOutFunc := @DevInOut;
      FlushFunc := @DevFlush;
      CloseFunc := @DevClose;
      Name[0]   := #0;
    end;
end;
```

The device interface functions can use the *UserData* field in the file record to store private information. This field is not modified by the Turbo Pascal file system at any time.

## The Open Function

---

The *Open* function is called by the *Reset*, *Rewrite*, and *Append* standard procedures to open a text file associated with a device. On entry, the *Mode* field contains *fmInput*, *fmOutput*, or *fmInOut* to indicate whether the *Open* function was called from *Reset*, *Rewrite*, or *Append*.

The *Open* function prepares the file for input or output, according to the *Mode* value. If *Mode* specified *fmInOut* (indicating that *Open* was called from *Append*), it must be changed to *fmOutput* before *Open* returns.

*Open* is always called before any of the other device interface functions. For that reason, *Assign* only initializes the *OpenFunc* field, leaving initialization of the remaining vectors up to *Open*. Based on *Mode*, *Open* can then install

pointers to either input- or output-oriented functions. This saves the *InOut*, *Flush*, and *Close* functions from determining the current mode.

## ***The InOut Function***

---

The *InOut* function is called by the *Read*, *Readln*, *Write*, *Writeln*, *Eof*, *Eoln*, *SeekEof*, *SeekEoln*, and *Close* standard procedures and functions whenever input or output from the device is required.

When *Mode* is *fmInput*, the *InOut* function reads up to *BufSize* characters into *BufPtr*<sup>^</sup>, and returns the number of characters read in *BufEnd*. In addition, it stores 0 in *BufPos*. If the *InOut* function returns 0 in *BufEnd* as a result of an input request, *Eof* becomes True for the file.

When *Mode* is *fmOutput*, the *InOut* function writes *BufPos* characters from *BufPtr*<sup>^</sup>, and returns 0 in *BufPos*.

## ***The Flush Function***

---

The *Flush* function is called at the end of each *Read*, *Readln*, *Write*, and *Writeln*. It can optionally flush the text file buffer.

If *Mode* is *fmInput*, the *Flush* function can store 0 in *BufPos* and *BufEnd* to flush the remaining (un-read) characters in the buffer. This feature is seldom used.

If *Mode* is *fmOutput*, the *Flush* function can write the contents of the buffer, exactly like the *InOut* function, which ensures that text written to the device appears on the device immediately. If *Flush* does nothing, the text will not appear on the device until the buffer becomes full or the file is closed.

## ***The Close Function***

---

The *Close* function is called by the *Close* standard procedure to close a text file associated with a device. (The *Reset*, *Rewrite*, and *Append* procedures also call *Close* if the file they are opening is already open.) If *Mode* is *fmOutput*, then before calling *Close*, Turbo Pascal's file system calls *InOut* to ensure that all characters have been written to the device.

## ***Examples of Text File Device Drivers***

---

The following unit implements a text file device driver for the communication ports (serial ports) of an IBM PC:

```

unit AuxInOut;
interface
uses Dos;
procedure AssignAux(var F: Text; Port,Params: word);
implementation
{$R-,S-}
type
  AuxRec = record
    Port,Params: word;
    Unused: array[1..12] of byte;
  end;

procedure AuxInit(Port,Params: word);
inline(
  $58/          { POP AX   ;Pop parameters }
  $5A/          { POP DX   ;Pop port number }
  $B4/$00/      { MOV AH,0 ;Code for initialize }
  $CD/$14);     { INT 14H  ;Call BIOS }

function AuxInChar(Port: word): char;
inline(
  $5A/          { POP DX   ;Pop port number }
  $B4/$02/      { MOV AH,2 ;Code for input }
  $CD/$14);     { INT 14H  ;Call BIOS }

procedure AuxOutChar(Port: word; Ch: char);
inline(
  $58/          { POP AX   ;Pop character }
  $5A/          { POP DX   ;Pop port number }
  $B4/$01/      { MOV AH,1 ;Code for output }
  $CD/$14);     { INT 14H  ;Call BIOS }

function AuxInReady(Port: word): boolean;
inline(
  $5A/          { POP DX   ;Pop port number }
  $B4/$03/      { MOV AH,3 ;Code for status }
  $CD/$14/      { INT 14H  ;Call BIOS }
  $88/$E0/      { MOV AL,AH ;Get line status in AH }
  $24/$01);     { AND AL,1  ;Isolate Data Ready bit }

{$F+}

function AuxInput(var F: TextRec): integer;
var
  P: word;
begin
  with F,AuxRec(UserData) do
  begin
    P := 0;
    while AuxInReady(Port) and (P<BufSize) do
    begin
      BufPtr^[P] := AuxInChar(Port); Inc(P);
    end;
  end;
end;

```

```

    BufPos := 0; Bufend := P;
end;
AuxInput := 0;
end;

function AuxOutput(var F: TextRec): integer;
var
    P: word;
begin
    with F, AuxRec(UserData) do
        begin
            P := 0;
            while P < BufPos do
                begin
                    AuxOutChar(Port, BufPtr^[P]); Inc(P);
                end;
            BufPos := 0;
        end;
        AuxOutput := 0;
    end;

function AuxIgnore(var F: TextRec): integer;
begin
    AuxIgnore := 0;
end;

function AuxOpen(var F: TextRec): integer;
begin
    with F, AuxRec(UserData) do
        begin
            AuxInit(Port, Params);
            if Mode = fmInput then
                begin
                    InOutFunc := @AuxInput;
                    FlushFunc := @AuxIgnore;
                end
            else
                begin
                    Mode := fmOutput;
                    InOutFunc := @AuxOutput;
                    FlushFunc := @AuxOutput;
                end;
            CloseFunc := @AuxIgnore;
        end;
        AuxOpen := 0;
    end;
    {$F-}

procedure AssignAux;
begin
    with TextRec(F) do
        begin

```

```

    Handle := $FFFF;
    Mode := fmClosed;
    BufSize := Sizeof(Buffer);
    BufPtr := @Buffer;
    OpenFunc := @AuxOpen;
    AuxRec(UserData).Port := Port;
    AuxRec(UserData).Params := Params;
    Name[0] := #0;
end;
end;
end.

```

The *TextRec* record is defined in the *Dos* unit. The first two words of the 16-byte *UserData* array are used for storing the communications port number and parameter byte. The remaining 12 bytes are not used. Note that the *AuxRec* record is used only for typecasting.

The *AuxInit* procedure initializes a specified communications port according to a specified parameter byte. The *AuxInChar* function reads a character from the specified port. The *AuxOutChar* procedure outputs a character to the specified port. The *AuxInReady* function returns True if a character is ready to be read from the specified port. Notice the use of inline directives to implement these procedures and functions. For further details on the communication ports, refer to the *IBM PC Technical Reference Manual*.

*AssignAux* initializes a specified text file variable to refer to a specified communication port with a specified parameter byte. Port numbers 0 and 1 correspond to COM1 and COM2. The parameter byte is described in the *IBM PC Technical Reference Manual*.

*AuxOpen* initializes the selected communication port and sets up the function pointers according to the *Mode* field. Note that for output, *FlushFunc* is set to the same address as *InOutFunc*, causing the text file buffer to be flushed after each *Write* or *Writeln*.

*AuxInput* inputs up to *BufSize* characters from the selected port, and *AuxOutput* outputs the contents of the buffer to the selected port.

*AuxIgnore* is used in those cases where no special action is required, such as for *Close* and for *Flush* (when in input mode).

The following short program uses the *AuxInOut* unit to write a string to one of the communication ports. Through the *AssignAux* procedure, the *Com1* file is associated with the COM1 port using 1200 baud, no parity, 1 stop bit, and 8 data bits:

```

program TestAux;
uses AuxInOut;
var
    Com1: Text;
begin

```

```

AssignAux(Com1,0,$83);
Rewrite(Com1);
Writeln(Com1,'Device Drivers are fun!');
Close(Com1);
end.

```

## Exit Procedures

---

By installing an exit procedure, you can gain control over a program's termination process. This is useful when you want to make sure specific actions are carried out before a program terminates; a typical example is updating and closing files.

The *ExitProc* pointer variable allows you to install an exit procedure. The exit procedure always gets called as a part of a program's termination, whether it is a normal termination, a termination through a call to *Halt*, or a termination due to a run-time error.

An exit procedure takes no parameters, and must be compiled in the {\$F+} state to force it to use the FAR call model.

When implemented properly, an exit procedure actually becomes part of a chain of exit procedures. This chain makes it possible for units as well as programs to install exit procedures. Some units install an exit procedure as part of their initialization code, and then rely on that specific procedure to be called to clean up after the unit; for instance, to close files or to restore interrupt vectors. The procedures on the exit chain get executed in reverse order of installation. This ensures that the exit code of one unit does not get executed before the exit code of any units that depend upon it.

To keep the exit chain intact, you must save the current contents of *ExitProc* before changing it to the address of your own exit procedure. Furthermore, the first statement in your exit procedure must reinstall the saved value of *ExitProc*. The following program demonstrates a skeleton method of implementing an exit procedure:

```

program Testexit;
var
    ExitSave: pointer;

    {$F+}
procedure MyExit;
begin
    ExitProc := ExitSave;           { Always restore old vector first }
    :
    :
end;
    {$F-}

```

```

begin
  ExitSave := ExitProc;
  ExitProc := @MyExit;
  :
  :
end.

```

On entry, the program saves the contents of *ExitProc* in *ExitSave*, and then installs the *MyExit* exit procedure. After having been called as part of the termination process, the first thing *MyExit* does is reinstall the previous exit procedure.

The termination routine in the run-time library keeps calling exit procedures until *ExitProc* becomes *nil*. To avoid infinite loops, *ExitProc* is set to *nil* before every call, so the next exit procedure is called only if the current exit procedure assigns an address to *ExitProc*. If an error occurs in an exit procedure, it will not be called again.

An exit procedure may learn the cause of termination by examining the *ExitCode* integer variable and the *ErrorAddr* pointer variable.

In case of normal termination, *ExitCode* is zero and *ErrorAddr* is *nil*. In case of termination through a call to *Halt*, *ExitCode* contains the value passed to *Halt* and *ErrorAddr* is *nil*. Finally, in case of termination due to a run-time error, *ExitCode* contains the error code and *ErrorAddr* contains the address of the statement in error.

The last exit procedure (the one installed by the run-time library) closes the *Input* and *Output* files, and restores the interrupt vectors that were captured by Turbo Pascal. In addition, if *ErrorAddr* is not *nil*, it outputs a run-time error message.

If you wish to present run-time error messages yourself, install an exit procedure that examines *ErrorAddr* and outputs a message if it is not *nil*. In addition, before returning, make sure to set *ErrorAddr* to *nil*, so that the error is not reported again by other exit procedures.

Once the run-time library has called all exit procedures, it returns to DOS, passing as a return code the value stored in *ExitCode*.

## Automatic Optimizations

---

Turbo Pascal performs several different types of code optimizations, ranging from constant folding and short-circuit Boolean expression evaluation all the way up to smart linking. The following sections describe some of the types of optimizations performed.



## *Constant Folding*

---

If the operand(s) of an operator are constants, Turbo Pascal evaluates the expression at compile time. For example, `X := 3 + 4 * 2` generates the same code as `X := 11`, and `S := 'In' + 'Out'` generates the same code as `S := 'InOut'`.

Likewise, if an operand of an *Abs*, *Chr*, *Hi*, *Length*, *Lo*, *Odd*, *Ord*, *Pred*, *Ptr*, *Round*, *Succ*, *Swap*, or *Trunc* function call is a constant, the function is evaluated at compile time.

If an array index expression is a constant, the address of the component is evaluated at compile time. For example, accessing `Data[5,5]` is just as efficient as accessing a simple variable.

## *Constant Merging*

---

Using the same string constant two or more times in a statement part generates only one copy of the constant. For example, two or more `Write('Done')` statements in the same statement part will reference the same copy of the string constant `'Done'`.

## *Short-Circuit Evaluation*

---

Turbo Pascal implements short-circuit Boolean evaluation, which means that evaluation of a Boolean expression stops as soon as the result of the entire expression becomes evident. This guarantees minimum execution time, and usually minimum code size. Short-circuit evaluation also makes possible the evaluation of constructs that would not otherwise be legal; for instance:

```
while (I<=Length(S)) and (S[I]<>' ') do Inc(I);  
while (P<>nil) and (P^.Value<>5) do P:=P^.Next;
```

In both cases, the second test is not evaluated if the first test is False.

The opposite of short-circuit evaluation is complete evaluation, which is selected through a `($B+)` compiler directive. In this state, every operand of a Boolean expression is guaranteed to be evaluated.

## Order of Evaluation

---

As permitted by the Pascal standards, operands of an expression are frequently evaluated differently from the left to right order in which they are written. For example, the statement

```
I:=F(J) div G(J);
```

where *F* and *G* are functions of type integer, causes *G* to be evaluated before *F*, since this enables the compiler to produce better code. Because of this, it is important that an expression never depend on any specific order of evaluation of the embedded functions. Referring to the previous example, if *F* must be called before *G*, use a temporary variable:

```
T:=F(J); I:=T div G(J);
```

**Note:** As an exception to this rule, when short-circuit evaluation is enabled (the {\$B-} state), boolean operands grouped with **and** or **or** are *always* evaluated from left to right.

## Range-Checking

---

Assignment of a constant to a variable and use of a constant as a value parameter is range-checked at compile time; no run-time range-check code is generated. For example, *x:=999*, where *X* is of type *Byte*, causes a compile-time error.

## Shift Instead of Multiply

---

The operation *X \* C*, where *C* is a constant and a power of 2, is coded using a *Shl* instruction.

Likewise, when the size of an array's components is a power of 2, a *Shl* instruction (not a *Mul* instruction) is used to scale the index expression.

## Automatic Word Alignment

---

By default, Turbo Pascal aligns all variables and typed constants larger than 1 byte on a machine-word boundary. On all 16-bit 80x86 CPUs, word alignment means faster execution, since word-sized items on even addresses are accessed faster than words on odd addresses.

Data alignment is controlled through the *\$A* compiler directive. In the default {\$A+} state, variables and typed constants are aligned as described

above. In the {\$A-} state, no alignment measures are taken. For further details, refer to Appendix B, "Compiler Directives".

## *Dead Code Removal*

---

Statements that are known never to execute do not generate any code. For example, these constructs don't generate any code:

```
if False then statement
while False do statement
```

## *Smart Linking*

---

Turbo Pascal 5.0's built-in linker automatically removes unused code and data when building an .EXE file. Procedures, functions, variables, and typed constants that are part of the compilation, but never get referenced, are removed in the .EXE file. The removal of unused code takes place on a per procedure basis, and the removal of unused data takes place on a per declaration section basis.

Consider the following program:

```
program SmartLink;

const
  H: array[0..15] of char = '0123456789ABCDEF';

var
  I,J: integer;
  X,Y: real;

var
  S: string[79];

var
  A: array[1..10000] of integer;

procedure P1;
begin
  A[1] := 1;
end;

procedure P2;
begin
  I := 1;
end;
```

```

procedure P3;
begin
  S := 'Turbo Pascal';
  P2;
end;

begin
  P3;
end.

```

The main program calls *P3*, which calls *P2*, so both *P2* and *P3* are included in the .EXE file; and since *P2* references the first **var** declaration section, and *P3* references the second **var** declaration, *I*, *J*, *X*, *Y*, and *S* are also included in the .EXE file. However, no references are made to *P1*, and none of the included procedures reference *H* and *A*, so these objects are removed.

Smart linking is especially valuable in connection with units that implement procedure/function libraries. An example of such a unit is the *Dos* standard unit: It contains a number of procedures and functions, all of which are seldom used by the same program. If a program uses only one or two procedures from *Dos*, then only these procedures are included in the final .EXE file, and the remaining ones are removed, greatly reducing the size of the .EXE file.

**Note:** When compiling to memory, Turbo Pascal's smart linker is disabled. This explains why some programs become smaller when compiled to disk.



## Turbo Pascal Reference Lookup

This chapter describes all the procedures and functions of Turbo Pascal 5.0. For your convenience, they're arranged alphabetically. For a list of what procedures and functions are new and modified in Turbo Pascal 5.0, refer to Appendix A in the *User's Guide*, "Differences Between Turbo Pascal 3.0, 4.0, and 5.0." Here's a sample layout so you can easily understand the format of the lookup; note that only the relevant items are listed in each entry.

---

Sample procedure	What unit it occupies
------------------	-----------------------

---

<b>Function</b>	What it does
<b>Declaration</b>	How it's declared; italicized items are user-defined
<b>Result type</b>	What it returns if it's a function
<b>Remarks</b>	General information about the procedure or function
<b>Restrictions</b>	Things to be aware of
<b>Differences</b>	From 3.0 and 4.0
<b>See also</b>	Related procedures/functions, and so on.
<b>Example</b>	Sample program or code fragment

**Note:** When you compile in numeric processing mode ( $\{\$N+\}$ ), the return values of the floating-point routines in the *System* unit—*Sqrt*, *Pi*, *Sin*, and so on—are of type extended instead of real.

---

## Abs function

---

<b>Function</b>	Returns the absolute value of the argument.
<b>Declaration</b>	<code>Abs(x)</code>
<b>Result type</b>	Same type as parameter.
<b>Remarks</b>	<code>x</code> is an integer-type or real-type expression. The result, of the same type as <code>x</code> , is the absolute value of <code>x</code> .
<b>Example</b>	<pre>var   r: real;   i: integer; begin   r := Abs(-2.3);      { 2.3 }   i := Abs(-157);     { 157 } end.</pre>

---

## Addr function

---

<b>Function</b>	Returns the address of a specified object.
<b>Declaration</b>	<code>Addr(x)</code>
<b>Result type</b>	pointer
<b>Remarks</b>	<code>x</code> is any variable, or a procedure or function identifier. The result is a pointer that points to <code>x</code> . Like <code>nil</code> , the result of <i>Addr</i> is assignment compatible with all pointer types.  <b>Note:</b> The <code>@</code> operator produces the same result as <i>Addr</i> .
<b>See also</b>	<i>Ofs, Ptr, Seg</i>
<b>Example</b>	<pre>var p: pointer; begin   p := Addr(p);      { Now points to itself } end.</pre>

---

## Append procedure

---

<b>Function</b>	Opens an existing file for appending.
<b>Declaration</b>	<code>Append(var f: text)</code>
<b>Remarks</b>	<p><i>f</i> is a text-file variable that must have been associated with an external file using <i>Assign</i>.</p> <p><i>Append</i> opens the existing external file with the name assigned to <i>f</i>. It is an error if there is no existing external file of the given name. If <i>f</i> was already open, it is first closed and then re-opened. The current file position is set to the end of the file.</p> <p>If a <i>Ctrl-Z</i> (ASCII 26) is present in the last 128-byte block of the file, the current file position is set to overwrite the first <i>Ctrl-Z</i> in the block. In this way, text can be appended to a file that terminates with a <i>Ctrl-Z</i>.</p> <p>If <i>f</i> was assigned an empty name, such as <i>Assign(f, '')</i>, then, after the call to <i>Append</i>, <i>f</i> will refer to the standard output file (standard handle number 1).</p> <p>After a call to <i>Append</i>, <i>f</i> becomes write-only, and the file pointer is at end-of-file.</p> <p>With <i>{I-}</i>, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>

**See also** *Assign, Close, Reset, Rewrite*

**Example**

```

var f: text;
begin
  Assign(f, 'TEST.TXT');
  Rewrite(f);                      { Create new file }
  Writeln(f, 'original text');
  Close(f);                        { Close file, save changes }
  Append(f);                       { Add more text onto end }
  Writeln(f, 'appended text');
  Close(f);                        { Close file, save changes }
end.
```



---

## Arc procedure

## Graph

---

<b>Function</b>	Draws a circular arc from start angle to end angle, using (x,y) as the center point.
<b>Declaration</b>	Arc(X, Y: integer; StAngle, EndAngle, Radius: word)
<b>Remarks</b>	<p>Draws a circular arc around (x,y), with a radius of <i>Radius</i>. The <i>Arc</i> travels from <i>StAngle</i> to <i>EndAngle</i> and is drawn in the current drawing color.</p> <p>Each graphics driver contains an aspect ratio that is used by <i>Circle</i>, <i>Arc</i>, and <i>PieSlice</i>. A start angle of 0 and an end angle of 360 will draw a complete circle. The angles for <i>Arc</i>, <i>Ellipse</i>, and <i>PieSlice</i> are counterclockwise with 0 degrees at 3 o'clock, 90 degrees at 12 o'clock, and so on. Information about the last call to <i>Arc</i> can be retrieved with a call to <i>GetArcCoords</i>.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>Circle</i> , <i>Ellipse</i> , <i>FillEllipse</i> , <i>GetArcCoords</i> , <i>GetAspectRatio</i> , <i>PieSlice</i> , <i>Sector</i> , <i>SetAspectRatio</i>
<b>Example</b>	<pre> <b>uses</b> Graph; <b>var</b>   Gd, Gm: integer;   Radius: integer; <b>begin</b>   Gd := Detect;   InitGraph(Gd, Gm, '');   <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>     Halt(1);   <b>for</b> Radius := 1 <b>to</b> 5 <b>do</b>     Arc(100, 100, 0, 90, Radius*10);   Readln;   CloseGraph; <b>end.</b> </pre>

---

## ArcTan function

<b>Function</b>	Returns the arctangent of the argument.
<b>Declaration</b>	ArcTan(x: real)
<b>Result type</b>	real

<b>Remarks</b>	<i>x</i> is a real-type expression. The result is the principal value, in radians, of the arctangent of <i>x</i> .
<b>See also</b>	<i>Cos</i> , <i>Sin</i>
<b>Example</b>	<pre> var r: real; begin   r := ArcTan(Pi); end.</pre>

---

## Assign procedure

---

<b>Function</b>	Assigns the name of an external file to a file variable.
<b>Declaration</b>	Assign( <b>var</b> <i>f</i> ; <b>name</b> : <b>string</b> )
<b>Remarks</b>	<p><i>f</i> is a file variable of any file type, and <i>name</i> is a string-type expression. All further operations on <i>f</i> will operate on the external file with the file name <i>name</i>.</p> <p>After a call to <i>Assign</i>, the association between <i>f</i> and the external file continues to exist until another <i>Assign</i> is done on <i>f</i>.</p> <p>A file name consists of a path of zero or more directory names separated by backslashes, followed by the actual file name:</p> <pre>Drive:\DirName\...\DirName\FileName</pre> <p>If the path begins with a backslash, it starts in the root directory; otherwise, it starts in the current directory.</p> <p><i>Drive</i> is a disk drive identifier (A-Z). If <i>Drive</i> and the colon are omitted, the default drive is used. <i>\DirName\...\DirName</i> is the root directory and subdirectory path to the file name. <i>FileName</i> consists of a name of up to eight characters, optionally followed by a period and an extension of up to three characters.</p> <p>The maximum length of the entire file name is 79 characters.</p> <p>A special case arises when <i>name</i> is an empty string; that is, when <i>Length(name)</i> is zero. In that case, <i>f</i> becomes associated with the standard input or standard output file. These special files allow a program to utilize the I/O redirection feature of the DOS operating system. If assigned an empty name, then after a call to <i>Reset(f)</i>, <i>f</i></p>

## Assign procedure

will refer to the standard input file, and after a call to *Rewrite(f)*, *f* will refer to the standard output file.

**Restrictions** *Assign* must never be used on an open file.

**See also** *Append, Close, Reset, Rewrite*

**Example**

```
{ Try redirecting this program from DOS
  to PRN, disk file, etc. }
var f: text;
begin
  Assign(f, ''); { Standard output }
  Rewrite(f);
  Writeln(f, 'standard output...');
  Close(f);
end.
```

---

## AssignCrt procedure

## Crt

---

**Function** Associates a text file with the CRT.

**Declaration** AssignCrt (**var** f: Text)

**Remarks** *AssignCrt* works exactly like the *Assign* standard procedure except that no file name is specified. Instead, the text file is associated with the CRT.

This allows faster output (and input) than would normally be possible using standard output (or input).

**Example**

```
uses Crt;
var f: text;
begin
  Write('Output to screen or printer [S, P]? ');
  if UpCase(ReadKey) = 'P' then
    Assign(f, 'PRN') { Output to printer }
  else
    AssignCrt(f); { Output to screen, use fast CRT routines }
  Rewrite(f);
  Writeln(f, 'Fast output via CRT routines...');
  Close(f);
end.
```

---

## Bar procedure

## Graph

---

<b>Function</b>	Draws a bar using the current fill style and color.
<b>Declaration</b>	<code>Bar(x1, y1, x2, y2: integer)</code>
<b>Remarks</b>	<p>Draws a filled-in rectangle (used in bar charts, for example). Uses the pattern and color defined by <i>SetFillStyle</i> or <i>SetFillPattern</i>. To draw an outlined bar, call <i>Bar3D</i> with a depth of zero.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>Bar3D</i> , <i>GraphResult</i> , <i>SetFillStyle</i> , <i>SetFillPattern</i> , <i>SetLineStyle</i>
<b>Example</b>	<pre> <b>uses</b> Graph; <b>var</b>     Gd, Gm : integer;     I, Width: integer; <b>begin</b>     Gd := Detect;     InitGraph(Gd, Gm, '');     <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>         Halt(1);     Width := 10;     <b>for</b> I := 1 <b>to</b> 5 <b>do</b>         Bar(I*Width, I*10, Succ(I)*Width, 200);     Readln;     CloseGraph; <b>end.</b> </pre>

---

## Bar3D procedure

## Graph

---

<b>Function</b>	Draws a 3-D bar using the current fill style and color.
<b>Declaration</b>	<code>Bar3D(x1, y1, x2, y2: integer; Depth: word; Top: boolean)</code>
<b>Remarks</b>	<p>Draws a filled-in, three-dimensional bar. Uses the pattern and color defined by <i>SetFillStyle</i> or <i>SetFillPattern</i>. The 3-D outline of the bar is drawn in the current line style and color as set by <i>SetLineStyle</i> and <i>SetColor</i>. <i>Depth</i> is the number of pixels deep of the 3-D outline. If <i>Top</i> is True, a 3-D top is put on the bar; if <i>Top</i> is False, no top is</p>

## Bar3D procedure

put on the bar (making it possible to stack several bars on top one another).

A typical depth could be calculated by taking 25% of the width of the bar:

```
Bar3d(x1,y1,x2,y2,(x2-x1+1) div 4, TopOn);
```

The following constants are defined:

```
const
  TopOn  = True;
  TopOff = False;
```

A similar routine exists in Turbo C 2.0.

### Restrictions

Must be in graphics mode.

### See also

*Bar, GraphResult, SetFillPattern, SetFillStyle, SetLineStyle*

### Example

```
uses Graph;
var
  Gd, Gm: integer;
  y0, y1, y2, x1, x2: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  y0 := 10;
  y1 := 60;
  y2 := 110;
  x1 := 10;
  x2 := 50;
  Bar3D(x1, y0, x2, y1, 10, TopOn);
  Bar3D(x1, y1, x2, y2, 10, TopOff);
  Readln;
  CloseGraph;
end.
```

---

## BlockRead procedure

---

### Function

Reads one or more records into a variable.

### Declaration

```
BlockRead(var f: file; var buf; count: word
  [; var result: word ])
```

### Remarks

*f* is an untyped file variable, *buf* is any variable, *count* is an expression of type *word*, and *result* is a variable of type *word*.

*BlockRead* reads *count* or less records from the file *f* into memory, starting at the first byte occupied by *buf*. The actual number of complete records read (less than or equal to *count*) is returned in the optional parameter *result*. If *result* is not specified, an I/O error will occur if the number read is not equal to *count*.

The entire block transferred occupies at most *count* \* *recsize* bytes, where *recsize* is the record size specified when the file was opened (or 128 if it was omitted). It's an error if *count* \* *recsize* is greater than 65535 (64 Kb).

*result* is an optional parameter. Here is how it works: If the entire block was transferred, *result* will be equal to *count* on return. Otherwise, if *result* is less than *count*, the end of the file was reached before the transfer was completed. In that case, if the file's record size is greater than one, *result* returns the number of complete records read; that is, a possible last partial record is not included in *result*.

The current file position is advanced by *result* records as an effect of the *BlockRead*.

With (\$I-), *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

### Restrictions

File must be open.

### Differences

3.0 read partial records; 5.0 discards them.

### See also

*BlockWrite*

### Example

```
program CopyFile;
{ Simple, fast file copy program with NO error-checking }
var
    FromF, ToF: file;
    NumRead, NumWritten: word;
    buf: array[1..2048] of char;
begin
    Assign(FromF, ParamStr(1));           { Open input file }
    Reset(FromF, 1);                      { Record size = 1 }
    Assign(ToF, ParamStr(2));             { Open output file }
    Rewrite(ToF, 1);                      { Record size = 1 }
    Writeln('Copying ', FileSize(FromF), ' bytes...');
    repeat
        BlockRead(FromF, buf, SizeOf(buf), NumRead);
        BlockWrite(ToF, buf, NumRead, NumWritten);
    until (NumRead = 0) or (NumWritten <> NumRead);
```

## BlockWrite procedure

```
Close(FromF);  
Close(ToF);  
end.
```

---

## BlockWrite procedure

---

<b>Function</b>	Writes one or more records from a variable.
<b>Declaration</b>	<code>BlockWrite(BlockWrite(<b>var</b> f: <b>file</b>; <b>var</b> buf; count: word [; <b>var</b> result: word ])</code>
<b>Remarks</b>	<p><i>f</i> is an untyped file variable, <i>buf</i> is any variable, <i>count</i> is an expression of type <i>word</i>, and <i>result</i> is a variable of type <i>word</i>.</p> <p><i>BlockWrite</i> writes <i>count</i> or less records to the file <i>f</i> from memory, starting at the first byte occupied by <i>buf</i>. The actual number of complete records written (less than or equal to <i>count</i>) is returned in the optional parameter <i>result</i>. If <i>result</i> is not specified, an I/O error will occur if the number written is not equal to <i>count</i>.</p> <p>The entire block transferred occupies at most <i>count</i> * <i>recsize</i> bytes, where <i>recsize</i> is the record size specified when the file was opened (or 128 if it was omitted). It is an error if <i>count</i> * <i>recsize</i> is greater than 65535 (64K).</p> <p><i>result</i> is an optional parameter. Here is how it works: If the entire block was transferred, <i>result</i> will be equal to <i>count</i> on return. Otherwise, if <i>result</i> is less than <i>count</i>, the disk became full before the transfer was completed. In that case, if the file's record size is greater than one, <i>result</i> returns the number of complete records written; that is, it's possible a remaining partial record is not included in <i>result</i>.</p> <p>The current file position is advanced by <i>result</i> records as an effect of the <i>BlockWrite</i>.</p> <p>With <i>{I-}</i>, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>
<b>Restrictions</b>	File must be open.
<b>Differences</b>	3.0 read partial records; 5.0 discards them.
<b>See also</b>	<i>BlockRead</i>
<b>Example</b>	See example for <i>BlockRead</i> .

---

## ChDir procedure

---

<b>Function</b>	Changes the current directory.
<b>Declaration</b>	ChDir( <i>s</i> : <b>string</b> )
<b>Remarks</b>	<p><i>s</i> is a string-type expression. The current directory is changed to a path specified by <i>s</i>. If <i>s</i> specifies a drive letter, the current drive is also changed.</p> <p>With {\$I-}, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>
<b>See also</b>	<i>GetDir, Mkdir, Rmdir</i>
<b>Example</b>	<pre> begin   {\$I-}   { Get directory name from command line }   ChDir(ParamStr(1));   if IOResult &lt;&gt; 0 then     Writeln('Cannot find directory');   end. </pre>

---

## Chr function

---

<b>Function</b>	Returns a character with a specified ordinal number.
<b>Declaration</b>	Chr( <i>x</i> : <b>byte</b> )
<b>Result type</b>	<b>char</b>
<b>Remarks</b>	<i>x</i> is an integer-type expression. The result is the character with an ordinal value (ASCII value) of <i>x</i> .
<b>See also</b>	<i>Ord</i>
<b>Example</b>	<pre> uses Printer; begin   Writeln(Lst, Chr(12));           { Send form feed to printer } end. </pre>



---

## Circle procedure

## Graph

---

<b>Function</b>	Draws a circle using (X,Y) as the center point.
<b>Declaration</b>	Circle(X, Y: integer; Radius: word)
<b>Remarks</b>	<p>The circle is drawn in the current color set by <i>SetColor</i>. Each graphics driver contains an aspect ratio that is used by <i>Circle</i>, <i>Arc</i>, and <i>PieSlice</i> to make circles.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>Arc</i> , <i>Ellipse</i> , <i>FillEllipse</i> , <i>GetArcCoords</i> , <i>GetAspectRatio</i> , <i>PieSlice</i> , <i>Sector</i> , <i>SetAspectRatio</i>
<b>Example</b>	<pre> <b>uses</b> Graph; <b>var</b>     Gd, Gm: integer;     Radius: integer; <b>begin</b>     Gd := Detect;     InitGraph(Gd, Gm, '');     <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>         Halt(1);     <b>for</b> Radius := 1 <b>to</b> 5 <b>do</b>         Circle(100, 100, Radius*10);     Readln;     CloseGraph; <b>end.</b> </pre>

---

## ClearDevice procedure

## Graph

---

<b>Function</b>	Clears the graphics screen and prepares it for output.
<b>Declaration</b>	ClearDevice
<b>Remarks</b>	<p><i>ClearDevice</i> moves the current pointer to (0,0), clears the screen using the background color set by <i>SetBkColor</i>, and prepares it for output.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>ClearViewport</i> , <i>CloseGraph</i> , <i>GraphDefaults</i> , <i>InitGraph</i> , <i>RestoreCrtMode</i> , <i>SetGraphMode</i>

**Example**

```

uses Crt, Graph;
var
  Gd, Gm: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  Randomize;
  repeat
    LineTo(Random(200), Random(200));
  until KeyPressed;
  ClearDevice;
  Readln;
  CloseGraph;
end.

```

---

**ClearViewport procedure****Graph**

---

<b>Function</b>	Clears the current viewport.
<b>Declaration</b>	ClearViewport
<b>Remarks</b>	Sets the fill color to the background color ( <i>Palette[0]</i> ), calls <i>Bar</i> , and moves the current pointer to (0,0).  A similar routine exists in Turbo C 2.0.
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>Bar</i> , <i>ClearDevice</i> , <i>GetViewSettings</i> , <i>SetViewport</i>
<b>Example</b>	

```

uses Graph;
var
  Gd, Gm: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  Rectangle(19, 19, GetMaxX-19, GetMaxY-19);
  SetViewport(20, 20, GetMaxX-20, GetMaxY-20, ClipOn);
  OutTextXY(0, 0, '<ENTER> clears viewport:');
  Readln;
  ClearViewport;
  OutTextXY(0, 0, '<ENTER> to quit:');
  Readln;
  CloseGraph;
end.

```

---

## Close procedure

---

<b>Function</b>	Closes an open file.
<b>Declaration</b>	<code>Close(var f)</code>
<b>Remarks</b>	<p><i>f</i> is a file variable of any file type that was previously opened with <i>Reset</i>, <i>Rewrite</i>, or <i>Append</i>. The external file associated with <i>f</i> is completely updated and then closed, and its DOS file handle is freed for reuse.</p> <p>With <i>{I-}</i>, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>
<b>See also</b>	<i>Append</i> , <i>Assign</i> , <i>Reset</i> , <i>Rewrite</i>
<b>Example</b>	<pre> var f: file; begin   Assign(f, '\AUTOEXEC.BAT');           { Open file }   Reset(f, 1);   Writeln('File size = ', FileSize(f));   Close(f);                             { Close file } end.</pre>

---

## CloseGraph procedure

---

## Graph

<b>Function</b>	Shuts down the graphics system.
<b>Declaration</b>	<code>CloseGraph</code>
<b>Remarks</b>	<p><i>CloseGraph</i> restores the original screen mode before graphics was initialized and frees the memory allocated on the heap for the graphics scan buffer. <i>CloseGraph</i> also deallocates driver and font memory buffers if they were allocated by calls to <i>GraphGetMem</i> and <i>GraphFreeMem</i>.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>DetectGraph</i> , <i>GetGraphMode</i> , <i>InitGraph</i> , <i>RestoreCrtMode</i> , <i>SetGraphMode</i>
<b>Example</b>	<pre> uses Graph; var   Gd, Gm: integer; begin   Gd := Detect;</pre>

```

InitGraph(Gd, Gm, '');
if GraphResult <> grOk then
    Halt(1);
Line(0, 0, GetMaxX, GetMaxY);
Readln;
CloseGraph;                                { Shut down graphics }
end.

```

---

## ClrEol procedure

## Crt

<b>Function</b>	Clears all characters from the cursor position to the end of the line without moving the cursor.
<b>Declaration</b>	ClrEol
<b>Remarks</b>	<p>All character positions are set to blanks with the currently defined text attributes. Thus, if <i>TextBackground</i> is not black, the column from the cursor to the right edge of the screen becomes the background color.</p> <p>This procedure is window-relative:</p> <pre> Window(1,1,60,20); ClrEol; </pre> <p>will clear from the current cursor position (1,1) to the right edge of the active window (60,1).</p>
<b>See also</b>	<i>ClrScr, Window</i>
<b>Example</b>	<pre> uses Crt; begin     TextBackground(LightGray);     ClrEol; { Changes cleared columns to LightGray background } end. </pre>

---

## ClrScr procedure

## Crt

<b>Function</b>	Clears the active window and places the cursor in the upper left-hand corner.
<b>Declaration</b>	ClrScr
<b>Remarks</b>	All character positions are set to blanks with the currently defined text attributes. Thus, if <i>TextBackground</i> is

## ClrScr procedure

not black, the entire screen becomes the background color. This also applies to characters cleared by *ClrEol*, *InsLine*, and *DelLine*, as well as empty lines created by scrolling.

This procedure is window-relative:

```
Window(1,1,60,20);  
ClrScr;
```

will clear a 60 × 20 rectangle beginning at (1,1).

**See also**

*ClrEol*, *Window*

**Example**

```
uses Crt;  
begin  
  TextBackground(LightGray);  
  ClrScr;    { Changes entire window to LightGray background }  
end.
```

---

## Concat function

---

**Function**

Concatenates a sequence of strings.

**Declaration**

Concat(s1 [ , s2, ..., sn ]: **string**)

**Result type**

**string**

**Remarks**

Each parameter is a string-type expression. The result is the concatenation of all the string parameters. If the resulting string is longer than 255 characters, it is truncated after the 255th character. Using the plus (+) operator returns the same results as using the *Concat* function:

```
S := 'ABC' + 'DEF';
```

**See also**

*Copy*, *Delete*, *Insert*, *Length*, *Pos*

**Example**

```
var s: string;  
begin  
  s := Concat('ABC', 'DEF');           { 'ABCDEF' }  
end.
```

---

## Copy function

---

<b>Function</b>	Returns a substring of a string.
<b>Declaration</b>	<code>Copy(s: string; index: integer; count: integer)</code>
<b>Result type</b>	string
<b>Remarks</b>	<i>s</i> is a string-type expression. <i>index</i> and <i>count</i> are integer-type expressions. <i>Copy</i> returns a string containing <i>count</i> characters starting with the <i>index</i> th character in <i>s</i> . If <i>index</i> is larger than the length of <i>s</i> , an empty string is returned. If <i>count</i> specifies more characters than remain starting at the <i>index</i> th position, only the remainder of the string is returned.
<b>See also</b>	<i>Concat, Delete, Insert, Length, Pos</i>
<b>Example</b>	<pre> var s: string; begin   s := 'ABCDEF';   s := Copy(s, 2, 3)           { 'BCD' } end.</pre>

---

## Cos function

---

<b>Function</b>	Returns the cosine of the argument.
<b>Declaration</b>	<code>Cos(x: real)</code>
<b>Result type</b>	real
<b>Remarks</b>	<i>x</i> is a real-type expression. The result is the cosine of <i>x</i> . <i>x</i> is assumed to represent an angle in radians.
<b>See also</b>	<i>ArcTan, Sin</i>
<b>Example</b>	<pre> var r: real; begin   r := Cos(Pi); end.</pre>

---

## CSeg function

---

<b>Function</b>	Returns the current value of the CS register.
<b>Declaration</b>	CSeg
<b>Result type</b>	word
<b>Remarks</b>	The result of type word is the segment address of the code segment within which CSeg was called.
<b>See also</b>	DSeg, SSeg

---

## Dec procedure

---

<b>Function</b>	Decrements a variable.
<b>Declaration</b>	Dec( <b>var</b> x [ ; n: longint ])
<b>Remarks</b>	<p><math>x</math> is an ordinal-type variable, and <math>n</math> is an integer-type expression. <math>x</math> is decremented by 1, or by <math>n</math> if <math>n</math> is specified; that is, <math>Dec(x)</math> corresponds to <math>x := x-1</math>, and <math>Dec(x,n)</math> corresponds to <math>x := x-n</math>.</p> <p>Dec generates optimized code and is especially useful in a tight loop.</p>
<b>See also</b>	Inc, Pred, Succ
<b>Example</b>	<pre> <b>var</b>   IntVar: integer;   LongintVar: longint; <b>begin</b>   Dec(IntVar);   Dec(LongintVar, 5); <b>end.</b> </pre> <div style="text-align: right;"> <pre>       { IntVar := IntVar - 1 }       { LongintVar := LongintVar - 5 } </pre> </div>

---

## Delay procedure

---

**Crt**

<b>Function</b>	Delays a specified number of milliseconds.
<b>Declaration</b>	Delay(ms: word)
<b>Remarks</b>	ms specifies the number of milliseconds to wait.

*Delay* is an approximation, so the delay period will not last exactly *ms* milliseconds.

---

## Delete procedure

---

<b>Function</b>	Deletes a substring from a string.
<b>Declaration</b>	Delete( <b>var</b> <i>s</i> : <b>string</b> ; <i>index</i> : integer; <i>count</i> : integer)
<b>Remarks</b>	<i>s</i> is a string-type variable. <i>index</i> and <i>count</i> are integer-type expressions. <i>Delete</i> deletes <i>count</i> characters from <i>s</i> starting at the <i>index</i> th position. If <i>index</i> is larger than the length of <i>s</i> , no characters are deleted. If <i>count</i> specifies more characters than remain starting at the <i>index</i> th position, the remainder of the string is deleted.
<b>See also</b>	<i>Concat, Copy, Insert, Length, Pos</i>

---

## DelLine procedure

---

Crt

<b>Function</b>	Deletes the line containing the cursor.
<b>Declaration</b>	DelLine
<b>Remarks</b>	<p>The line containing the cursor is deleted, and all lines below are moved one line up (using the BIOS scroll routine). A new line is added at the bottom.</p> <p>All character positions are set to blanks with the currently defined text attributes. Thus, if <i>TextBackground</i> is not black, the new line becomes the background color.</p> <p>This procedure is window-relative:</p> <pre>Window(1,10,60,20); DelLine;</pre> <p>will delete the first line in the window, which is the tenth line on the screen.</p>
<b>See also</b>	<i>Insline, Window</i>



---

## DetectGraph procedure

## Graph

---

**Function** Checks the hardware and determines which graphics driver and mode to use.

**Declaration** DetectGraph(**var** GraphDriver, GraphMode: integer)

**Remarks** Returns the detected driver and mode value that can be passed to *InitGraph*, which will then load the correct driver. If no graphics hardware was detected, the *GraphDriver* parameter and *GraphResult* will return a value of -2 (*grNotDetected*).

The following constants are defined:

```

const
    Detect    = 0;                { Request autodetection }
    CGA      = 1;
    MCGA     = 2;
    EGA      = 3;
    EGA64    = 4;
    EGAMono  = 5;
    IBM8514  = 6;
    HercMono = 7;
    ATT400   = 8;
    VGA      = 9;
    PC3270   = 10;

```

Unless instructed otherwise, *InitGraph* calls *DetectGraph*, finds and loads the correct driver, and initializes the graphics system. The only reason to call *DetectGraph* directly is to override the driver that *DetectGraph* recommends. The example that follows identifies the system as a 64K or 256K EGA, and loads the CGA driver instead. Note that when you pass *InitGraph* a *GraphDriver* other than *Detect*, you must also pass in a valid *GraphMode* for the driver requested.

A similar routine exists in Turbo C 2.0.

**Restrictions** You should not use *DetectGraph* (or *Detect* with *InitGraph*) with the IBM 8514 unless you want the emulated VGA mode.

**See also** *CloseGraph*, *GraphResult*, *InitGraph*

**Example**

```

uses Graph;
var
    GraphDriver, GraphMode: integer;
begin

```

```

DetectGraph(GraphDriver, GraphMode);
if (GraphDriver = EGA) or
    (GraphDriver = EGA64) then
    begin
        GraphDriver := CGA;
        GraphMode := CGAHi;
    end;
InitGraph(GraphDriver, GraphMode, '');
if GraphResult <> grOk then
    Halt(1);
Line(0, 0, GetMaxX, GetMaxY);
Readln;
CloseGraph;
end.

```

## DiskFree function

Dos

<b>Function</b>	Returns the number of free bytes on a specified disk drive.
<b>Declaration</b>	DiskFree(Drive: byte)
<b>Result type</b>	longint
<b>Remarks</b>	A <i>Drive</i> of 0 indicates the default drive, 1 indicates drive A, 2 indicates B, and so on. <i>DiskFree</i> returns -1 if the drive number is invalid.
<b>See also</b>	<i>DiskSize</i> , <i>GetDir</i>
<b>Example</b>	<pre> <b>uses</b> Dos; <b>begin</b>     Writeln(DiskFree(0) <b>div</b> 1024, ' k-bytes free '); <b>end</b>. </pre>

## DiskSize function

Dos

<b>Function</b>	Returns the total size in bytes on a specified disk drive.
<b>Declaration</b>	DiskSize(Drive: byte)
<b>Result type</b>	longint
<b>Remarks</b>	A <i>Drive</i> of 0 indicates the default drive, 1 indicates drive A, 2 indicates B, and so on. <i>DiskSize</i> returns -1 if the drive number is invalid.

## DiskSize function

**See also** *DiskFree, GetDir*

**Example**

```
uses Dos;
begin
  Writeln(DiskSize(0) div 1024, ' k-bytes capacity');
end.
```

---

## Dispose procedure

---

**Function** Disposes a dynamic variable.

**Declaration** Dispose(**var** p: pointer)

**Remarks** *p* is a pointer variable of any pointer type that was previously assigned by the *New* procedure or was assigned a meaningful value by an assignment statement. *Dispose* destroys the variable referenced by *p* and returns its memory region to the heap. After a call to *Dispose*, the value of *p* becomes undefined, and it is an error to subsequently reference *p*<sup>^</sup>.

**Restrictions** If *p* does not point to a memory region in the heap, a run-time error occurs.

*Dispose* and *FreeMem* cannot be used interchangeably with *Mark* and *Release* unless certain rules are observed. For a complete discussion of this topic, refer to the section "The Heap Manager" on page 181.

**See also** *FreeMem, GetMem, Mark, New, Release*

**Example**

```
type
  Str18 = string[18];
var
  p: ^Str18;
begin
  New(p);
  p^ := 'Now you see it...';
  Dispose(p);
end.                                     { Now you don't... }
```

---

## DosExitCode function

Dos

---

<b>Function</b>	Returns the exit code of a subprocess.
<b>Declaration</b>	DosExitCode
<b>Result type</b>	word
<b>Remarks</b>	<p>The low byte is the code sent by the terminating process. The high byte is set to</p> <ul style="list-style-type: none"> <li>■ 0 for normal termination</li> <li>■ 1 if terminated by <i>Ctrl-C</i></li> <li>■ 2 if terminated due to a device error</li> <li>■ 3 if terminated by the <i>Keep</i> procedure</li> </ul>
<b>See also</b>	<i>Exec, Keep</i>

---



---

## DosVersion function

Dos

---

<b>Function</b>	Returns the DOS version number.
<b>Declaration</b>	DosVersion
<b>Result type</b>	word
<b>Remarks</b>	<p><i>DosVersion</i> returns the DOS version number. The low byte of the result is the major version number, and the high byte is the minor version number. For example, DOS 3.20 returns 3 in the low byte, and 20 in the high byte.</p>
<b>Example</b>	<pre> <b>uses</b> Dos; <b>var</b>     Ver: word; <b>begin</b>     Ver:=DosVersion;     Writeln('This is DOS version ',Lo(Ver),'.',Hi(Ver)); <b>end.</b> </pre>

---

---

## DrawPoly procedure

## Graph

---

<b>Function</b>	Draws the outline of a polygon using the current line style and color.
<b>Declaration</b>	<code>DrawPoly(NumPoints: word; <b>var</b> PolyPoints)</code>
<b>Remarks</b>	<p><i>PolyPoints</i> is an untyped parameter that contains the coordinates of each intersection in the polygon. <i>NumPoints</i> specifies the number of coordinates in <i>PolyPoints</i>. A coordinate consists of two words, an <i>x</i> and a <i>y</i> value.</p> <p><i>DrawPoly</i> uses the current line style and color. Use <i>SetWriteMode</i> to determine whether the polygon is copied to or XOR'd to the screen.</p> <p>Note that in order to draw a closed figure with <i>n</i> vertices, you must pass <i>N + 1</i> coordinates to <i>DrawPoly</i>, and where <i>PolyPoints[n+1] = PolyPoints[1]</i> (see the example that follows). In order to draw a triangle, for example, four coordinates must be passed to <i>DrawPoly</i>.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>FillPoly</i> , <i>GetLineSettings</i> , <i>GraphResult</i> , <i>SetColor</i> , <i>SetLineStyle</i> , <i>SetWriteMode</i>
<b>Example</b>	<pre> <b>uses</b> Graph; <b>const</b>     Triangle: <b>array</b>[1..4] <b>of</b> PointType = ((x: 50; y: 100),  (x: 100; y: 100),  (x: 150; y: 150),  (x: 50; y: 100));  <b>var</b>     Gd, Gm: integer; <b>begin</b>     Gd := Detect;     InitGraph(Gd, Gm, '');     <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>         Halt(1);      DrawPoly(SizeOf(Triangle) <b>div</b> SizeOf(PointType),               Triangle);     Readln;     CloseGraph; <b>end.</b> </pre>

---

## DSeg function

---

<b>Function</b>	Returns the current value of the DS register.
<b>Declaration</b>	DSeg
<b>Result type</b>	word
<b>Remarks</b>	The result of type word is the segment address of the data segment.
<b>See also</b>	CSeg, SSeg

---

## Ellipse procedure

---



---

## Graph

---

<b>Function</b>	Draws an elliptical arc from start angle to end angle, using (X,Y) as the center point.
<b>Declaration</b>	Ellipse(X, Y: integer; StAngle, EndAngle: word; XRadius, YRadius: word)
<b>Remarks</b>	<p>Draws an elliptical arc using (X,Y) as a center point, and <i>XRadius</i> and <i>YRadius</i> as the horizontal and vertical axes. The ellipse travels from <i>StAngle</i> to <i>EndAngle</i> and is drawn in the current color.</p> <p>A start angle of 0 and an end angle of 360 will draw a complete oval. The angles for <i>Arc</i>, <i>Ellipse</i>, and <i>PieSlice</i> are counterclockwise with 0 degrees at 3 o'clock, 90 degrees at 12 o'clock, and so on. Information about the last call to <i>Ellipse</i> can be retrieved with a call to <i>GetArcCoords</i>.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>Arc</i> , <i>Circle</i> , <i>FillEllipse</i> , <i>GetArcCoords</i> , <i>GetAspectRatio</i> , <i>PieSlice</i> , <i>Sector</i> , <i>SetAspectRatio</i>
<b>Example</b>	<pre> <b>uses</b> Graph; <b>var</b>   Gd, Gm: integer; <b>begin</b>   Gd := Detect;   InitGraph(Gd, Gm, '');   <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>     Halt(1); </pre>

```

Ellipse(100,100,0,360,30,50);
Ellipse(100,100,0,180,50,30);
Readln;
CloseGraph;
end.

```

---

## EnvCount function

## Dos

<b>Function</b>	Returns the number of strings contained in the DOS environment.
<b>Declaration</b>	<code>EnvCount</code>
<b>Result type</b>	integer
<b>Remarks</b>	<p><i>EnvCount</i> returns the number of strings contained in the DOS environment. Each environment string is of the form <i>VAR=VALUE</i>. The strings can be examined with the <i>EnvStr</i> function.</p> <p>For more information about the DOS environment, refer to your DOS manuals.</p>
<b>See also</b>	<i>EnvStr</i> , <i>GetEnv</i>
<b>Example</b>	<pre> uses Dos; var   I: integer; begin   for I := 1 to EnvCount do     Writeln(EnvStr(I));   end. </pre>

---

## EnvStr function

## Dos

<b>Function</b>	Returns a specified environment string.
<b>Declaration</b>	<code>EnvStr(Index: integer)</code>
<b>Result type</b>	string
<b>Remarks</b>	<p><i>EnvStr</i> returns a specified string from the DOS environment. The string <i>EnvStr</i> returns is of the form <i>VAR=VALUE</i>. The index of the first string is one. If <i>Index</i> is less than one or greater than <i>EnvCount</i>, <i>EnvStr</i> returns an empty string.</p>

For more information about the DOS environment, refer to your DOS manuals.

**See also** *EnvCount, GetEnv*

---

## Eof function (text files)

---

<b>Function</b>	Returns the end-of-file status of a text file.
<b>Declaration</b>	<code>Eof [ (var f: text) ]</code>
<b>Result type</b>	boolean
<b>Remarks</b>	<p><i>f</i>, if specified, is a text-file variable. If <i>f</i> is omitted, the standard file variable <i>Input</i> is assumed. <i>Eof(f)</i> returns True if the current file position is beyond the last character of the file or if the file contains no components; otherwise, <i>Eof(f)</i> returns False.</p> <p>With <i>{\$I-}</i>, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>

**See also** *Eoln, SeekEof*

**Example**

```

var
  f : text;
  ch: char;
begin
  { Get file to read from command line }
  Assign(f, ParamStr(1));
  Reset(f);
  while not Eof(f) do
  begin
    Read(f,ch);
    Write(ch);                                { Dump text file }
  end;
end.
```

---

## Eof function (typed, untyped files)

---

<b>Function</b>	Returns the end-of-file status of a typed or untyped file.
<b>Declaration</b>	<code>Eof(var f)</code>
<b>Result type</b>	boolean



## Eof function (typed, untyped files)

Remarks	<p><i>f</i> is a file variable. <i>Eof(f)</i> returns True if the current file position is beyond the last component of the file or if the file contains no components; otherwise, <i>Eof(f)</i> returns False.</p> <p>With {<i>I</i>-}, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>
---------	---

---

## Eoln function

---

Function	Returns the end-of-line status of a file.
Declaration	<code>Eoln [ (var f: text) ]</code>
Result type	boolean
Remarks	<p><i>f</i>, if specified, is a text-file variable. If <i>f</i> is omitted, the standard file variable <i>Input</i> is assumed. <i>Eoln(f)</i> returns True if the current file position is at an end-of-line marker or if <i>Eof(f)</i> is True; otherwise, <i>Eoln(f)</i> returns False.</p> <p>When checking <i>Eoln</i> on standard input that has not been redirected, the following program will wait for a carriage return to be entered before returning from the call to <i>Eoln</i>:</p> <pre>begin   { Tells program to wait for keyboard input }   Writeln(Eoln); end.</pre> <p>With {<i>I</i>-}, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>
See also	<i>Eof</i> , <i>SeekEoln</i>

---

## Erase procedure

---

Function	Erases an external file.
Declaration	<code>Erase(var f)</code>
Remarks	<i>f</i> is a file variable of any file type. The external file associated with <i>f</i> is erased.

With `{I-}`, *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

**Restrictions** *Erase* must never be used on an open file.

**See also** *Rename*

**Example**

```

var
  f : file;
  ch: char;
begin
  { Get file to delete from command line }
  Assign(f, ParamStr(1));
  {I-}
  Reset(f);
  {I+}
  if IOResult <> 0 then
    Writeln('Cannot find ', ParamStr(1))
  else
    begin
      Close(f);
      Write('Erase ', ParamStr(1), '? ');
      Readln(ch);
      if UpCase(ch) = 'Y' then
        Erase(f);
    end;
  end.

```

---

## Exec procedure

## Dos

**Function** Executes a specified program with a specified command line.

**Declaration** `Exec(Path, CmdLine: string)`

**Remarks** The program name is given by the *Path* parameter, and the command line is given by *CmdLine*. To execute a DOS internal command, run `COMMAND.COM`; for instance,

```
Exec('COMMAND.COM', '/C DIR *.PAS');
```

The `/C` in front of the command is a requirement of `COMMAND.COM` (but not of other applications). Errors are reported in *DosError*; possible error codes are 2, 8, 10, and 11. The exit code of any child process is reported by the *DosExitCode* function.

## Exec procedure

It is recommended that *SwapVectors* be called just before and just after the call to *Exec*. *SwapVectors* swaps the contents of the *SaveIntXX* pointers in the *System* unit with the current contents of the interrupt vectors. This ensures that the *Exec*'d process does not use any interrupt handlers installed by the current process, and vice versa.

*Exec* does not change the memory allocation state before executing the program. Therefore, when compiling a program that uses *Exec*, be sure to reduce the "maximum" heap size; otherwise, there won't be enough memory (*DosError* = 8).

### Restrictions

Versions of the Novell Network system software earlier than 2.01 or 2.02 do not support a DOS call used by *Exec*. If you are using the integrated development environment to run a program that uses *Exec*, and you have early Novell system software, set Compile/Destination to Disk and run your program from DOS (you can use the File/OS Shell command to do this).

### See also

*DosExitCode*, *SwapVectors*

### Example

```
{ $M $4000,0,0 } { 16K stack, no heap required or reserved }
uses Dos;
var
  ProgramName, CmdLine: string;
begin
  Write('Program to Exec (include full path): ');
  Readln(ProgramName);
  Write('Command line to pass to ', ProgramName, ': ');
  Readln(CmdLine);
  Writeln('About to Exec...');
  SwapVectors;
  Exec(ProgramName, CmdLine);
  SwapVectors;
  Writeln('...back from Exec');
  if DosError <> 0 then { Error? }
    Writeln('Dos error #', DosError)
  else
    Writeln('Exec successful. ',
      'Child process exit code = ',
      DosExitCode);
end.
```

---

## Exit procedure

---

<b>Function</b>	Exits immediately from the current block.
<b>Declaration</b>	<code>Exit</code>
<b>Remarks</b>	When <i>Exit</i> is executed in a subroutine (procedure or function), it causes the subroutine to return. When it is executed in the statement part of a program, it causes the program to terminate. A call to <i>Exit</i> is analogous to a <code>goto</code> statement addressing a label just before the <code>end</code> of a block.
<b>See also</b>	<i>Halt</i>
<b>Example</b>	<pre>uses Crt; procedure WasteTime; begin     repeat         if KeyPressed then Exit;         Write('Xx');     until False; end; begin     WasteTime; end.</pre>

---

## Exp function

---

<b>Function</b>	Returns the exponential of the argument.
<b>Declaration</b>	<code>Exp(x: real)</code>
<b>Result type</b>	<code>real</code>
<b>Remarks</b>	$x$ is a real-type expression. The result is the exponential of $x$ ; that is, the value $e$ raised to the power of $x$ , where $e$ is the base of the natural logarithms.
<b>See also</b>	<i>Ln</i>

---

## FExpand function

Dos

---

<b>Function</b>	Expands a file name into a fully qualified file name.
<b>Declaration</b>	<code>FExpand(Path: PathStr)</code>
<b>Result type</b>	<i>PathStr</i>
<b>Remarks</b>	<p>Expands the file name in <i>Path</i> into a fully qualified file name. The resulting name is converted to uppercase and consists of a drive letter, a colon, a root relative directory path, and a file name. Embedded '.' and '..' directory references are removed.</p> <p>The <i>PathStr</i> type is defined in the <i>Dos</i> unit as <code>string[79]</code>.</p> <p>Assuming that the current drive and directory is C:\SOURCE\PAS, the following <i>FExpand</i> calls would produce these values:</p> <pre> FExpand('test.pas')      = 'C:\SOURCE\PAS\TEST.PAS' FExpand('..\*.TPU')      = 'C:\SOURCE\*.TPU' FExpand('c:\bin\turbo.exe') = 'C:\BIN\TURBO.EXE' </pre> <p>The <i>FSplit</i> procedure may be used to split the result of <i>FExpand</i> into a drive/directory string, a file name string, and an extension string.</p>
<b>See also</b>	<i>FindFirst, FindNext, FSplit</i>

---

## FilePos function

---

<b>Function</b>	Returns the current file position of a file.
<b>Declaration</b>	<code>FilePos(var f)</code>
<b>Result type</b>	<code>longint</code>
<b>Remarks</b>	<p><i>f</i> is a file variable. If the current file position is at the beginning of the file, <i>FilePos(f)</i> returns 0. If the current file position is at the end of the file—that is, if <i>Eof(f)</i> is True—<i>FilePos(f)</i> is equal to <i>FileSize(f)</i>.</p> <p>With <i>{\$I-}</i>, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>
<b>Restrictions</b>	Cannot be used on a text file. File must be open.

---

Differences	The result type in 3.0 was an integer.
See also	<i>FileSize</i> , <i>Seek</i>

---

## FileSize function

---

Function	Returns the current size of a file.
Declaration	<code>FileSize(<b>var</b> f)</code>
Result type	<code>longint</code>
Remarks	<p><i>f</i> is a file variable. <i>FileSize(f)</i> returns the number of components in <i>f</i>. If the file is empty, <i>FileSize(f)</i> returns 0.</p> <p>With <i>{\$I-}</i>, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>
Restrictions	Cannot be used on a text file. File must be open.
Differences	The result type in 3.0 was an integer.
See also	<i>FilePos</i>
Example	<pre><b>var</b>     f: <b>file of</b> byte; <b>begin</b>     { Get file name from command line }     Assign(f, ParamStr(1));     Reset(f);     Writeln('File size in bytes: ', FileSize(f));     Close(f); <b>end.</b></pre>

---

## FillChar procedure

---

Function	Fills a specified number of contiguous bytes with a specified value.
Declaration	<code>FillChar(<b>var</b> x; count: word; value)</code>
Remarks	<p><i>x</i> is a variable reference of any type. <i>count</i> is an expression of type <i>word</i>. <i>value</i> is any ordinal-type expression. <i>FillChar</i> writes <i>count</i> contiguous bytes of memory into <i>value</i>, starting at the first byte occupied by <i>x</i>. No range-checking is performed, so be careful.</p>

## FillChar procedure

Whenever possible, use the *SizeOf* function to specify the count parameter. When using *FillChar* on strings, remember to set the length byte after the fill.

### See also

*Move*

### Example

```
var s: string[80];
begin
  { Set a string to all spaces }
  FillChar(s, SizeOf(s), ' ');
  s[0] := #80; { Set length byte }
end.
```

---

## FillEllipse procedure

## Graph

---

**Function** Draws a filled ellipse.

**Declaration** FillEllipse(X, Y: integer; XRadius, YRadius: word)

**Remarks** Draws a filled ellipse using (X,Y) as a center point, and *XRadius* and *YRadius* as the horizontal and vertical axes. The ellipse is filled with the current fill color and fill style, and is bordered with the current color.

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *Arc, Circle, Ellipse, GetArcCoords, GetAspectRatio, PieSlice, Sector, SetAspectRatio*

### Example

```
uses
  Graph;
const
  R = 30;
var
  Driver, Mode : integer;
  Xasp, Yasp : word;
begin
  Driver := Detect; { Put in graphics mode }
  InitGraph(Driver, Mode, '');
  if GraphResult < 0 then
    Halt(1);
  { Draw ellipse }
  FillEllipse(GetMaxX div 2, GetMaxY div 2, 50, 50);
  GetAspectRatio(Xasp, Yasp);
  { Circular ellipse }
  FillEllipse(R, R, R, R * LongInt(Xasp) div Yasp);
```

```

    Readln;
    Closegraph;
end.

```

---

## FillPoly procedure

## Graph

---

<b>Function</b>	Draws and fills a polygon, using the scan converter.
<b>Declaration</b>	<code>FillPoly(NumPoints: word; var PolyPoints)</code>
<b>Remarks</b>	<p><i>PolyPoints</i> is an untyped parameter that contains the coordinates of each intersection in the polygon. <i>NumPoints</i> specifies the number of coordinates in <i>PolyPoints</i>. A coordinate consists of two words, an <i>x</i> and a <i>y</i> value.</p> <p><i>FillPoly</i> calculates all the horizontal intersections, and then fills the polygon using the current fill style and color defined by <i>SetFillStyle</i> or <i>SetFillPattern</i>. The outline of the polygon is drawn in the current line style and color as set by <i>SetLineStyle</i>.</p> <p>If an error occurs while filling the polygon, <i>GraphResult</i> will return a value of <code>-6 (grNoScanMem)</code>.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>DrawPoly, GetFillSettings, GetLineSettings, GraphResult, SetFillPattern, SetFillStyle, SetLineStyle</i>

**Example**

```

uses Graph;
const
    Triangle : array[1..3] of PointType = ((x: 50; y: 100),
                                             (x: 100; y: 100),
                                             (x: 150; y: 150));

var
    Gd, Gm : integer;
begin
    Gd := Detect;
    InitGraph(Gd, Gm, '');
    if GraphResult <> grOk then
        Halt(1);
    FillPoly(SizeOf(Triangle) div SizeOf(PointType), Triangle);

```



## FindFirst procedure

```
    Readln;  
    CloseGraph;  
end.
```

---

## FindFirst procedure

## Dos

---

**Function** Searches the specified (or current) directory for the first entry matching the specified file name and set of attributes.

**Declaration** FindFirst(Path: **string**; Attr: word; **var** S: SearchRec)

**Remarks** *Path* is the directory mask (for example, \*.\*). The *Attr* parameter specifies the special files to include (in addition to all normal files). Here are the file attributes as they are declared in the *Dos* unit:

```
const  
    ReadOnly  = $01;  
    Hidden    = $02;  
    SysFile   = $04;  
    VolumeID  = $08;  
    Directory = $10;  
    Archive   = $20;  
    AnyFile   = $3F;
```

The result of the directory search is returned in the specified search record. *SearchRec* is declared in the *Dos* unit:

```
type  
    SearchRec = record  
        Fill: array[1..21] of byte;  
        Attr: byte;  
        Time: longint;  
        Size: longint;  
        Name: string[12];  
    end;
```

Errors are reported in *DosError*; possible error codes are 3 (Directory Not Found) and 18 (No More Files).

**See also** *FExpand*, *FindNext*

### Example

```
uses Dos;  
  
var  
    DirInfo: SearchRec;  
  
begin  
    FindFirst('*.PAS', Archive, DirInfo); { Same as DIR *.PAS }
```

```

while DosError = 0 do
begin
  Writeln(DirInfo.Name);
  FindNext(DirInfo);
end;
end.

```

---

## FindNext procedure

Dos

---

<b>Function</b>	Returns the next entry that matches the name and attributes specified in a previous call to <i>FindFirst</i> .
<b>Declaration</b>	<code>FindNext (var S: SearchRec)</code>
<b>Remarks</b>	S must be the same one Passed to <i>FindFirst</i> ( <i>SearchRec</i> is declared in <i>Dos</i> unit; see <i>FindFirst</i> ). Errors are reported in <i>DosError</i> ; the only possible error code is 18, which indicates no more files.
<b>See also</b>	<i>FindFirst</i> , <i>FExpand</i>
<b>Example</b>	See the example for <i>FindFirst</i> .

---

## FloodFill procedure

Graph

---

<b>Function</b>	Fills a bounded region with the current fill pattern.
<b>Declaration</b>	<code>FloodFill(x, y: integer; Border: word)</code>
<b>Remarks</b>	<p>This procedure is called to fill an enclosed area on bitmap devices. (x,y) is a seed within the enclosed area to be filled. The current fill pattern, as set by <i>SetFillStyle</i> or <i>SetFillPattern</i>, is used to flood the area bounded by <i>Border</i> color. If the seed point is within an enclosed area, then the inside will be filled. If the seed is outside the enclosed area, then the exterior will be filled.</p> <p>If an error occurs while flooding a region, <i>GraphResult</i> will return a value of -7 (<i>grNoFloodMem</i>).</p> <p>Note that <i>FloodFill</i> stops after two blank lines have been output. This can occur with a sparse fill pattern and a small polygon. In the following program, the rectangle is not completely filled:</p>

---

## FloodFill procedure

```
program StopFill;
uses Graph;
var
  Driver, Mode: integer;
begin
  Driver := Detect;
  InitGraph(Driver, Mode, 'c:\bgi');
  if GraphResult <> grOk then
    Halt(1);
  SetFillStyle(LtSlashFill, GetMaxColor);
  Rectangle(0, 0, 8, 20);
  FloodFill(1, 1, GetMaxColor);
  Readln;
  CloseGraph;
end.
```

In this case, using a denser fill pattern like *SlashFill* will completely fill the figure.

A similar routine exists in Turbo C 2.0.

### Restrictions

Use *FillPoly* instead of *FloodFill* whenever possible so that you can maintain code compatibility with future versions. Must be in graphics mode. This procedure is not available when using the IBM 8514 graphics driver (IBM8514.BGI).

### See also

*FillPoly*, *GraphResult*, *SetFillPattern*, *SetFillStyle*

### Example

```
uses Graph;
var
  Gd, Gm: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  SetColor(GetMaxColor);
  Circle(50, 50, 20);
  FloodFill(50, 50, GetMaxColor);
  Readln;
  CloseGraph;
end.
```

---

## Flush procedure

---

<b>Function</b>	Flushes the buffer of a text file open for output.
<b>Declaration</b>	Flush( <b>var</b> f: text)
<b>Remarks</b>	<p><i>f</i> is a text-file variable.</p> <p>When a text file has been opened for output using <i>Rewrite</i> or <i>Append</i>, a call to <i>Flush</i> will empty the file's buffer. This guarantees that all characters written to the file at that time have actually been written to the external file. <i>Flush</i> has no effect on files opened for input.</p> <p>With <math>\{ \\$I - \}</math>, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>

---

## Frac function

---

<b>Function</b>	Returns the fractional part of the argument.
<b>Declaration</b>	Frac(x: real)
<b>Result type</b>	real
<b>Remarks</b>	<i>x</i> is a real-type expression. The result is the fractional part of <i>x</i> , that is, $Frac(x) = x - Int(x)$ .
<b>See also</b>	<i>Int</i>
<b>Example</b>	<pre><b>var</b> r: real; <b>begin</b>   r := Frac(123.456);    { 0.456 }   r :=Frac(-123.456);   { -0.456 } <b>end.</b></pre>

---

## FreeMem procedure

---

<b>Function</b>	Disposes a dynamic variable of a given size.
<b>Declaration</b>	FreeMem( <b>var</b> p: pointer; size: word)
<b>Remarks</b>	<i>p</i> is a pointer variable of any pointer type that was previously assigned by the <i>GetMem</i> procedure or was

## FreeMem procedure

assigned a meaningful value by an assignment statement. *Size* is an expression of type `word`, specifying the size in bytes of the dynamic variable to dispose; it must be *exactly* the number of bytes previously allocated to that variable by *GetMem*. *FreeMem* destroys the variable referenced by *p* and returns its memory region to the heap. If *p* does not point to a memory region in the heap, a run-time error occurs. After a call to *FreeMem*, the value of *p* becomes undefined, and it is an error to subsequently reference *p*<sup>^</sup>.

<b>Restrictions</b>	<i>Dispose</i> and <i>FreeMem</i> cannot be used interchangeably with <i>Mark</i> and <i>Release</i> unless certain rules are observed. For a complete discussion of this topic, refer to the section "The Heap Manager" on page 181.
<b>Differences</b>	In 3.0, <i>size</i> was an integer.
<b>See also</b>	<i>Dispose</i> , <i>GetMem</i> , <i>Mark</i> , <i>New</i> , <i>Release</i>

---

## FSearch function

## Dos

<b>Function</b>	Searches for a file in a list of directories.
<b>Declaration</b>	<code>FSearch(Path: PathStr; DirList: <b>string</b>)</code>
<b>Result type</b>	<i>PathStr</i>
<b>Remarks</b>	<p>Searches for the file given by <i>Path</i> in the list of directories given by <i>DirList</i>. The directories in <i>DirList</i> must be separated by semicolons, just like the directories specified in a <code>PATH</code> command in DOS. The search always starts with the current directory of the current drive. The returned value is a concatenation of one of the directory paths and the file name, or an empty string if the file could not be located.</p> <p>The <i>PathStr</i> type is defined in the <i>Dos</i> unit as <code>string[79]</code>.</p> <p>To search the <code>PATH</code> used by DOS to locate executable files, call <i>GetEnv</i>('PATH') and pass the result to <i>FSearch</i> as the <i>DirList</i> parameter.</p> <p>The result of <i>FSearch</i> can be passed to <i>FExpand</i> to convert it into a fully qualified file name, that is, an uppercase file name that includes both a drive letter and a root-relative directory path. In addition, you can use</p>

*FSplit* to split the file name into a drive/directory string, a file name string, and an extension string.

See also

*FExpand, FSplit, GetEnv*

Example

```
uses Dos;
var
  S: PathStr;
begin
  S := FSearch('TURBO.EXE', GetEnv('PATH'));
  if S = '' then
    Writeln('TURBO.EXE not found')
  else
    Writeln('Found as ', FExpand(S));
end.
```

---

## FSplit procedure

## Dos

---

**Function** Splits a file name into its three components.

**Declaration** `FSplit(Path: PathStr; var Dir: DirStr;  
var Name: NameStr; var Ext: ExtStr)`

**Remarks** Splits the file name specified by *Path* into its three components. *Dir* is set to the drive and directory path with any leading and trailing backslashes, *Name* is set to the file name, and *Ext* is set to the extension with a preceding dot. Each of the component strings may possibly be empty, if *Path* contains no such component.

The *PathStr*, *DirStr*, *NameStr*, and *ExtStr* types are defined in the *Dos* unit as follows:

```
type
  PathStr = string[79];
  DirStr = string[67];
  NameStr = string[8];
  ExtStr = string[4];
```

*FSplit* never adds or removes characters when it splits the file name, and the concatenation of the resulting *Dir*, *Name*, and *Ext* will always equal the specified *Path*.

See also

*FExpand, FindFirst, FindNext*

Example

```
uses Dos;
var
  P: PathStr;
  D: DirStr;
```

```

N: NameStr;
E: ExtStr;
begin
  Write('Filename (WORK.PAS): ');
  ReadLn(P);
  FSplit(P, D, N, E);
  if N = '' then N:='WORK';
  if E = '' then E:='.PAS';
  P := D + N + E;
  Writeln('Resulting name is ', P);
end.

```

---

## GetArcCoords procedure

## Graph

---

**Function** Allows the user to inquire about the coordinates of the last *Arc* command.

**Declaration** GetArcCoords (**var** ArcCoords: ArcCoordsType)

A similar routine exists in Turbo C 2.0.

**Remarks** *GetArcCoords* returns a variable of type *ArcCoordsType*. *ArcCoordsType* is predeclared as follows:

```

type
  ArcCoordsType = record
    X, Y: integer;
    Xstart, Ystart: integer;
    Xend, Yend: integer;
  end;

```

*GetArcCoords* returns a variable containing the center point (X,Y), the starting position (Xstart,Ystart), and the ending position (Xend,Yend) of the last *Arc* or *Ellipse* command. These values are useful if you need to connect a line to the end of an ellipse.

**Restrictions** Must be in graphics mode.

**See also** *Arc*, *Circle*, *Ellipse*, *FillEllipse*, *PieSlice*, *PieSliceXY*, *Sector*

**Example**

```

uses Graph;
var
  Gd, Gm : integer;
  ArcCoords : ArcCoordsType;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then

```

```

    Halt(1);
    Arc(100,100,0,270,30);
    GetArcCoords(ArcCoords);
    with ArcCoords do
        Line(Xstart, Ystart, Xend, Yend);
    Readln;
    CloseGraph;
end.

```

---

## GetAspectRatio procedure

## Graph

---

**Function** Returns the effective resolution of the graphics screen from which the aspect ratio (*Xasp:Yasp*) can be computed.

**Declaration** GetAspectRatio(**var** Xasp, Yasp: word)

**Remarks** Each driver and graphics mode has an aspect ratio associated with it (maximum *y* resolution divided by maximum *x* resolution). This ratio can be computed by making a call to *GetAspectRatio* and then dividing the *Xasp* parameter by the *Yasp* parameter. This ratio is used to make circles, arcs, and pie slices round.

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *Arc, Circle, Ellipse, GetMaxX, GetMaxY, PieSlice, SetAspectRatio*

**Example**

```

uses Graph;
var
    Gd, Gm : integer;
    Xasp, Yasp : word;
    XSideLength, YSideLength : integer;
begin
    Gd := Detect;
    InitGraph(Gd, Gm, '');
    if GraphResult <> grOk then
        Halt(1);
    GetAspectRatio(Xasp, Yasp);
    XSideLength := 20;

    { Adjust Y length for aspect ratio }
    YSideLength := Round((Xasp/Yasp) * XSideLength);

```



## GetBkColor function

```
{ Draw a "square" rectangle on the screen }  
Rectangle(0, 0, XSideLength, YSideLength);  
Readln;  
CloseGraph;  
end.
```

---

## GetBkColor function

## Graph

<b>Function</b>	Returns the index into the palette of the current background color.
<b>Declaration</b>	GetBkColor
<b>Result type</b>	word
<b>Remarks</b>	<p>Background colors can range from 0 to 15, depending on the current graphics driver and current graphics mode.</p> <p><i>GetBkColor</i> will return 0 if the 0th palette entry is changed by a call to <i>SetPalette</i> or <i>SetAllPalette</i>.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>GetColor, GetPalette, InitGraph, SetAllPalette, SetBkColor, SetColor, SetPalette</i>
<b>Example</b>	<pre><b>uses</b> Crt, Graph; <b>var</b>   Gd, Gm: integer;   Color: word;   Pal: PaletteType; <b>begin</b>   Gd := Detect;   InitGraph(Gd, Gm, '');   <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>     Halt(1);   Randomize;   GetPalette(Pal);   <b>if</b> Pal.Size &lt;&gt; 1 <b>then</b>     <b>begin</b>       <b>repeat</b> { Cycle through colors }         Color := Succ(GetBkColor);         <b>if</b> Color &gt; Pal.Size-1 <b>then</b>           Color := 0;         SetBkColor(Color);         LineTo(Random(GetMaxX), Random(GetMaxY));       <b>until</b> KeyPressed;</pre>

```

    end
  else
    Line(0, 0, GetMaxX, GetMaxY);
    Readln;
    CloseGraph;
  end.

```

---

## GetCBreak procedure

Dos

---

<b>Function</b>	Returns the state of <i>Ctrl-Break</i> checking in DOS.
<b>Declaration</b>	GetCBreak( <b>var</b> Break: boolean)
<b>Remarks</b>	<i>GetCBreak</i> returns the state of <i>Ctrl-Break</i> checking in DOS. When off (False), DOS only checks for <i>Ctrl-Break</i> during I/O to console, printer, or communication devices. When on (True), checks are made at every system call.
<b>See also</b>	<i>SetCBreak</i>

---



---

## GetColor function

Graph

---

<b>Function</b>	Returns the color value passed to the previous successful call to <i>SetColor</i> .
<b>Declaration</b>	GetColor
<b>Result type</b>	word
<b>Remarks</b>	Drawing colors can range from 0 to 15, depending on the current graphics driver and current graphics mode. A similar routine exists in Turbo C 2.0.
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>GetBkColor</i> , <i>GetPalette</i> , <i>InitGraph</i> , <i>SetAllPalette</i> , <i>SetColor</i> , <i>SetPalette</i>
<b>Example</b>	<pre> <b>uses</b> Graph; <b>var</b>   Gd, Gm: integer;   Color: word;   Pal: PaletteType;  <b>begin</b>   Gd := Detect; </pre>

---

## GetColor function

```
InitGraph(Gd, Gm, '');  
if GraphResult <> grOk then  
  Halt(1);  
Randomize;  
GetPalette(Pal);  
repeat  
  Color := Succ(GetColor);  
  if Color > Pal.Size-1 then  
    Color := 0;  
  SetColor(Color);  
  LineTo(Random(GetMaxX), Random(GetMaxY));  
until KeyPressed;  
CloseGraph;  
end.
```

---

## GetDate procedure

Dos

---

<b>Function</b>	Returns the current date set in the operating system.
<b>Declaration</b>	GetDate( <b>var</b> Year, Month, Day, DayOfWeek: word)
<b>Remarks</b>	Ranges of the values returned are <i>Year</i> 1980..2099, <i>Month</i> 1..12, <i>Day</i> 1..31, and <i>DayOfWeek</i> 0..6 (where 0 corresponds to Sunday).
<b>See also</b>	<i>GetTime, SetDate, SetTime</i>

---

## GetDefaultPalette function

Graph

---

<b>Function</b>	Returns the palette definition record.
<b>Declaration</b>	GetDefaultPalette ( <b>var</b> Palette : PaletteType)
<b>Result type</b>	<i>PaletteType</i>
<b>Remarks</b>	<i>GetDefaultPalette</i> returns a <i>PaletteType</i> record, which contains the palette as the driver initialized it during <i>InitGraph</i> :

```
const  
  MaxColors = 15;  
type  
  PaletteType = record  
    Size : byte;  
    Colors : array[0..MaxColor] of shortint;  
  end;
```

A similar routine exists in Turbo C 2.0.

### Restrictions

Must be in graphics mode.

### See also

*InitGraph, GetPalette, SetAllPalette, SetPalette*

### Example

```

uses
    Crt, Graph;
var
    Driver, Mode,
    i : integer;
    MyPal, OldPal : PaletteType;
begin
    DirectVideo := false;
    Randomize;
    Driver := Detect;                      { Put in graphics mode }
    InitGraph(Driver, Mode, '');
    if GraphResult < 0 then
        Halt(1);
    GetDefaultPalette(OldPal);              { Preserve old one }
    MyPal := OldPal;                       { Duplicate and modify }
    { Display something }
    for i := 0 to MyPal.Size - 1 do
        begin
            SetColor(i);
            OutTextXY(10, i * 10, '...Press any key...');
        end;
    repeat                                { Change palette until a key is pressed }
        with MyPal do
            Colors[Random(Size)] := Random(Size + 1);
            SetAllPalette(MyPal);
        until KeyPressed;
    SetAllPalette(OldPal);                  { Restore original palette }
    ClearDevice;
    OutTextXY(10, 10, 'Press <Return>...');
    Readln;
    Closegraph;
end.

```

---

## GetDir procedure

---

### Function

Returns the current directory of a specified drive.

### Declaration

GetDir(d: byte; **var** s: string)

### Remarks

*d* is an integer-type expression, and *s* is a string-type variable. The current directory of the drive specified by

*d* is returned in *s*. *d* = 0 indicates the current drive, 1 indicates drive *A*, 2 indicates drive *B*, and so on.

With *{I-}*, *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

See also

*ChDir*, *DiskFree*, *DiskSize*, *MkDir*, *Rmdir*

---

## GetDriverName function

## Graph

<b>Function</b>	Returns a string containing the name of the current driver.
<b>Declaration</b>	<code>GetDriverName</code>
<b>Result type</b>	string
<b>Remarks</b>	<p>After a call to <i>InitGraph</i>, returns the name of the active driver.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>GetModeName</i> , <i>InitGraph</i>
<b>Example</b>	<pre><b>uses</b>     Graph; <b>var</b>     Driver, Mode : integer; <b>begin</b>     Driver := Detect;                { Put in graphics mode }     InitGraph(Driver, Mode, '');     <b>if</b> GraphResult &lt; 0 <b>then</b>         Halt(1);     OutText('Using driver ' + GetDriverName);     Readln;     Closegraph; <b>end.</b></pre>

---

## GetEnv function

## Dos

<b>Function</b>	Returns the value of a specified environment variable.
<b>Declaration</b>	<code>GetEnv(EnvVar: <b>string</b>)</code>
<b>Result type</b>	string

**Remarks** *GetEnv* returns the value of a specified variable. The variable name can be in either uppercase or lowercase, but it must not include the equal sign (=) character. If the specified environment variable does not exist, *GetEnv* returns an empty string.

For more information about the DOS environment, refer to your DOS manuals.

**See also** *EnvCount*, *EnvStr*

**Example**

```
{ $M 8192,0,0 }
uses Dos;
var
    Command: string[79];
begin
    Write('Enter DOS command: ');
    Readln(Command);
    if Command <> '' then
        Command := '/C ' + Command;
    SwapVectors;
    Exec(GetEnv('COMSPEC'), Command);
    SwapVectors;
    if DosError <> 0 then
        Writeln('Could not execute COMMAND.COM');
end.
```

---

## GetFAttr procedure

## Dos

---

**Function** Returns the attributes of a file.

**Declaration** GetFAttr(**var** f; **var** Attr: word);

**Remarks** *F* must be a file variable (typed, untyped, or text file) that has been assigned but not opened. The attributes are examined by **anding** them with the file attribute masks defined as constants in the *Dos* unit:

```
const
    ReadOnly  = $01;
    Hidden    = $02;
    SysFile   = $04;
    VolumeID  = $08;
    Directory = $10;
    Archive   = $20;
    AnyFile   = $3F;
```

## GetFAttr procedure

Errors are reported in *DosError*; possible error codes are:

- 3 (Invalid Path)
- 5 (File Access Denied)

### Restrictions

*f* cannot be open.

### See also

*GetFTime, SetFAttr, SetFTime*

### Example

```
uses Dos;
var
  f: file;
  attr: word;

begin
  { Get file name from command line }
  Assign(f, ParamStr(1));
  GetFAttr(f, attr);
  Writeln(ParamStr(1));
  if DosError <> 0 then
    Writeln('Dos error code = ', DosError)
  else
    begin
      Write('Attribute = ', attr, 'to:'to);
      { Determine file attribute type
        using flags in Dos unit }
      if attr and ReadOnly <> 0 then
        Writeln('read only file');
      if attr and Hidden <> 0 then
        Writeln('hidden file');
      if attr and SysFile <> 0 then
        Writeln('system file');
      if attr and VolumeID <> 0 then
        Writeln('volume ID');
      if attr and Directory <> 0 then
        Writeln('directory name');
      if attr and Archive <> 0 then
        Writeln('archive (normal file)');
    end; { else }
end.
```

---

## GetFillPattern procedure

## Graph

---

<b>Function</b>	Returns the last fill pattern set by a previous call to <i>SetFillPattern</i> .
-----------------	---

<b>Declaration</b>	GetFillPattern( <b>var</b> FillPattern: FillPatternType);
--------------------	---

<b>Remarks</b>	<i>FillPatternType</i> is declared in the <i>Graph</i> unit:
----------------	--

## type

FillPatternType = **array**[1..8] of byte;

If no user call has been made to *SetFillPattern*, *GetFillPattern* will return an array filled with \$FF.

A similar routine exists in Turbo C 2.0.

## Restrictions

Must be in graphics mode.

## See also

*GetFillSettings*, *SetFillPattern*, *SetFillStyle*

---

## GetFillSettings procedure

## Graph

### Function

Returns the last fill pattern and color set by a previous call to *SetFillPattern* or *SetFillStyle*.

### Declaration

GetFillSettings(**var** FillInfo: FillSettingsType)

### Remarks

*GetFillSettings* returns a variable of type *FillSettingsType*. *FillSettingsType* is predeclared as follows:

## type

```
FillSettingsType = record
    Pattern: word;
    Color: word;
end;
```

The *Pattern* field reports the current fill pattern selected. The *Color* field reports the current fill color selected. Both the fill pattern and color can be changed by calling the *SetFillStyle* or *SetFillPattern* procedure. If *Pattern* is equal to *UserFill*, use *GetFillPattern* to get the user-defined fill pattern that is selected.

A similar routine exists in Turbo C 2.0.

## Restrictions

Must be in graphics mode.

## See also

*FillPoly*, *GetFillPattern*, *SetFillPattern*, *SetFillStyle*

## Example

```
uses Graph;
var
    Gd, Gm : integer;
    FillInfo: FillSettingsType;
begin
    Gd := Detect;
    InitGraph(Gd, Gm, '');
    if GraphResult <> grOk then
        Halt(1);
```



## GetFillSettings procedure

```
GetFillSettings(FillInfo);      { Save fill style and color }
Bar(0, 0, 50, 50);
SetFillStyle(XHatchFill, GetMaxColor);      { New style }
Bar(50, 0, 100, 50);
with FillInfo do
    SetFillStyle(Pattern, Color);      { Restore old fill style }
Bar(100, 0, 150, 50);
Readln;
CloseGraph;
end.
```

---

## GetFTime procedure

Dos

---

<b>Function</b>	Returns the date and time a file was last written.
<b>Declaration</b>	GetFTime( <b>var</b> f; <b>var</b> Time: longint);
<b>Remarks</b>	<i>f</i> must be a file variable (typed, untyped, or text file) that has been assigned and opened. The time returned in the <i>Time</i> parameter may be unpacked through a call to <i>UnpackTime</i> . Errors are reported in <i>DosError</i> ; the only possible error code is 6 (Invalid File Handle).
<b>Restrictions</b>	<i>f</i> must be open.
<b>See also</b>	<i>PackTime</i> , <i>SetFAttr</i> , <i>SetFTime</i> , <i>UnpackTime</i>

---

## GetGraphMode function

Graph

---

<b>Function</b>	Returns the current graphics mode.
<b>Declaration</b>	GetGraphMode
<b>Result type</b>	integer
<b>Remarks</b>	<i>GetGraphMode</i> returns the current graphics mode set by <i>InitGraph</i> or <i>SetGraphMode</i> . The <i>Mode</i> value is an integer from 0 to 5, depending on the current driver.

The following mode constants are defined:

Graphics Driver	Constant Name	Value	Column x Row	Palette	Pages
CGA	CGAC0	0	320x200	C0	1
	CGAC1	1	320x200	C1	1
	CGAC2	2	320x200	C2	1
	CGAC3	3	320x200	C3	1
	CGAHi	4	640x200	2 color	1
MCGA	MCGAC0	0	320x200	C0	1
	MCGAC1	1	320x200	C1	1
	MCGAC2	2	320x200	C2	1
	MCGAC3	3	320x200	C3	1
	MCGAMed	4	640x200	2 color	1
	MCGAHi	5	640x480	2 color	1
EGA	EGALo	0	640x200	16 color	4
	EGAHi	1	640x350	16 color	2
EGA64	EGA64Lo	0	640x200	16 color	1
	EGA64Hi	1	640x350	4 color	1
EGA-MONO	EGAMonoHi	3	640x350	2 color	1*
	EGAMonoHi	3	640x350	2 color	2**
HERC	HercMonoHi	0	720x348	2 color	2
ATT400	ATT400C0	0	320x200	C0	1
	ATT400C1	1	320x200	C1	1
	ATT400C2	2	320x200	C2	1
	ATT400C3	3	320x200	C3	1
	ATT400Med	4	640x200	2 color	1
	ATT400Hi	5	640x400	2 color	1
VGA	VGALo	0	640x200	16 color	2
	VGAMed	1	640x350	16 color	2
	VGAHi	2	640x480	16 color	1
PC3270	PC3270Hi	0	720x350	2 color	1
8514	IBM8514Lo	0	640x480	256 color	1
8514	IBM8514Hi	0	1024x768	256 color	1

\* 64K on EGAMono card

\*\* 256K on EGAMono card

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

## GetGraphMode function

**See also** *ClearDevice, DetectGraph, InitGraph, RestoreCrtMode, SetGraphMode*

**Example**

```
uses Graph;  
var  
    Gd, Gm: integer;  
    Mode : integer;  
begin  
    Gd := Detect;  
    InitGraph(Gd, Gm, '');  
    if GraphResult <> grOk then  
        Halt(1);  
    OutText('<ENTER> to leave graphics:');  
    Readln;  
    RestoreCrtMode;  
    Writeln('Now in text mode');  
    Write('<ENTER> to enter graphics mode:');  
    Readln;  
    SetGraphMode(GetGraphMode);  
    OutTextXY(0, 0, 'Back in graphics mode');  
    OutTextXY(0, TextHeight('H'), '<ENTER> to quit:');  
    Readln;  
    CloseGraph;  
end.
```

---

## GetImage procedure

## Graph

---

<b>Function</b>	Saves a bit image of the specified region into a buffer.
<b>Declaration</b>	<code>GetImage(x1, y1, x2, y2: integer; <b>var</b> BitMap);</code>
<b>Remarks</b>	<p><i>x1, y1, x2, and y2</i> define a rectangular region on the screen. <i>BitMap</i> is an untyped parameter that must be greater than or equal to 6 plus the amount of area defined by the region. The first two words of <i>BitMap</i> store the width and height of the region. The third word is reserved.</p> <p>The remaining part of <i>BitMap</i> is used to save the bit image itself. Use the <i>ImageSize</i> function to determine the size requirements of <i>BitMap</i>.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode. The memory required to save the region must be less than 64K.
<b>See also</b>	<i>ImageSize, PutImage</i>

## Example

```

uses Graph;
var
  Gd, Gm : integer;
  P      : pointer;
  Size   : word;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  Bar(0, 0, GetMaxX, GetMaxY);
  Size := ImageSize(10,20,30,40);
  GetMem(P, Size);           { Allocate memory on heap }
  GetImage(10,20,30,40,P^);
  Readln;
  ClearDevice;
  PutImage(100, 100, P^, NormalPut);
  Readln;
  CloseGraph;
end.

```

---

## GetIntVec procedure

Dos

<b>Function</b>	Returns the address stored in a specified interrupt vector.
<b>Declaration</b>	GetIntVec(IntNo: byte; <b>var</b> Vector: pointer)
<b>Remarks</b>	<i>IntNo</i> specifies the interrupt vector number (0..255), and the address is returned in <i>Vector</i> .
<b>See also</b>	<i>SetIntVec</i>

---

## GetLineSettings procedure

Graph

<b>Function</b>	Returns the current line style, line pattern, and line thickness as set by <i>SetLineStyle</i> .
<b>Declaration</b>	GetLineSettings( <b>var</b> LineInfo: LineSettingsType)
<b>Remarks</b>	The following type and constants are defined: <b>type</b> LineSettingsType = <b>record</b> LineStyle: word; Pattern: word;

## GetLineSettings procedure

```
        Thickness: word;
    end;

const
    { Line styles }
    SolidLn    = 0;
    DottedLn   = 1;
    CenterLn   = 2;
    DashedLn   = 3;
    UserBitLn  = 4;                { User-defined line style }

    { Line widths }
    NormWidth  = 1;
    ThickWidth = 3;
```

A similar routine exists in Turbo C 2.0.

**Restrictions**      Must be in graphics mode.

**See also**          *DrawPoly, SetLineStyle*

**Example**

```
uses Graph;
var
    Gd, Gm : integer;
    OldStyle: LineSettingsType;
begin
    Gd := Detect;
    InitGraph(Gd, Gm, '');
    if GraphResult <> grOk then
        Halt(1);
    Line(0, 0, 100, 0);
    GetLineSettings(OldStyle);
    SetLineStyle(DottedLn, 0, ThickWidth);      { New style }
    Line(0, 10, 100, 10);
    with OldStyle do                            { Restore old line style }
        SetLineStyle(LineStyle, Pattern, Thickness);
    Line(0, 20, 100, 20);
    Readln;
    CloseGraph;
end.
```

---

## GetMaxColor function

## Graph

**Function**      Returns the highest color that can be passed to the *SetColor* procedure.

**Declaration**    `GetMaxColor`

**Result type**    `word`

<b>Remarks</b>	As an example, on a 256K EGA, <i>GetMaxColor</i> will always return 15, which means that any call to <i>SetColor</i> with a value from 0..15 is valid. On a CGA in high-resolution mode or on a Hercules monochrome adapter, <i>GetMaxColor</i> returns a value of 1 because these adapters only support draw colors of 0 or 1.  A similar routine exists in Turbo C 2.0.
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>SetColor</i>

---

## GetMaxMode function

## Graph

<b>Function</b>	Returns the maximum mode number for the currently loaded driver.
<b>Declaration</b>	<i>GetMaxMode</i>
<b>Result type</b>	word
<b>Remarks</b>	<p><i>GetMaxMode</i> lets you find out the maximum mode number for the current driver, directly from the driver. (Formerly, <i>GetModeRange</i> was the only way you could get this number; <i>GetModeRange</i> is still supported, but only for the Borland drivers.)</p> <p>The value returned by <i>GetMaxMode</i> is the maximum value that may be passed to <i>SetGraphMode</i>. Every driver supports modes 0..<i>GetMaxMode</i>.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>GetModeRange</i> , <i>SetGraphMode</i>
<b>Example</b>	<pre> <b>uses</b>     Graph; <b>var</b>     Driver, Mode : integer;     i : integer; <b>begin</b>     Driver := Detect;                                { Put in graphics mode }     InitGraph(Driver, Mode, '');     <b>if</b> GraphResult &lt; 0 <b>then</b>         Halt(1);     <b>for</b> i := 0 <b>to</b> GetMaxMode <b>do</b>                    { Display all mode names }         </pre>

## GetMaxMode function

```
      OutTextXY(10, 10 * Succ(i), GetModeName(i));  
      Readln;  
      Closegraph;  
end.
```

---

## GetMaxX function

## Graph

<b>Function</b>	Returns the rightmost column ( <i>x</i> resolution) of the current graphics driver and mode.
<b>Declaration</b>	GetMaxX
<b>Result type</b>	integer
<b>Remarks</b>	<p>Returns the maximum <i>x</i> value for the current graphics driver and mode. On a CGA in 320×200 mode; for example, <i>GetMaxX</i> will return 319.</p> <p><i>GetMaxX</i> and <i>GetMaxY</i> are invaluable for centering, determining the boundaries of a region on the screen, and so on.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>GetMaxY</i> , <i>GetX</i> , <i>GetY</i> , <i>MoveTo</i>
<b>Example</b>	<pre>uses Graph; var   Gd, Gm: integer; begin   Gd := Detect;   InitGraph(Gd, Gm, '');   if GraphResult &lt;&gt; grOk then     Halt(1);   Rectangle(0,0,GetMaxX,GetMaxY); { Draw a full-screen box }   Readln;   CloseGraph; end.</pre>

---

## GetMaxY function

## Graph

<b>Function</b>	Returns the bottommost row ( <i>y</i> resolution) of the current graphics driver and mode.
<b>Declaration</b>	GetMaxY
<b>Result type</b>	integer
<b>Remarks</b>	<p>Returns the maximum <i>y</i> value for the current graphics driver and mode. On a CGA in 320×200 mode; for example, <i>GetMaxY</i> will return 199.</p> <p><i>GetMaxX</i> and <i>GetMaxY</i> are invaluable for centering, determining the boundaries of a region on the screen, and so on.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>GetMaxX</i> , <i>GetX</i> , <i>GetY</i> , <i>MoveTo</i>
<b>Example</b>	<pre> <b>uses</b> Graph; <b>var</b>     Gd, Gm: integer; <b>begin</b>     Gd := Detect;     InitGraph(Gd, Gm, '');     <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>         Halt(1);     Rectangle(0,0,GetMaxX,GetMaxY);    { Draw a full-screen box }     Readln;     CloseGraph; <b>end.</b> </pre>

---

## GetMem procedure

<b>Function</b>	Creates a new dynamic variable of the specified size, and puts the address of the block in a pointer variable.
<b>Declaration</b>	GetMem( <b>var</b> p: pointer; size: word)
<b>Remarks</b>	<i>p</i> is a pointer variable of any pointer type. <i>Size</i> is an expression of type word specifying the size in bytes of the dynamic variable to allocate. The newly created variable can be referenced as <i>p</i> <sup>^</sup> .



## GetMem procedure

If there isn't enough free space in the heap to allocate the new variable, a run-time error occurs. (It is possible to avoid a run-time error; see "The Heap Error Function" on page 187.)

**Restrictions** The largest block that can be allocated on the heap at one time is 65521 bytes (64Kb-\$F). If the heap is not fragmented, for example at the beginning of a program, successive calls to *GetMem* will return neighboring blocks of memory.

**Differences** In 3.0, *size* was an integer.

**See also** *Dispose, FreeMem, Mark, New, Release*

---

## GetModeName function

## Graph

**Function** Returns a string containing the name of the specified graphics mode.

**Declaration** `GetModeName (ModeNumber : integer)`

**Result type** string

**Remarks** The mode names are embedded in each driver. The return values (320 x 200 CGA P1, 640 x 200 CGA, etc.) are useful for building menus, display status, etc.

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *GetDriverName, GetMaxMode, GetModeRange*

**Example**

```
uses
    Graph;
var
    Driver, Mode : integer;
    i : integer;
begin
    Driver := Detect;                { Put in graphics mode }
    InitGraph(Driver, Mode, '');
    if GraphResult < 0 then
        Halt(1);
    for i := 0 to GetMaxMode do      { Display all mode names }
        OutTextXY(10, 10 * Succ(i), GetModeName(i));
    Readln;
    Closegraph;
end.
```

---

## GetModeRange procedure

## Graph

---

<b>Function</b>	Returns the lowest and highest valid graphics mode for a given driver.
<b>Declaration</b>	<pre>GetModeRange(GraphDriver : integer;               var LoMode, HiMode: integer);</pre>
<b>Remarks</b>	<p>The output from the following program:</p> <pre>uses Graph; var   Lowest, Highest : integer; begin   GetModeRange(EGA64, Lowest, Highest);   Write('Lowest = ', Lowest);   Write(' Highest = ', Highest); end.</pre> <p>will be <i>Lowest</i> = 0 and <i>Highest</i> = 1.</p> <p>If the value of <i>GraphDriver</i> is invalid, the return parameters are set to -1.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>See also</b>	<i>GetGraphMode, SetGraphMode, InitGraph, DetectGraph</i>

---

## GetPalette procedure

## Graph

---

<b>Function</b>	Returns the current palette and its size.
<b>Declaration</b>	<pre>GetPalette(var Palette: PaletteType)</pre>
<b>Remarks</b>	<p>Returns the current palette and its size in a variable of type <i>PaletteType</i>. <i>PaletteType</i> is defined as follows:</p> <pre>const   MaxColors = 15; type   PaletteType = record     Size: byte;     Colors: array[0..MaxColors] of shortint;   end;</pre> <p>The size field reports the number of colors in the palette for the current driver in the current mode. <i>Colors</i> contains the actual colors 0..<i>Size</i>-1.</p>

## GetPalette procedure

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode, and can only be used with EGA, EGA 64, or VGA (not the IBM 8514 or the VGA in 256-color mode).

**See also** *GetDefaultPalette, GetPaletteSize, SetAllPalette, SetPalette*

**Example**

```
uses Graph;
var
  Gd, Gm : integer;
  Color : word;
  Palette: PaletteType;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  GetPalette(Palette);
  if Palette.Size <> 1 then
    for Color := 0 to Pred(Palette.Size) do
      begin
        SetColor(Color);
        Line(0, Color*5, 100, Color*5);
      end
    else
      Line(0, 0, 100, 0);
  Readln;
  CloseGraph;
end.
```

---

## GetPaletteSize function

## Graph

---

**Function** Returns the the size of the palette color lookup table.

**Declaration** GetPaletteSize

**Result type** integer

**Remarks** *GetPaletteSize* reports how many palette entries can be set for the current graphics mode; for example, the EGA in color mode will return a value of 16.

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *GetMaxColor, GetDefaultPalette, GetPalette, SetPalette*

---

## GetPixel function

## Graph

---

<b>Function</b>	Gets the pixel value at X,Y.
<b>Declaration</b>	GetPixel(X,Y: integer)
<b>Result type</b>	word
<b>Remarks</b>	Gets the pixel color at (X,Y). A similar routine exists in Turbo C 2.0.
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>PutPixel, GetImage, PutImage, SetWriteMode</i>
<b>Example</b>	

```

uses Graph;
var
    Gd, Gm    : integer;
    PixelColor: word;
begin
    Gd := Detect;
    InitGraph(Gd, Gm, '');
    if GraphResult <> grOk then
        Halt(1);
    PixelColor := GetPixel(10,10);
    if PixelColor = 0 then
        PutPixel(10, 10, GetMaxColor);
    Readln;
    CloseGraph;
end.

```

---

## GetTextSettings procedure

## Graph

---

<b>Function</b>	Returns the current text font, direction, size, and justification as set by <i>SetTextStyle</i> and <i>SetTextJustify</i> .
<b>Declaration</b>	GetTextSettings( <b>var</b> TextInfo: TextSettingsType)
<b>Remarks</b>	The following type and constants are defined:

```

type
    TextSettingsType = record
        Font: word;
        Direction: word;
        CharSize: word;
        Horiz: word;
        Vert: word;
    end;

```

## GetTextSettings procedure

```
const
  DefaultFont  = 0;                { 8x8 bit mapped font }
  TriplexFont  = 1;                { "Stroked" fonts }
  SmallFont    = 2;
  SansSerifFont = 3;
  GothicFont   = 4;
  HorizDir     = 0;                { Left to right }
  VertDir      = 1;                { Bottom to top }
```

A similar routine exists in Turbo C 2.0.

**Restrictions**      Must be in graphics mode.

**See also**          *InitGraph, SetTextJustify, SetTextStyle, TextHeight, TextWidth*

**Example**

```
uses Graph;
var
  Gd, Gm : integer;
  OldStyle: TextSettingsType;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  GetTextSettings(OldStyle);
  OutTextXY(0, 0, 'Old text style');
  SetTextJustify(LeftText, CenterText);
  SetTextStyle(TriplexFont, VertDir, 4);
  OutTextXY(GetMaxX div 2, GetMaxY div 2, 'New Style');
  with OldStyle do
    begin
      { Restore old text style }
      SetTextJustify(Horiz, Vert);
      SetTextStyle(Font, Direction, CharSize);
    end;
  OutTextXY(0, TextHeight('H'), 'Old style again');
  Readln;
  CloseGraph;
end.
```

---

## GetTime procedure

Dos

---

<b>Function</b>	Returns the current time set in the operating system.
<b>Declaration</b>	GetTime( <b>var</b> Hour, Minute, Second, Sec100: word)
<b>Remarks</b>	Ranges of the values returned are <i>Hour</i> 0..23, <i>Minute</i> 0..59, <i>Second</i> 0..59, and <i>Sec100</i> (hundredths of seconds) 0..99.
<b>See also</b>	<i>GetDate, SetDate, SetTime, UnpackTime</i>

---



---

## GetVerify procedure

Dos

---

<b>Function</b>	Returns the state of the verify flag in DOS.
<b>Declaration</b>	GetVerify( <b>var</b> Verify: boolean)
<b>Remarks</b>	<i>GetVerify</i> returns the state of the verify flag in DOS. When off (False), disk writes are not verified. When on (True), all disk writes are verified to ensure proper writing.
<b>See also</b>	<i>SetVerify</i>

---



---

## GetViewSettings procedure

Graph

---

<b>Function</b>	Returns the current viewport and clipping parameters, as set by <i>SetViewport</i> .
<b>Declaration</b>	GetViewSettings( <b>var</b> ViewPort: ViewPortType)
<b>Remarks</b>	<i>GetViewSettings</i> returns a variable of type <i>ViewPortType</i> . <i>ViewPortType</i> is predeclared as follows:

---

```

type
  ViewPortType = record
    x1, y1, x2, y2: integer;
    Clip: boolean;
  end;

```

The points (*x1*, *y1*) and (*x2*, *y2*) are the dimensions of the active viewport and are given in absolute screen coordinates. *Clip* is a Boolean variable that controls whether clipping is active.

## GetViewSettings procedure

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *ClearViewPort, SetViewPort*

**Example**

```
uses Graph;
var
  Gd, Gm : integer;
  ViewPort: ViewPortType;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  GetViewSettings(ViewPort);
  with ViewPort do
    begin
      Rectangle(0, 0, x2-x1, y2-y1);
      if Clip then
        OutText('Clipping is active.')
      else
        OutText('No clipping today.');
```

**end;**  
Readln;  
CloseGraph;  
**end.**

---

## GetX function

## Graph

---

**Function** Returns the X coordinate of the current position (CP).

**Declaration** GetX

**Result type** integer

**Remarks** *GetX* is viewport-relative. In the following example:

```
1  SetViewPort(0,0,GetMaxX,GetMaxY,True);
2  MoveTo(5,5);
3  SetViewPort(10,10,100,100,True);
4  MoveTo(5,5);
```

■ Line 1 moves CP to absolute (0,0), and *GetX* would also return a value of 0.

■ Line 2 moves CP to absolute (5,5), and *GetX* would also return a value of 5.

- Line 3 moves CP to absolute (10,10), but *GetX* would return a value of 0.
- Line 4 moves CP to absolute (15,15), but *GetX* would return a value of 5.

A similar routine exists in Turbo C 2.0.

## Restrictions

Must be in graphics mode.

## See also

*GetViewSettings*, *GetY*, *InitGraph*, *MoveTo*, *SetViewPort*

## Example

```
uses Graph;
var
  Gd, Gm: integer;
  X, Y: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  OutText('Starting here. ');
  X := GetX;
  Y := GetY;
  OutTextXY(20, 10, 'Now over here...');
  OutTextXY(X, Y, 'Now back over here. ');
  Readln;
  CloseGraph;
end.
```

---

# GetY function

# Graph

<b>Function</b>	Returns the Y coordinate of the current position (CP).
<b>Declaration</b>	<i>GetY</i>
<b>Result type</b>	integer
<b>Remarks</b>	<p><i>GetY</i> is viewport-relative. In the following example:</p> <pre> 1  SetViewPort(0,0,GetMaxX,GetMaxY,True); 2  MoveTo(5,5); 3  SetViewPort(10,10,100,100,True); 4  MoveTo(5,5); </pre> <ul style="list-style-type: none"> <li>■ Line 1 moves CP to absolute (0,0), and <i>GetY</i> would also return a value of 0.</li> <li>■ Line 2 moves CP to absolute (5,5), and <i>GetY</i> would also return a value of 5.</li> </ul>



## GetY function

- Line 3 moves CP to absolute (10,10), but *GetY* would return a value of 0.
- Line 4 moves CP to absolute (15,15), but *GetY* would return a value of 5.

A similar routine exists in Turbo C 2.0.

### Restrictions

Must be in graphics mode.

### See also

*GetViewSettings, GetX, InitGraph, MoveTo, SetViewPort*

### Example

```
uses Graph;
var
  Gd, Gm: integer;
  X, Y: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  OutText('Starting here. ');
  X := GetX;
  Y := GetY;
  OutTextXY(20, 10, 'Now over here...');
  OutTextXY(X, Y, 'Now back over here. ');
  Readln;
  CloseGraph;
end.
```

---

## GotoXY procedure

Crt

### Function

Positions the cursor.

### Declaration

*GotoXY*(X, Y: byte)

### Remarks

The cursor is moved to the position within the current window specified by X and Y (X is the column, Y is the row). The upper left corner is (1,1).

This procedure is window-relative:

```
Window(1,10,60,20);
GotoXY(1,1);
```

and will move the cursor to the upper left corner of the active window (absolute coordinates (1,10)).

### Restrictions

If the coordinates are in any way invalid, the call to *GotoXY* is ignored.

See also *Window, WhereX, WhereY*

---

## GraphDefaults procedure

---

## Graph

<b>Function</b>	Resets the graphics settings.
<b>Declaration</b>	<code>GraphDefaults</code>
<b>Remarks</b>	<p>Homes the current pointer (CP) and resets the graphics system to the default values for</p> <ul style="list-style-type: none"> <li>■ viewport</li> <li>■ palette</li> <li>■ draw and background colors</li> <li>■ line style and line pattern</li> <li>■ fill style, fill color, and fill pattern</li> <li>■ active font, text style, text justification, and user char size</li> </ul> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>InitGraph</i>

---

## GraphErrorMsg function

---

## Graph

<b>Function</b>	Returns an error message string for the specified <i>ErrorCode</i> .
<b>Declaration</b>	<code>GraphErrorMsg(ErrorCode: integer)</code>
<b>Result type</b>	string
<b>Remarks</b>	<p>This function returns a string containing an error message that corresponds with the error codes in the graphics system. This makes it easy for a user program to display a descriptive error message ("Device driver not found" instead of "error code -3").</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>See also</b>	<i>DetectGraph, GraphResult, InitGraph</i>
<b>Example</b>	<pre>uses Graph; var     GraphDriver, GraphMode: integer;</pre>

## GraphErrorMsg function

```
    ErrorCode: integer;  
begin  
    GraphDriver := Detect;  
    InitGraph(GraphDriver, GraphMode, '');  
    ErrorCode := GraphResult;  
    if ErrorCode <> grOk then  
        begin  
            Writeln('Graphics error: ', GraphErrorMsg(ErrorCode));  
            Readln;  
            Halt(1);  
        end;  
    Line(0, 0, GetMaxX, GetMaxY);  
    Readln;  
    CloseGraph;  
end.
```

---

## GraphResult function

## Graph

---

<b>Function</b>	Returns an error code for the last graphics operation.
<b>Declaration</b>	GraphResult
<b>Result type</b>	integer
<b>Remarks</b>	Returns an error code for the last graphics operation. The following error return codes are defined:

Error Code	Graphics Error Constant	Corresponding Error Message String
0	grOk	No error
-1	grNoInitGraph	(BGI) graphics not installed (use <i>InitGraph</i> )
-2	grNotDetected	Graphics hardware not detected
-3	grFileNotFound	Device driver file not found
-4	grInvalidDriver	Invalid device driver file
-5	grNoLoadMem	Not enough memory to load driver
-6	grNoScanMem	Out of memory in scan fill
-7	grNoFloodMem	Out of memory in flood fill
-8	grFontNotFound	Font file not found
-9	grNoFontMem	Not enough memory to load font
-10	grInvalidMode	Invalid graphics mode for selected driver
-11	grError	Graphics error
-12	grIOerror	Graphics I/O error
-13	grInvalidFont	Invalid font file
-14	grInvalidFontNum	Invalid font number

The following routines set *GraphResult*:

<i>Bar</i>	<i>ImageSize</i>	<i>SetFillPattern</i>
<i>Bar3D</i>	<i>InitGraph</i>	<i>SetFillStyle</i>
<i>ClearViewPort</i>	<i>InstallUserDriver</i>	<i>SetGraphBufSize</i>
<i>CloseGraph</i>	<i>InstallUserFont</i>	<i>SetGraphMode</i>
<i>DetectGraph</i>	<i>PieSlice</i>	<i>SetLineStyle</i>
<i>DrawPoly</i>	<i>RegisterBGIDriver</i>	<i>SetPalette</i>
<i>FillPoly</i>	<i>RegisterBGIfont</i>	<i>SetTextJustify</i>
<i>FloodFill</i>	<i>SetAllPalette</i>	<i>SetTextStyle</i>
<i>GetGraphMode</i>		

Note that *GraphResult* is reset to zero after it has been called (similar to *IOResult*). Therefore, the user should store the value of *GraphResult* into a temporary variable and then test it.

A string function, *GraphErrorMsg*, is provided to return a string that corresponds with each error code.

A similar routine exists in Turbo C 2.0.

See also

*GraphErrorMsg*

## GraphResult function

### Example

```
uses Graph;
var
  ErrorCode: integer;
  GrDriver, GrMode: integer;
begin
  GrDriver := Detect;
  InitGraph(GrDriver, GrMode, '');
  ErrorCode := GraphResult;           { Check for errors }
  if ErrorCode <> grOk then
  begin
    Writeln('Graphics error:');
    Writeln(GraphErrorMsg(ErrorCode));
    Writeln('Program aborted...');
    Halt(1);
  end;

  { Do some graphics... }
  ClearDevice;
  Rectangle(0, 0, GetMaxX, GetMaxY);
  Readln;
  CloseGraph;
end.
```

---

## Halt procedure

---

<b>Function</b>	Stops program execution and returns to the operating system.
<b>Declaration</b>	<code>Halt [ ( exitcode: word ) ]</code>
<b>Remarks</b>	<p><i>exitcode</i> is an optional expression of type <i>word</i> that specifies the exit code of the program. <i>Halt</i> without a parameter corresponds to <i>Halt(0)</i>. The exit code can be examined by a parent process using the <i>DosExitCode</i> function in the <i>Dos</i> unit or through an <i>ERRORLEVEL</i> test in a DOS batch file.</p> <p>Note that <i>Halt</i> will initiate execution of any unit <i>Exit</i> procedures (see Chapter 15).</p>
<b>See also</b>	<i>Exit, RunError</i>

---

## Hi function

---

<b>Function</b>	Returns the high-order byte of the argument.
<b>Declaration</b>	<code>Hi(x)</code>
<b>Result type</b>	byte
<b>Remarks</b>	<i>x</i> is an expression of type integer or word. <i>Hi</i> returns the high-order byte of <i>x</i> as an unsigned value.
<b>See also</b>	<i>Lo</i> , <i>Swap</i>
<b>Example</b>	<pre> var w: word; begin   w := Hi(\$1234);  { \$12 } end.</pre>

---

## HighVideo procedure

---

**Crt**

<b>Function</b>	Selects high-intensity characters.
<b>Declaration</b>	<code>HighVideo</code>
<b>Remarks</b>	There is a byte variable in <i>Crt</i> — <i>TextAttr</i> —that is used to hold the current video attribute. <i>HighVideo</i> sets the high intensity bit of <i>TextAttr</i> 's foreground color, thus mapping colors 0-7 onto colors 8-15.
<b>Differences</b>	In 3.0, <i>HighVideo</i> always selected yellow on black (white on black in mono and BW80 video modes).
<b>See also</b>	<i>LowVideo</i> , <i>NormVideo</i> , <i>TextBackground</i> , <i>TextColor</i>
<b>Example</b>	<pre> uses Crt; begin   TextAttr := LightGray;   HighVideo;                      { Color is now white } end.</pre>

# ImageSize function

# Graph

**Function** Returns the number of bytes required to store a rectangular region of the screen.

**Declaration** `ImageSize(x1, y1, x2, y2: integer)`

**Result type** word

**Remarks** *x1, y1, x2, and y2* define a rectangular region on the screen. *ImageSize* determines the number of bytes necessary for *GetImage* to save the specified region of the screen. The image size includes space for three words. The first stores the width of the region, the second stores the height, and the third is reserved.

If the memory required to save the region is greater than or equal to 64K, a value of 0 is returned and *GraphResult* will return -11 (*grError*).

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *GetImage, PutImage*

**Example**

```

uses Graph;
var
    Gd, Gm: integer;
    P: pointer;
    Size: word;
begin
    Gd := Detect;
    InitGraph(Gd, Gm, '');
    if GraphResult <> grOk then
        Halt(1);
    Bar(0, 0, GetMaxX, GetMaxY);
    Size := ImageSize(10,20,30,40);
    GetMem(P, Size); { Allocate memory on heap }
    GetImage(10,20,30,40,P^);
    Readln;
    ClearDevice;
    PutImage(100, 100, P^, NormalPut);
    Readln;
    CloseGraph;
end.

```

---

## Inc procedure

---

<b>Function</b>	Increments a variable.
<b>Declaration</b>	<code>Inc(var x [ ; n: longint ] )</code>
<b>Remarks</b>	<p><math>x</math> is an ordinal-type variable, and <math>n</math> is an integer-type expression. <math>x</math> is incremented by 1, or by <math>n</math> if <math>n</math> is specified; that is, <math>Inc(x)</math> corresponds to <math>x := x+1</math>, and <math>Inc(x,n)</math> corresponds to <math>x := x+n</math>.</p> <p><i>Inc</i> generates optimized code and is especially useful for use in tight loops.</p>
<b>See also</b>	<i>Dec, Pred, Succ</i>
<b>Example</b>	<pre> var   IntVar: integer;   LongintVar: longint; begin   Inc(IntVar);   Inc(LongintVar, 5); end. { IntVar := IntVar + 1 } { LongintVar := LongintVar + 5 }</pre>

---

## InitGraph procedure

---

## Graph

<b>Function</b>	Initializes the graphics system and puts the hardware into graphics mode.
<b>Declaration</b>	<pre> InitGraph(var GraphDriver: integer;           var GraphMode: integer; PathToDriver: string)</pre>
<b>Remarks</b>	<p>Both <i>GraphDriver</i> and <i>GraphMode</i> are <b>var</b> parameters.</p> <p>If <i>GraphDriver</i> is equal to <i>Detect</i> (0), a call is made to any user-defined autodetect routines (see <i>InstallUserDriver</i>) and then <i>DetectGraph</i>. If graphics hardware is detected, the appropriate graphics driver is initialized, and a graphics mode is selected.</p> <p>If <i>GraphDriver</i> is not equal to 0, the value of <i>GraphDriver</i> is assumed to be a driver number; that driver is selected, and the system is put into the mode specified by <i>GraphMode</i>. If you override autodetection in this manner, you must supply a valid <i>GraphMode</i> parameter for the driver requested.</p>



*PathToDriver* specifies the directory path where the graphics drivers can be found. If *PathToDriver* is null, the driver files must be in the current directory.

Normally, *InitGraph* loads a graphics driver by allocating memory for the driver (through *GraphGetMem*), then loads the appropriate .BGI file from disk. As an alternative to this dynamic loading scheme, you can link a graphics driver file (or several of them) directly into your executable program file. You do this by first converting the .BGI file to an .OBJ file (using the BINOBJ utility), then placing calls to *RegisterBGIDriver* in your source code (before the call to *InitGraph*) to register the graphics driver(s). When you build your program, you must link the .OBJ files for the registered drivers. You can also load a BGI driver onto the heap and then register it using *RegisterBGIDriver*.

If memory for the graphics driver is allocated on the heap using *GraphGetMem*, that memory is released when a call is made to *CloseGraph*.

After calling *InitGraph*, *GraphDriver* will be set to the current graphics driver, and *GraphMode* will be set to the current graphics mode.

If an error occurred, both *GraphDriver* and *GraphResult* (a function) will return one of the following values:

- 2     Cannot detect a graphics card
- 3     Cannot find driver file
- 4     Invalid driver
- 5     Insufficient memory to load driver
- 10    Invalid graphics mode for selected driver

*InitGraph* resets all graphics settings to their defaults (current pointer, palette, color, viewport, etc.).

You can use *InstallDriver* to install a vendor-supplied graphics driver (see *InstallUserDriver* for more information).

Several useful constants are defined for each graphics driver supported:

Error Code	Graphics Error Constant	Corresponding Error Message String
0	grOk	No error
-1	grNoInitGraph	(BGI) graphics not installed (use <i>InitGraph</i> )
-2	grNotDetected	Graphics hardware not detected
-3	grFileNotFound	Device driver file not found
-4	grInvalidDriver	Invalid device driver file
-5	grNoLoadMem	Not enough memory to load driver
-6	grNoScanMem	Out of memory in scan fill
-7	grNoFloodMem	Out of memory in flood fill
-8	grFontNotFound	Font file not found
-9	grNoFontMem	Not enough memory to load font
-10	grInvalidMode	Invalid graphics mode for selected driver
-11	grError	Graphics error
-12	grIOerror	Graphics I/O error
-13	grInvalidFont	Invalid font file
-14	grInvalidFontNum	Invalid font number

A similar routine exists in Turbo C 2.0.

## Restrictions

Must be in graphics mode. If you use the Borland Graphics Interface (BGI) on a Zenith Z-449 card, Turbo Pascal's autodetection code will always select the 640x480 enhanced EGA mode. If this mode isn't compatible with your monitor, select a different mode in the *InitGraph* call. Also, Turbo Pascal cannot autodetect the IBM 8514 graphics card (the autodetection logic recognizes it as VGA). Therefore, to use the IBM 8514 card, the *GraphDriver* variable must be assigned the value *IBM8514* (which is defined in the *Graph* unit) when *InitGraph* is called. You should not use *DetectGraph* (or *Detect* with *InitGraph*) with the IBM 8514 unless you want the emulated VGA mode.

## See also

*CloseGraph*, *DetectGraph*, *InstallUserDriver*, *RestoreCrtMode*, *SetGraphMode*, *GraphResult*, *SetGraphBufSize*, *RegisterBGIdriver*, *RegisterBGIfont*, *GraphDefaults*

## Example

```
uses Graph;
var
```

## InitGraph procedure

```
grDriver: integer;
grMode : integer;
ErrCode : integer;
begin
  grDriver := Detect;
  InitGraph(grDriver,grMode,'');
  ErrCode := GraphResult;
  if ErrCode = grOk then
    begin { Do graphics }
      Line(0, 0, GetMaxX, GetMaxY);
      Readln;
      CloseGraph;
    end
  else
    Writeln('Graphics error:', GraphErrorMsg(ErrCode));
  end.
```

---

## Insert procedure

---

Function	Inserts a substring into a string.
Declaration	Insert(source: <b>string</b> ; var s: <b>string</b> ; index: integer)
Remarks	<i>source</i> is a string-type expression. <i>s</i> is a string-type variable of any length. <i>index</i> is an integer-type expression. <i>Insert</i> inserts <i>source</i> into <i>s</i> at the <i>index</i> th position. If the resulting string is longer than 255 characters, it is truncated after the 255th character.
See also	<i>Delete, Copy, Concat, Length, Pos</i>
Example	<pre>var   s: string; begin   s := 'Honest Lincoln';   Insert('Abe ', s, 8);           { 'Honest Abe Lincoln' } end.</pre>

---

## InsLine procedure

---

**Crt**

Function	Inserts an empty line at the cursor position.
Declaration	InsLine

<b>Remarks</b>	<p>All lines below the inserted line are moved down one line, and the bottom line scrolls off the screen (using the BIOS scroll routine).</p> <p>All character positions are set to blanks with the currently defined text attributes. Thus, if <i>TextBackground</i> is not black, the new line becomes the background color.</p> <p>This procedure is window-relative:</p> <pre>Window(1,10,60,20); InsLine;</pre> <p>and will insert a line 60 columns wide at absolute coordinates (1,10).</p>
<b>See also</b>	<i>DelLine, Window</i>

## InstallUserDriver function

## Graph

<b>Function</b>	Installs a vendor-added device driver to the BGI device driver table.
<b>Declaration</b>	<pre>InstallUserDriver(Name : string;                   AutoDetectPtr : pointer)</pre>
<b>Result type</b>	integer
<b>Remarks</b>	<p><i>InstallUserDriver</i> allows you to use a vendor-added device driver. The <i>Name</i> parameter is the file name of the new device driver. <i>AutoDetectPtr</i> is a pointer to an optional autodetect function that may accompany the new driver. This autodetect function takes no parameters and returns an integer value.</p> <p>If the internal driver table is full, <i>InstallUserDriver</i> returns a value of -11 (<i>grError</i>); otherwise <i>InstallUserDriver</i> assigns and returns a driver number for the new device driver.</p> <p>There are two ways to use this vendor-supplied driver. Let's assume you have a new video card called the Spiffy Graphics Array (SGA) and that the SGA manufacturer provided you with a BGI device driver (SGA.BGI). The easiest way to use this driver is to install it by calling <i>InstallUserDriver</i> and then passing the return value (the assigned driver number) directly to <i>InitGraph</i>:</p>

## InstallUserDriver function

```
var
  Driver, Mode : integer;
begin
  Driver := InstallUserDriver('SGA', Nil);
  if Driver = grError then                                { Table full? }
    Halt(1);
  Mode := 0;                                               { Every driver supports mode of 0 }
  InitGraph(Driver, Mode, '');                             { Override autodetection }
  ...                                                       { Do graphics ... }
end.
```

The *nil* value for the *AutoDetectPtr* parameter in the *InstallUserDriver* call indicates there isn't an autodetect function for the SGA.

The other, more general way to use this driver is to link in an autodetect function that will be called by *InitGraph* as part of its hardware-detection logic. Presumably, the manufacturer of the SGA gave you an autodetect function that looks something like this:

```
{ $F+ }
function DetectSGA : integer;
var Found : boolean;
begin
  DetectSGA := grError;                                     { Assume it's not there }
  Found := ...                                             { Look for the hardware }
  if not Found then
    Exit;                                                  { Returns -11 }
  DetectSGA := 3; { Return recommended default video mode }
end;
{ $F- }
```

*DetectSGA*'s job is to look for the SGA hardware at run time. If an SGA is not detected, *DetectSGA* returns a value of -11 (*grError*); otherwise, the return value is the default video mode for the SGA (usually the best mix of color and resolution available on this hardware).

Note that this function takes no parameters, returns a signed, integer-type value, and *must* be a far call. When you install the driver (by calling *InstallUserDriver*), you pass the address of *DetectSGA* along with the device driver's file name:

```

var
  Driver, Mode : integer;
begin
  Driver := InstallUserDriver('SGA', @DetectSGA);
  if Driver = grError then { Table full? }
    Halt(1);
  Driver := Detect;
  { Discard SGA driver #; trust autodetection }
  InitGraph(Driver, Mode, '');
  ...
end.

```

After you install the device driver file name and the SGA autodetect function, you call *InitGraph* and let it go through its normal autodetection process. Before *InitGraph* calls its built-in autodetection function (*DetectGraph*), it first calls *DetectSGA*. If *DetectSGA* doesn't find the SGA hardware, it returns a value of -11 (*grError*) and *InitGraph* proceeds with its normal hardware detection logic (which may include calling any other vendor-supplied autodetection functions in the order in which they were "installed"). If, however, *DetectSGA* determines that an SGA is present, it returns a nonnegative mode number, and *InitGraph* locates and loads SGA.BGI, puts the hardware into the default graphics mode recommended by *DetectSGA*, and finally returns control to your program.

A similar routine exists in Turbo C 2.0.

See also

*GraphResult*, *InitGraph*, *InstallUserFont*, *RegisterBGIfont*, *RegisterBGIdriver*

Example

```

uses
  Graph;
var
  Driver, Mode,
  TestDriver,
  ErrCode : integer;

{$F+}
function TestDetect : integer;
{ Autodetect function: assume hardware is always present;
  return value = recommended default mode }
begin
  TestDetect := 1; { Default mode = 1 }
end;
{$F-}

begin
  { Install the driver }

```

## InstallUserDriver function

```
TestDriver := InstallUserDriver('TEST', @TestDetect);
if GraphResult <> grOk then
begin
    Writeln('Error installing TestDriver');
    Halt(1);
end;
Driver := Detect;                                { Put in graphics mode }
InitGraph(Driver, Mode, '');
ErrCode := GraphResult;
if ErrCode <> grOk then
begin
    Writeln('Error during Init: ', ErrCode);
    Halt(1);
end;
OutText('Installable drivers supported...');
Readln;
Closegraph;
end.
```

---

## InstallUserFont function

## Graph

---

<b>Function</b>	Installs a new font not built into the BGI system.
<b>Declaration</b>	<b>function</b> InstallUserFont(FontFileName : <b>string</b> )
<b>Result type</b>	<b>integer</b>
<b>Remarks</b>	<p><i>FontFileName</i> is the file name of a stroked font. <i>InstallUserFont</i> returns the font ID number that can be passed to <i>SetTextStyle</i> to select this font. If the internal font table is full, a value of 0 (<i>DefaultFont</i>) will be returned.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>See also</b>	<i>InstallUserDriver, RegisterBGIdriver, RegisterBGIfont, SetTextStyle</i>
<b>Example</b>	<pre><b>uses</b>     Graph; <b>var</b>     Driver, Mode : <b>integer</b>;     TestFont : <b>integer</b>; <b>begin</b>     TestFont := InstallUserFont('TEST');    { Install the font }     <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>     <b>begin</b>         Writeln('Error installing TestFont (using DefaultFont)');         Readln;</pre>

```

end;
Driver := Detect;                      { Put in graphics mode }
InitGraph(Driver, Mode, '');
if GraphResult <> grOk then
    Halt(1);
    SetTextStyle(TestFont, HorizDir, 2);      { Use new font }
    OutText('Installable fonts supported...');
    Readln;
    Closegraph;
end.

```

---

## Int function

---

<b>Function</b>	Returns the integer part of the argument.
<b>Declaration</b>	Int(x: real)
<b>Result type</b>	real
<b>Remarks</b>	<i>x</i> is a real-type expression. The result is the integer part of <i>x</i> , that is, <i>x</i> rounded toward zero.
<b>See also</b>	<i>Frac, Round, Trunc</i>
<b>Example</b>	<pre> var r: real; begin     r := Int(123.456);    { 123.0 }     r := Int(-123.456);  { -123.0 } end. </pre>

---

## Intr procedure

---

Dos

<b>Function</b>	Executes a specified software interrupt.
<b>Declaration</b>	Intr(IntNo: byte; var Regs: Registers)
<b>Remarks</b>	<i>IntNo</i> is the software interrupt number (0..255). <i>Registers</i> is a record defined in DOS:

```

type
    Registers = record
        case integer of
            0: (AX, BX, CX, DX, BP, SI, DI, DS, ES,
                Flags: word);
            1: (AL, AH, BL, BH, CL, CH, DL, DH: byte);
        end;
end;

```



## Intr procedure

Before executing the specified software interrupt, *Intr* loads the 8086 CPU's AX, BX, CX, DX, BP, SI, DI, DS, and ES registers from the *Regs* record. When the interrupt completes, the contents of the AX, BX, CX, DX, BP, SI, DI, DS, ES, and Flags registers are stored back into the *Regs* record.

For details on writing interrupt procedures, refer to the section "Interrupt Handling" in Chapter 15, "Inside Turbo Pascal."

<b>Restrictions</b>	Software interrupts that depend on specific values in SP or SS on entry, or modify SP and SS on exit, cannot be executed using this procedure.
<b>Differences</b>	In 3.0, the <i>Registers</i> variable passed to <i>Intr</i> was a user-defined type. In 5.0, the <i>Registers</i> variable must be of type <i>Registers</i> defined in the <i>Dos</i> unit.
<b>See also</b>	<i>MSDOS</i>

---

## IOResult function

---

<b>Function</b>	Returns an integer value that is the status of the last I/O operation performed.
<b>Declaration</b>	<i>IOResult</i>
<b>Result type</b>	word
<b>Remarks</b>	<p>I/O-checking must be off—{\$I-}—in order to trap I/O errors using <i>IOResult</i>. If an I/O error occurs and I/O-checking is off, all subsequent I/O operations are ignored until a call is made to <i>IOResult</i>. A call to <i>IOResult</i> clears its internal error flag.</p> <p>The codes returned are summarized in Appendix D, "Error Messages and Codes." A value of 0 reflects a successful I/O operation.</p>
<b>Differences</b>	In 3.0, return codes were mapped differently.
<b>Example</b>	<pre>var f: file of byte; begin   { Get file name command line }   Assign(f, ParamStr(1));   {\$I-}   Reset(f);</pre>

```

{$I+}
if IOResult = 0 then
  Writeln('File size in bytes: ', FileSize(f))
else
  Writeln('File not found');
end.

```

---

## Keep procedure

Dos

<b>Function</b>	<i>Keep</i> (or <i>Terminate Stay Resident</i> ) terminates the program and makes it stay in memory.
<b>Declaration</b>	<i>Keep</i> (ExitCode: word)
<b>Remarks</b>	The entire program stays in memory—including data segment, stack segment, and heap—so be sure to specify a maximum size for the heap using the \$M compiler directive. The <i>ExitCode</i> corresponds to the one passed to the <i>Halt</i> standard procedure.
<b>Restrictions</b>	Use with care! <i>Terminate Stay Resident</i> (TSR) programs are complex and <i>no</i> other support for them is provided. Refer to the MS-DOS technical documentation for more information.
<b>See also</b>	<i>DosExitCode</i>

---

## KeyPressed function

Crt

<b>Function</b>	Returns True if a key has been pressed on the keyboard; False otherwise.
<b>Declaration</b>	<i>KeyPressed</i>
<b>Result type</b>	boolean
<b>Remarks</b>	The character (or characters) is left in the keyboard buffer. <i>KeyPressed</i> does not detect shift keys like <i>Shift</i> , <i>Alt</i> , <i>NumLock</i> , and so on.
<b>Differences</b>	In 3.0, break-checking {\$C-} had to be off; 5.0 has no such restriction.
<b>See also</b>	<i>ReadKey</i>

## Length function

### Example

```
uses Crt;
begin
  repeat
    Write('Xx');      { Fill the screen until a key is typed }
  until KeyPressed;
end.
```

---

## Length function

---

<b>Function</b>	Returns the dynamic length of a string.
<b>Declaration</b>	Length(s: <b>string</b> )
<b>Result type</b>	integer
<b>Remarks</b>	s is a string-type expression. The result is the length of s.
<b>See also</b>	<i>Concat, Copy, Delete, Insert, Pos</i>
<b>Example</b>	<pre>var f: text; s: <b>string</b>; begin   Assign(f, 'gary.pas');   Reset(f);   Readln(f, s);   Writeln('"' , s, '"')   Writeln('length = ' , length(s)); end.</pre>

---

## Line procedure

## Graph

---

<b>Function</b>	Draws a line from the (x1, y1) to (x2, y2).
<b>Declaration</b>	Line(x1, y1, x2, y2: integer)
<b>Remarks</b>	Draws a line in the style and thickness defined by <i>SetLineStyle</i> and uses the color set by <i>SetColor</i> . Use <i>SetWriteMode</i> to determine whether the line is copied or XOR'd to the screen.  Note that <pre>MoveTo(100,100); LineTo(200,200);</pre> is equivalent to <pre>Line(100,100,200,200);</pre>

```
MoveTo(200,200);
```

Use *LineTo* when the current pointer is at one endpoint of the line. If you want the current pointer updated automatically when the line is drawn, use *LineRel* to draw a line a relative distance from the CP. Note that *Line* doesn't update the current pointer.

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode. Also, for drawing a horizontal line, *Bar* is faster than *Line*.

**See also** *GetLineStyle*, *LineRel*, *LineTo*, *MoveTo*, *Rectangle*, *SetColor*, *SetLineStyle*, *SetWriteMode*

**Example**

```
uses Crt, Graph;
var
  Gd, Gm: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  Randomize;
  repeat
    Line(Random(200), Random(200), Random(200), Random(200));
  until KeyPressed;
  Readln;
  CloseGraph;
end.
```

---

## LineRel procedure

## Graph

**Function** Draws a line to a point that is a relative distance from the current pointer (CP).

**Declaration** *LineRel*(Dx, Dy: integer);

**Remarks** *LineRel* will draw a line from the current pointer to a point that is a relative (Dx,Dy) distance from the current pointer. The current line style and pattern, as set by *SetLineStyle*, are used for drawing the line and uses the color set by *SetColor*. Relative move and line commands are useful for drawing a shape on the screen whose starting point can be changed to draw the same shape in a different location on the screen. Use *SetWriteMode* to

## LineRel procedure

determine whether the line is copied or XOR'd to the screen.

The current pointer is set to the last point drawn by *LineRel*.

### Restrictions

Must be in graphics mode.

A similar routine exists in Turbo C 2.0.

### See also

*GetLineStyle*, *Line*, *LineTo*, *MoveRel*, *MoveTo*, *SetLineStyle*, *SetWriteMode*

### Example

```
uses Graph;
var
  Gd, Gm: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  MoveTo(1,2);
  LineRel(100, 100);           { Draw to the point (101,102) }
  Readln;
  CloseGraph;
end.
```

---

## LineTo procedure

## Graph

---

### Function

Draws a line from the current pointer to (x,y).

### Declaration

*LineTo*(x, y: integer)

### Remarks

Draws a line in the style and thickness defined by *SetLineStyle* and uses the color set by *SetColor*. Use *SetWriteMode* to determine whether the line is copied or XOR'd to the screen.

Note that

```
MoveTo(100,100);
LineTo(200,200);
```

is equivalent to

```
Line(100,100,200,200);
```

The first method is slower and uses more code. Use *LineTo* only when the current pointer is at one endpoint of the line. Use *LineRel* to draw a line a relative distance

from the CP. Note that the second method doesn't change the value of the current pointer.

*LineTo* moves the current pointer to (x,y).

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *Line, LineRel, MoveTo, MoveRel, SetLineStyle, GetLineStyle, SetWriteMode*

**Example**

```

uses Crt, Graph;
var
    Gd, Gm: integer;
begin
    Gd := Detect;
    InitGraph(Gd, Gm, '');
    if GraphResult <> grOk then
        Halt(1);
    Randomize;
    repeat
        LineTo(Random(200), Random(200));
    until KeyPressed;
    Readln;
    CloseGraph;
end.

```

---

## Ln function

---

<b>Function</b>	Returns the natural logarithm of the argument.
<b>Declaration</b>	Ln(x: real)
<b>Result type</b>	real
<b>Remarks</b>	x is a real-type expression. The result is the natural logarithm of x.
<b>See Also</b>	<i>Exp</i>

---

## Lo function

---

<b>Function</b>	Returns the low-order byte of the argument.
<b>Declaration</b>	<code>Lo(x)</code>
<b>Result type</b>	byte
<b>Remarks</b>	<i>x</i> is an expression of type integer or word. <i>Lo</i> returns the low-order byte of <i>x</i> as an unsigned value.
<b>See also</b>	<i>Hi</i> , <i>Swap</i>
<b>Example</b>	<pre> var w: word; begin   w := Lo(\$1234);  { \$34 } end.</pre>

---

## LowVideo procedure

---

Crt

<b>Function</b>	Selects low-intensity characters.
<b>Declaration</b>	<code>LowVideo</code>
<b>Remarks</b>	There is a byte variable in <i>Crt</i> — <i>TextAttr</i> —that is used to hold the current video attribute. <i>LowVideo</i> clears the high-intensity bit of <i>TextAttr</i> 's foreground color, thus mapping colors 8-15 onto colors 0-7.
<b>Differences</b>	In 3.0, <i>LowVideo</i> always selected <i>LightGray</i> on black.
<b>See also</b>	<i>HighVideo</i> , <i>NormVideo</i> , <i>TextBackground</i> , <i>TextColor</i>
<b>Example</b>	<pre> uses Crt; begin   TextAttr := White;   LowVideo;                      { Color is now light gray } end.</pre>

---

## Mark procedure

---

<b>Function</b>	Records the state of the heap in a pointer variable.
<b>Declaration</b>	Mark ( <b>var</b> p: pointer)
<b>Remarks</b>	<i>p</i> is a pointer variable of any pointer type. The current value of the heap pointer is recorded in <i>p</i> , and can later be used as an argument to <i>Release</i> .
<b>Restrictions</b>	<i>Mark</i> and <i>Release</i> cannot be used interchangeably with <i>Dispose</i> and <i>FreeMem</i> unless certain rules are observed. For a complete discussion of this topic, refer to the section "The Heap Manager" on page 181.
<b>See also</b>	<i>Dispose</i> , <i>FreeMem</i> , <i>GetMem</i> , <i>New</i> , <i>Release</i>

---

## MaxAvail function

---

<b>Function</b>	Returns the size of the largest contiguous free block in the heap, corresponding to the size of the largest dynamic variable that can be allocated at that time.
<b>Declaration</b>	MaxAvail
<b>Result type</b>	longint
<b>Remarks</b>	This number is calculated by comparing the sizes of all free blocks below the heap pointer to the size of free memory above the heap pointer. To find the total amount of free memory on the heap, call <i>MemAvail</i> . Your program can specify minimum and maximum heap requirements using the <i>\$M</i> compiler directive (see Appendix B, "Compiler Directives").
<b>Differences</b>	In 3.0, the returned value was an integer that represented the size of the largest free block in paragraphs.
<b>See also</b>	<i>MemAvail</i>
<b>Example</b>	<pre> <b>type</b>   FriendRec = <b>record</b>     Name: <b>string</b>[30];     Age : byte;   <b>end</b>;  <b>var</b>   p: pointer;</pre>



## MaxAvail function

```
begin
  if MaxAvail < SizeOf(FriendRec) then
    Writeln('Not enough memory')
  else
    begin
      { Allocate memory on heap }
      GetMem(p, SizeOf(FriendRec));
      :
      :
    end;
end.
```

---

## MemAvail function

---

<b>Function</b>	Returns the sum of all free blocks in the heap.
<b>Declaration</b>	MemAvail
<b>Result type</b>	longint
<b>Remarks</b>	This number is calculated by adding the sizes of all free blocks below the heap pointer to the size of free memory above the heap pointer. Note that unless <i>Dispose</i> and <i>FreeMem</i> were never called, a block of storage the size of the returned value is unlikely to be available due to fragmentation of the heap. To find the largest free block, call <i>MaxAvail</i> . Your program can specify minimum and maximum heap requirements using the \$M compiler directive (see Appendix B, "Compiler Directives").
<b>Differences</b>	In 3.0, the returned value was an integer that represented the number of free paragraphs.
<b>See also</b>	<i>MaxAvail</i>
<b>Example</b>	<pre>begin   Writeln(MemAvail, ' bytes available');   Writeln('Largest free block is ', MaxAvail, ' bytes'); end.</pre>

---

## MkDir procedure

---

<b>Function</b>	Creates a subdirectory.
<b>Declaration</b>	MkDir(s: string)

**Remarks** *s* is a string-type expression. A new subdirectory with the path specified by *s* is created. The last item in the path cannot be an existing file name.

With  $\{I-\}$ , *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

**See also** *RmDir*, *ChDir*, *GetDir*

**Example**

```
begin
  {I-}
  { Get directory name from command line }
  Mkdir(ParamStr(1));
  if IOResult <> 0 then
    Writeln('Cannot create directory')
  else
    Writeln('New directory created');
end.
```

---

## Move procedure

---

**Function** Copies a specified number of contiguous bytes from a source range to a destination range.

**Declaration** `Move(var source, dest; count: word)`

**Remarks** *source* and *dest* are variable references of any type. *count* is an expression of type *word*. *Move* copies a block of *count* bytes from the first byte occupied by *source* to the first byte occupied by *dest*. No checking is performed, so be careful with this procedure.

**Note:** When *source* and *dest* are in the same segment, that is, when the segment parts of their addresses are equal, *Move* automatically detects and compensates for any overlap. Intra-segment overlaps never occur on statically and dynamically allocated variables (unless they are deliberately forced), and they are therefore not detected.

Whenever possible, use the *SizeOf* function to determine the *count*.

**See also** *FillChar*

## MoveRel procedure

### Example

```
var
  a: array[1..4] of char;
  b: longint;
begin
  Move(a, b, SizeOf(a));           { SizeOf = safety! }
end.
```

---

## MoveRel procedure

## Graph

---

**Function** Moves the current pointer (CP) a relative distance from its current location.

**Declaration** MoveRel(Dx, Dy: integer)

**Remarks** *MoveRel* moves the current pointer (CP) to a point that is a relative (Dx,Dy) distance from the current pointer. Relative move and line commands are useful for drawing a shape on the screen whose starting point can be changed to draw the same shape in a different location on the screen.

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *GetMaxX, GetMaxY, GetX, GetY, LineRel, LineTo, MoveTo*

### Example

```
uses Graph;
var
  Gd, Gm: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  MoveTo(1,2);
  MoveRel(10,10);           { Move to the point (11, 12) }
  PutPixel(GetX, GetY, GetMaxColor);
  Readln;
  CloseGraph;
end.
```

---

**MoveTo procedure****Graph**

---

<b>Function</b>	Moves the current pointer (CP) to $(x,y)$ .
<b>Declaration</b>	<code>MoveTo(x, y: integer)</code>
<b>Remarks</b>	The CP is similar to a text mode cursor except that the CP is not visible. The following routines move the CP:

<i>ClearDevice</i>	<i>MoveRel</i>
<i>ClearViewPort</i>	<i>MoveTo</i>
<i>GraphDefaults</i>	<i>OutText</i>
<i>InitGraph</i>	<i>SetGraphMode</i>
<i>LineRel</i>	<i>SetViewPort</i>
<i>LineTo</i>	

If a viewport is active, the CP will be viewport-relative (the  $x$  and  $y$  values will be added to the viewport's  $x1$  and  $y1$  values). The CP is never clipped at the current viewport's boundaries.

A similar routine exists in Turbo C 2.0.

**See also** *GetMaxX, GetMaxY, GetX, GetY, MoveRel*

**Example**

```

uses Graph;
var
    Gd, Gm: integer;
begin
    Gd := Detect;
    InitGraph(Gd, Gm, '');
    if GraphResult <> grOk then
        Halt(1);
    MoveTo(0,0);           { Upper left corner of viewport }
    LineTo(GetMaxX, GetMaxY);
    Readln;
    CloseGraph;
end.
```

---

## MsDos procedure

Dos

---

<b>Function</b>	Executes a DOS function call.
<b>Declaration</b>	MsDos( <b>var</b> Regs: Registers)
<b>Remarks</b>	<p>The effect of a call to <i>MsDos</i> is the same as a call to <i>Intr</i> with an <i>IntNo</i> of \$21. <i>Registers</i> is a record declared in the <i>Dos</i> unit:</p> <pre> type   Registers = record     case integer of       0: (AX, BX, CX, DX, BP, SI, DI, DS, ES,           Flags: word);       1: (AL, AH, BL, BH, CL, CH, DL, DH: byte);     end;</pre>
<b>Restrictions</b>	Software interrupts that depend on specific calls in SP or SS on entry or modify SP and SS on exit cannot be executed using this procedure.
<b>Differences</b>	In 3.0, no type-checking was performed on the <i>Registers</i> parameter.
<b>See also</b>	<i>Intr</i>

---

## New procedure

---

<b>Function</b>	Creates a new dynamic variable and sets a pointer variable to point to it.
<b>Declaration</b>	New( <b>var</b> p: pointer)
<b>Remarks</b>	<p><i>p</i> is a pointer variable of any pointer type. The size of the allocated memory block corresponds to the size of the type that <i>p</i> points to. The newly created variable can be referenced as <i>p</i><sup>^</sup>. If there isn't enough free space in the heap to allocate the new variable, a run-time error occurs. (It is possible to avoid a run-time error in this case; see "The Heap Error Function" on page 187.)</p>
<b>See also</b>	<i>Dispose</i> , <i>FreeMem</i> , <i>GetMem</i> , <i>Release</i>

---

## NormVideo procedure

Crt

---

<b>Function</b>	Selects the original text attribute read from the cursor location at startup.
<b>Declaration</b>	NormVideo
<b>Remarks</b>	There is a byte variable in <i>Crt</i> — <i>TextAttr</i> —that is used to hold the current video attribute. <i>NormVideo</i> restores <i>TextAttr</i> to the value it had when the program was started.
<b>Differences</b>	In 3.0, <i>NormVideo</i> and <i>HighVideo</i> were identical; see <i>HighVideo</i> .
<b>See also</b>	<i>HighVideo</i> , <i>LowVideo</i> , <i>TextColor</i> , <i>TextBackground</i>

---



---

## NoSound procedure

Crt

---

<b>Function</b>	Turns off the internal speaker.
<b>Declaration</b>	NoSound
<b>Remarks</b>	The following program fragment emits a 440-hertz tone for half a second:  Sound(440); Delay(500); NoSound;
<b>See also</b>	<i>Sound</i>

---



---

## Odd function

---

<b>Function</b>	Tests if the argument is an odd number.
<b>Declaration</b>	Odd(x: longint)
<b>Result type</b>	boolean
<b>Remarks</b>	<i>x</i> is a longint-type expression. The result is True if <i>x</i> is an odd number, and False if <i>x</i> is an even number.

---

---

## Ofs function

---

<b>Function</b>	Returns the offset of a specified object.
<b>Declaration</b>	<code>Ofs(x)</code>
<b>Result type</b>	word
<b>Remarks</b>	<i>x</i> is any variable, or a procedure or function identifier. The result of type word is the offset part of the address of <i>x</i> .
<b>See also</b>	<i>Addr, Seg</i>

---

## Ord function

---

<b>Function</b>	Returns the ordinal number of an ordinal-type value.
<b>Declaration</b>	<code>Ord(x)</code>
<b>Result type</b>	longint
<b>Remarks</b>	<i>x</i> is an ordinal-type expression. The result is of type longint and its value is the ordinality of <i>x</i> .
<b>See also</b>	<i>Chr</i>

---

## OutText procedure

## Graph

---

<b>Function</b>	Sends a string to the output device at the current pointer.
<b>Declaration</b>	<code>OutText (TextString: <b>string</b>)</code>
<b>Remarks</b>	<p><i>TextString</i> is output at the current pointer using the current justification settings. <i>TextString</i> is always truncated at the viewport border if it is too long. If one of the stroked fonts is active, <i>TextString</i> is truncated at the screen boundary if it is too long. If the default (bit-mapped) font is active and the string is too long to fit on the screen, no text is displayed.</p> <p><i>OutText</i> uses the font set by <i>SetTextStyle</i>. In order to maintain code compatibility when using several fonts,</p>

use the *TextWidth* and *TextHeight* calls to determine the dimensions of the string.

*OutText* uses the output options set by *SetTextJustify* (justify, center, rotate 90 degrees, and so on).

The current pointer (CP) is only updated by *OutText* if the direction is horizontal, and the horizontal justification is left. Text output direction is set by *SetTextStyle* (horizontal or vertical); text justification is set by *SetTextJustify* (CP at the left of the string, centered around CP, or CP at the right of the string—written above CP, below CP, or centered around CP). In the following example, block #1 outputs *ABCDEF* and moves CP (text is both horizontally output and left-justified); block #2 outputs *ABC* with *DEF* written right on top of it because text is right-justified; similarly, block #3 outputs *ABC* with *DEF* written right on top of it because text is written vertically.

```

program CPupdate;
uses Graph;
var
    Driver, Mode: integer;
begin
    Driver := Detect;
    InitGraph(Driver, Mode, '');
    if GraphResult < 0 then
        Halt(1);
    { #1 }
    MoveTo(0, 0);
    SetTextStyle(DefaultFont, HorizDir, 1);    { CharSize = 1 }
    SetTextJustify(LeftText, TopText);
    OutText('ABC');                            { CP is updated }
    OutText('DEF');                            { CP is updated }
    { #2 }
    MoveTo(100, 50);
    SetTextStyle(DefaultFont, HorizDir, 1);    { CharSize = 1 }
    SetTextJustify(RightText, TopText);
    OutText('ABC');                            { CP is updated }
    OutText('DEF');                            { CP is updated }
    { #3 }
    MoveTo(100, 100);
    SetTextStyle(DefaultFont, VertDir, 1);     { CharSize = 1 }
    SetTextJustify(LeftText, TopText);
    OutText('ABC');                            { CP is NOT updated }
    OutText('DEF');                            { CP is NOT updated }
    Readln;
    CloseGraph;
end.

```



## OutText procedure

The CP is never updated by *OutTextXY*.

The default font (8×8 bit-mapped) is not clipped at the screen edge. Instead, if any part of the string would go off the screen, no text is output. For example, the following statements would have no effect:

```
SetViewport(0, 0, GetMaxX, GetMaxY, ClipOn);
SetTextJustify(LeftText, TopText);
OutTextXY(-5, 0);           { -5,0 not on screen }
OutTextXY(GetMaxX - 1, 0, 'ABC');   { Part of 'A', }
                                   { All of 'BC' off screen }
```

The “stroked” fonts are clipped at the screen edge, however.

A similar routine exists in Turbo C 2.0.

### Restrictions

Must be in graphics mode.

### See also

*OutTextXY*, *SetTextStyle*, *SetTextJustify*, *GetTextSettings*, *TextHeight*, *TextWidth*, *SetUserCharSize*

### Example

```
uses Graph;
var
  Gd, Gm: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  OutText('Easy to use');
  Readln;
  CloseGraph;
end.
```

---

## OutTextXY procedure

## Graph

### Function

Sends a string to the output device.

### Declaration

*OutTextXY*(X,Y: integer; TextString: string)

### Remarks

*TextString* is output at (X,Y). *TextString* is always truncated at the viewport border if it is too long. If one of the stroked fonts is active, *TextString* is truncated at the screen boundary if it is too long. If the default (bit-mapped) font is active and the string is too long to fit on the screen, no text is displayed.

Use *OutText* to output text at the current pointer; use *OutTextXY* to output text elsewhere on the screen.

*OutTextXY* uses the font set by *SetTextStyle*. In order to maintain code compatibility when using several fonts, use the *TextWidth* and *TextHeight* calls to determine the dimensions of the string.

*OutTextXY* uses the output options set by *SetTextJustify* (justify, center, rotate 90 degrees, and so forth).

A similar routine exists in Turbo C 2.0.

<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>OutText</i> , <i>SetTextStyle</i> , <i>SetTextJustify</i> , <i>GetTextSetting</i> , <i>TextHeight</i> , <i>TextWidth</i> , <i>SetUserCharSize</i>
<b>Example</b>	<pre> <b>uses</b> Graph; <b>var</b>     Gd, Gm: integer; <b>begin</b>     Gd := Detect;     InitGraph(Gd, Gm, '');     <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>         Halt(1);     MoveTo(0, 0);     OutText('Inefficient');     Readln;     OutTextXY(GetX, GetY, 'Also inefficient');     Readln;     ClearDevice;     OutTextXY(0, 0, 'Perfect!');           { Replaces above }     Readln;     CloseGraph; <b>end.</b> </pre>

---

## OvrClearBuf procedure Overlay

---

<b>Function</b>	Clears the overlay buffer.
<b>Declaration</b>	<i>OvrClearBuf</i>
<b>Remarks</b>	Upon a call to <i>OvrClearBuf</i> , all currently loaded overlays are disposed from the overlay buffer. This forces subsequent calls to overlaid routines to reload the overlays from the overlay file (or from EMS). If <i>OvrClearBuf</i> is called from an overlay, that overlay will

immediately be reloaded upon return from *OvrClearBuf*. The overlay manager never requires you to call *OvrClearBuf*; in fact, doing so will decrease performance of your application, since it forces overlays to be reloaded. *OvrClearBuf* is solely intended for special use, such as temporarily reclaiming the memory occupied by the overlay buffer.

**See also** *OvrGetBuf*, *OvrSetBuf*

---

## OvrGetBuf function

## Overlay

---

<b>Function</b>	Returns the current size of the overlay buffer.
<b>Declaration</b>	<i>OvrGetBuf</i>
<b>Result type</b>	longint
<b>Remarks</b>	The size of the overlay buffer is set through a call to <i>OvrSetBuf</i> . Initially, the overlay buffer is as small as possible, corresponding to the size of the largest overlay. A buffer of this size is automatically allocated when an overlaid program is executed. (Note: The initial buffer size may be larger than 64K, since it includes both code and fix-up information for the largest overlay.)

**See also** *OvrInit*, *OvrInitEMS*, *OvrSetBuf*

**Example**

```
{ $M 16384,65536,655360 }
uses Overlay;
const
    ExtraSize = 49152; {48K}
begin
    OvrInit('EDITOR.OVR');
    Writeln('Initial size of overlay buffer is ',
           OvrGetBuf,' bytes. ');
    OvrSetBuf(OvrGetBuf+ExtraSize);
    Writeln('Overlay buffer now increased to ',
           OvrGetBuf,' bytes. ');
end.
```

---

## OvrInit procedure

## Overlay

---

**Function**            Initializes the overlay manager and opens the overlay file.

**Declaration**        `OvrInit (FileName: string)`

**Remarks**            If the file name parameter does not specify a drive or a subdirectory, the overlay manager searches for the file in the current directory, in the directory that contains the .EXE file (if running under DOS 3.x), and in the directories specified in the PATH environment variable.

Errors are reported in the *OvrResult* variable. *ovrOk* indicates success. *ovrError* means that the overlay file is of an incorrect format, or that the program has no overlays. *ovrNotFound* means that the overlay file could not be located.

In case of error, the overlay manager remains uninstalled, and an attempt to call an overlaid routine will produce run-time error 208 (Overlay manager not installed).

*OvrInit* must be called before any of the other overlay manager procedures.

**See also**             *OvrGetBuf*, *OvrInitEMS*, *OvrSetBuf*

**Example**             `uses Overlay;`  
`begin`  
`OvrInit('EDITOR.OVR');`  
`if OvrResult<>ovrOk then`  
`begin`  
`case OvrResult of`  
`ovrError:    Writeln('Program has no overlays.');`  
`ovrNotFound: Writeln('Overlay file not found.');`  
`end;`  
`Halt(1);`  
`end;`  
`end.`

---

## OvrInitEMS procedure

## Overlay

---

**Function**            Loads the overlay file into EMS if possible.

**Declaration**        `OvrInitEMS`

### Remarks

If an EMS driver can be detected and if enough EMS memory is available, *OvrInitEMS* loads all overlays into EMS and closes the overlay file. Subsequent overlay loads are reduced to fast in-memory transfers. *OvrInitEMS* installs an exit procedure, which automatically deallocates EMS memory upon termination of the program.

Errors are reported in the *OvrResult* variable. *ovrOk* indicates success. *ovrError* means that *OvrInit* failed or was not called. *ovrIOError* means that an I/O error occurred while reading the overlay file. *ovrNoEMSDriver* means that an EMS driver could not be detected. *ovrNoEMSMemory* means that there is not enough free EMS memory available to load the overlay file.

In case of error, the overlay manager will continue to function, but overlays will be read from disk.

The EMS driver must conform to the Lotus/Intel/Microsoft Expanded Memory Specification (EMS). If you are using an EMS-based RAM disk, make sure that the command in the CONFIG.SYS file that loads the RAM-disk driver leaves some unallocated EMS memory for your overlaid applications.

### See also

*OvrGetBuf*, *OvrInit*, *OvrSetBuf*

### Example

```
uses Overlay;
begin
  OvrInit('EDITOR.OVR');
  if OvrResult<>ovrOk then
  begin
    Writeln('Overlay manager initialization failed.');
```

Halt(1);

```
  end;
  OvrInitEMS;
  case OvrResult of
    ovrIOError:   Writeln('Overlay file I/O error.');
```

ovrNoEMSDriver: Writeln('EMS driver not installed.');

```
    ovrNoEMSMemory: Writeln('Not enough EMS memory.');
```

else

```
    Writeln('Using EMS for faster overlay swapping.');
```

end;

```
end;
```

---

## OvrSetBuf procedure

## Overlay

---

<b>Function</b>	Sets the size of the overlay buffer.
<b>Declaration</b>	<code>OvrSetBuf (BufSize: longint)</code>
<b>Remarks</b>	<p><i>BufSize</i> must be larger than or equal to the initial size of the overlay buffer, and less than or equal to <i>MemAvail</i> + <i>OvrGetBuf</i>. The initial size of the overlay buffer is the size returned by <i>OvrGetBuf</i> before any calls to <i>OvrSetBuf</i>.</p> <p>If the specified size is larger than the current size, additional space is allocated from the beginning of the heap, thus decreasing the size of the heap. Likewise, if the specified size is less than the current size, excess space is returned to the heap.</p> <p><i>OvrSetBuf</i> requires that the heap be empty; an error is returned if dynamic variables have already been allocated using <i>New</i> or <i>GetMem</i>. For this reason, make sure to call <i>OvrSetBuf</i> before the <i>Graph</i> unit's <i>InitGraph</i> procedure; <i>InitGraph</i> allocates memory on the heap and—once it has done so—all calls to <i>OvrSetBuf</i> will be ignored.</p> <p>If you are using <i>OvrSetBuf</i> to increase the size of the overlay buffer, you should also include a <i>\$M</i> compiler directive in your program to increase the minimum size of the heap accordingly.</p> <p>Errors are reported in the <i>OvrResult</i> variable. <i>ovrOk</i> indicates success. <i>ovrError</i> means that <i>OvrInit</i> failed or was not called, that <i>BufSize</i> is too small, or that the heap is not empty. <i>ovrNoMemory</i> means that there is not enough heap memory to increase the size of the overlay buffer.</p>
<b>See also</b>	<i>OvrGetBuf</i> , <i>OvrInit</i> , <i>OvrInitEMS</i>
<b>Example</b>	<pre> (\$M 16384,65536,655360) uses Overlay; const     ExtraSize = 49152; {48K} begin     OvrInit('EDITOR.OVR');     OvrSetBuf(OvrGetBuf+ExtraSize); end.</pre>

---

## PackTime procedure

Dos

<b>Function</b>	Converts a <i>DateTime</i> record into a 4-byte, packed date-and-time longint used by <i>SetFTime</i> .
<b>Declaration</b>	PackTime( <b>var</b> DT: DateTime; <b>var</b> Time: longint)
<b>Remarks</b>	<p><i>DateTime</i> is a record declared in the <i>Dos</i> unit:</p> <pre> DateTime = <b>record</b>     Year, Month, Day, Hour, Min, Sec: word; <b>end</b>; </pre> <p>The fields of the <i>DateTime</i> record are not range-checked.</p>
<b>See also</b>	<i>UnpackTime, GetFTime, SetFTime, GetTime, SetTime</i>

---

## ParamCount function

<b>Function</b>	Returns the number of parameters passed to the program on the command line.
<b>Declaration</b>	ParamCount
<b>Result type</b>	word
<b>Remarks</b>	Blanks and tabs serve as separators.
<b>See also</b>	<i>ParamStr</i>
<b>Example</b>	<pre> <b>begin</b>     <b>if</b> ParamCount &lt; 1 <b>then</b>         Writeln('No parameters on command line')     <b>else</b>         Writeln(ParamCount, ' parameter(s)');     <b>end</b>. </pre>

---

## ParamStr function

<b>Function</b>	Returns a specified command-line parameter.
<b>Declaration</b>	ParamStr(index)
<b>Result type</b>	string

<b>Remarks</b>	<i>index</i> is an expression of type <i>word</i> . <i>ParamStr</i> returns the <i>index</i> th parameter from the command line, or an empty string if <i>index</i> is zero or greater than <i>ParamCount</i> . With DOS 3.0 or later, <i>ParamStr</i> (0) returns the path and file name of the executing program (for example, C:\TP\MYPROG.EXE).
<b>See also</b>	<i>ParamCount</i>
<b>Example</b>	<pre> var i: word; begin   for i := 1 to ParamCount do     Writeln(ParamStr(i)); end.</pre>

---

## Pi function

---

<b>Function</b>	Returns the value of Pi (3.1415926535897932385).
<b>Declaration</b>	Pi
<b>Result type</b>	real
<b>Remarks</b>	Precision varies, depending on whether the compiler is in 8087 (80287, 80387) or software-only mode.
<b>Differences</b>	In 3.0, <i>Pi</i> was a constant.

---

## PieSlice procedure

## Graph

<b>Function</b>	Draws and fills a pie slice, using (X,Y) as the center point and drawing from start angle to end angle.
<b>Declaration</b>	PieSlice(x, y: integer; StAngle, EndAngle, Radius: word)
<b>Remarks</b>	<p>The pie slice is outlined using the current color, and filled using the pattern and color defined by <i>SetFillStyle</i> or <i>SetFillPattern</i>.</p> <p>Each graphics driver contains an aspect ratio that is used by <i>Circle</i>, <i>Arc</i>, and <i>PieSlice</i>. A start angle of 0 and an end angle of 360 will draw and fill a complete circle. The angles for <i>Arc</i>, <i>Ellipse</i>, and <i>PieSlice</i> are counterclockwise with 0 degrees at 3 o'clock, 90 degrees at 12 o'clock, and so on.</p>



## PieSlice procedure

If an error occurs while filling the pie slice, *GraphResult* will return a value of -6 (*grNoScanMem*).

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *Arc, Circle, Ellipse, FillEllipse, GetArcCoords, GetAspectRatio, Sector, SetFillStyle, SetFillPattern, SetGraphBufSize*

**Example**

```
uses Graph;
const
  Radius = 30;
var
  Gd, Gm: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  PieSlice(100, 100, 0, 270, Radius);
  Readln;
  CloseGraph;
end.
```

---

## Pos function

---

**Function** Searches for a substring in a string.

**Declaration** *Pos*(*substr*, *s*: **string**)

**Result type** byte

**Remarks** *substr* and *s* are string-type expressions. *Pos* searches for *substr* within *s*, and returns an integer value that is the index of the first character of *substr* within *s*. If *substr* is not found, *Pos* returns zero.

**See also** *Concat, Copy, Delete, Insert, Length*

**Example**

```
var s: string;
begin
  s := ' 123.5';
  { Convert spaces to zeroes }
  while Pos(' ', s) > 0 do
    s[Pos(' ', s)] := '0';
end.
```

---

## Pred function

---

<b>Function</b>	Returns the predecessor of the argument.
<b>Declaration</b>	<code>Pred(x)</code>
<b>Result type</b>	Same type as parameter.
<b>Remarks</b>	<i>x</i> is an ordinal-type expression. The result, of the same type as <i>x</i> , is the predecessor of <i>x</i> .
<b>See also</b>	<i>Succ, Dec, Inc</i>

---



---

## Ptr function

---

<b>Function</b>	Converts a segment base and an offset address to a pointer-type value.
<b>Declaration</b>	<code>Ptr(Seg, Ofs: word)</code>
<b>Result type</b>	pointer
<b>Remarks</b>	<p><i>Seg</i> and <i>Ofs</i> are expressions of type <i>word</i>. The result is a pointer that points to the address given by <i>Seg</i> and <i>Ofs</i>. Like <i>nil</i>, the result of <i>Ptr</i> is assignment-compatible with all pointer types.</p> <p>The function result may be dereferenced and typecast:</p> <pre> if Byte(Ptr(\$40, \$49)^(^)) = 7 then   Writeln('Video mode = mono'); </pre>
<b>See also</b>	<i>Addr, Ofs, Seg</i>
<b>Example</b>	<pre> var p: ^byte; begin   p := Ptr(\$40, \$49);   Writeln('Current video mode is ', p^(^)); end. </pre>

---



---

## PutImage procedure

---



---

## Graph

---

<b>Function</b>	Puts a bit image onto the screen.
<b>Declaration</b>	<code>PutImage(x, y: integer; var BitMap; BitBlt: word)</code>

## PutImage procedure

### Remarks

$(x,y)$  is the upper left corner of a rectangular region on the screen. *BitMap* is an untyped parameter that contains the height and width of the region, and the bit image that will be put onto the screen. *BitBl* specifies which binary operator will be used to put the bit image onto the screen.

The following constants are defined:

```
const
  CopyPut  = 0;      { MOV }
  XORPut   = 1;      { XOR }
  OrPut    = 2;      { OR  }
  AndPut   = 3;      { AND }
  NotPut   = 4;      { NOT }
```

Each constant corresponds to a binary operation. For example, *PutImage(x,y,BitMap,NormalPut)* puts the image stored in *BitMap* at  $(x,y)$  using the assembly language MOV instruction for each byte in the image.

Similarly, *PutImage(x,y,BitMap,XORPut)* puts the image stored in *BitMap* at  $(x,y)$  using the assembly language XOR instruction for each byte in the image. This is an often-used animation technique for “dragging” an image around the screen.

*PutImage(x,y,Bitmap,NotPut)* inverts the bits in *BitMap* and then puts the image stored in *BitMap* at  $(x,y)$  using the assembly language MOV for each byte in the image. Thus, the image appears in inverse video of the original *BitMap*.

Note that *PutImage* is never clipped to the viewport boundary. Moreover—with one exception—it is not actually clipped at the screen edge either. Instead, if any part of the image would go off the screen, no image is output. In the following example, the first image would be output, but the middle three *PutImage* statements would have no effect:

```
program NoClip;
uses graph;
var
  Driver, Mode: integer;
  p: pointer;
begin
  Driver := Detect;
  InitGraph(Driver, Mode, '');
  if GraphResult < 0 then
```

```

    Halt(1);
    SetViewport(0, 0, GetMaxX, GetMaxY, clipon);
    GetMem(p, ImageSize(0, 0, 99, 49));
    PieSlice(50, 25, 0, 360, 45);
    GetImage(0, 0, 99, 49, p^);      { Width = 100, height = 50 }
    ClearDevice;
    PutImage(GetMaxX - 99, 0,          { Will barely fit }
             p^, NormalPut);
    PutImage(GetMaxX - 98, 0,          { x + height > GetMaxX }
             p^, NormalPut);
    PutImage(-1, 0,                   { -1,0 not on screen }
             p^, NormalPut);
    PutImage(0, -1,                   { 0,-1 not on screen }
             p^, NormalPut);
    PutImage(0, GetMaxY - 30,         { Will output 31 "lines" }
             p^, NormalPut);
    Readln;
    CloseGraph;
end.

```

In the last *PutImage* statement, the height is clipped at the lower screen edge, and a partial image is displayed. This is the only time any clipping is performed on *PutImage* output.

A similar routine exists in Turbo C 2.0.

### Restrictions

Must be in graphics mode.

### See also

*GetImage*, *ImageSize*

### Example

```

uses Graph;
var
  Gd, Gm: integer;
  P: pointer;
  Size: word;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  Bar(0, 0, GetMaxX, GetMaxY);
  Size := ImageSize(10,20,30,40);
  GetMem(P, Size);      { Allocate memory on heap }
  GetImage(10,20,30,40,P^);
  Readln;
  ClearDevice;
  PutImage(100, 100, P^, NormalPut);
  Readln;
  CloseGraph;
end.

```

---

## PutPixel procedure

## Graph

---

<b>Function</b>	Plots a pixel at $x,y$ .
<b>Declaration</b>	PutPixel( $x$ , $y$ : integer; Pixel: word)
<b>Remarks</b>	Plots a point in the color defined by <i>Pixel</i> at $(x,y)$ . A similar routine exists in Turbo C 2.0.
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>GetImage, GetPixel, PutImage</i>
<b>Example</b>	<pre> <b>uses</b> Crt, Graph; <b>var</b>     Gd, Gm: integer;     Color : word; <b>begin</b>     Gd := Detect;     InitGraph(Gd, Gm, '');     <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>         Halt(1);     Color := GetMaxColor;     Randomize;     <b>repeat</b>         PutPixel(Random(100),Random(100),Color); { Plot "stars" }         Delay(10);     <b>until</b> KeyPressed;     Readln;     CloseGraph; <b>end.</b> </pre>

---

## Random function

<b>Function</b>	Returns a random number.
<b>Declaration</b>	Random [ ( range: word) ]
<b>Result type</b>	real or word, depending on the parameter
<b>Remarks</b>	If <i>range</i> is not specified, the result is a <i>Real</i> random number within the range $0 \leq x < 1$ . If <i>range</i> is specified, it must be an expression of type integer, and the result is a word random number within the range $0 \leq x < \text{range}$ . If <i>range</i> equals 0, a value of 0 will be returned.

The *Random* number generator should be initialized by making a call to *Randomize*, or by assigning a value to *RandSeed*.

**See also** *Randomize*

**Example**

```

uses Crt;
begin
  Randomize;
  repeat
    { Write text in random colors }
    TextAttr := Random(256);
    Write('!');
  until KeyPressed;
end.

```

---

## Randomize procedure

---

**Function**      Initializes the built-in random generator with a random value.

**Declaration**      *Randomize*

**Remarks**      The random value is obtained from the system clock.

**Note:** The random-number generator's seed is stored in a predeclared longint variable called *RandSeed*. By assigning a specific value to *RandSeed*, a specific sequence of random numbers can be generated over and over. This is particularly useful in applications that use data encryption.

**See also** *Random*

---

## Read procedure (text files)

---

**Function**      Reads one or more values from a text file into one or more variables.

**Declaration**      `Read( [ var f: text; ] v1 [, v2,...,vn ] )`

**Remarks**      *f*, if specified, is a text-file variable. If *f* is omitted, the standard file variable *Input* is assumed. Each *v* is a variable of type char, integer, real, or string.

With a type char variable, *Read* reads one character from the file and assigns that character to the variable. If *Eof(f)* was True before *Read* was executed, the value *Chr(26)* (a *Ctrl-Z* character) is assigned to the variable. If *Eoln(f)* was True, the value *Chr(13)* (a carriage-return character) is assigned to the variable. The next *Read* will start with the next character in the file.

With a type integer variable, *Read* expects a sequence of characters that form a signed number, according to the syntax shown in the section "Numbers" in Chapter 1, "Tokens and Constants." Any blanks, tabs, or end-of-line markers preceding the numeric string are skipped. Reading ceases at the first blank, tab, or end-of-line marker following the numeric string or if *Eof(f)* becomes True. If the numeric string does not conform to the expected format, an I/O error occurs; otherwise, the value is assigned to the variable. If *Eof(f)* was True before *Read* was executed or if *Eof(f)* becomes True while skipping initial blanks, tabs, and end-of-line markers, the value 0 is assigned to the variable. The next *Read* will start with the blank, tab, or end-of-line marker that terminated the numeric string.

With a type real variable, *Read* expects a sequence of characters that form a signed whole number, according to the syntax shown in the section "Numbers" in Chapter 1, "Tokens and Constants" (except that hexadecimal notation is not allowed). Any blanks, tabs, or end-of-line markers preceding the numeric string are skipped. Reading ceases at the first blank, tab, or end-of-line marker following the numeric string or if *Eof(f)* becomes True. If the numeric string does not conform to the expected format, an I/O error occurs; otherwise, the value is assigned to the variable. If *Eof(f)* was True before *Read* was executed, or if *Eof(f)* becomes True while skipping initial blanks, tabs, and end-of-line markers, the value 0 is assigned to the variable. The next *Read* will start with the blank, tab, or end-of-line marker that terminated the numeric string.

With a type string variable, *Read* reads all characters up to, but not including, the next end-of-line marker or until *Eof(f)* becomes True. The resulting character string is assigned to the variable. If the resulting string is longer than the maximum length of the string variable, it

is truncated. The next *Read* will start with the end-of-line marker that terminated the string.

With *{\$I-}*, *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

**Restrictions** *Read* with a type string variable does not skip to the next line after reading. For this reason, you cannot use successive *Read* calls to read a sequence of strings, since you will never get past the first line; after the first *Read*, each subsequent *Read* will see the end-of-line marker and return a zero-length string. Instead, use multiple *Readln* calls to read successive string values.

**Differences** See Appendix A in the *User's Guide*, "Differences between Turbo Pascal 3.0, 4.0, and 5.0."

**See also** *Readln*, *ReadKey*, *Write*, *Writeln*

---

## Read procedure (typed files)

---

**Function** Reads a file component into a variable.

**Declaration** `Read(f, v1 [, v2, ..., vn ] )`

**Remarks** *f* is a file variable of any type except text, and each *v* is a variable of the same type as the component type of *f*. For each variable read, the current file position is advanced to the next component. It's an error to attempt to read from a file when the current file position is at the end of the file, that is, when *Eof(f)* is True.

With *{\$I-}*, *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

**Restrictions** File must be open.

**See also** *Write*

---

## ReadKey function

---

**Crt**

**Function** Reads a character from the keyboard.

**Declaration** `ReadKey`

**Result type** `char`



## ReadKey function

### Remarks

The character read is not echoed to the screen. If *KeyPressed* was True before the call to *ReadKey*, the character is returned immediately. Otherwise, *ReadKey* waits for a key to be typed.

The special keys on the PC keyboard generate extended scan codes. (The extended scan codes are summarized in Appendix C.) Special keys are the function keys, the cursor control keys, *Alt* keys, and so on. When a special key is pressed, *ReadKey* first returns a null character (#0), and then returns the extended scan code. Null characters cannot be generated in any other way, so you are guaranteed the next character will be an extended scan code.

The following program fragment reads a character or an extended scan code into a variable called *Ch* and sets a Boolean variable called *FuncKey* to True if the character is a special key:

```
Ch := ReadKey;
if Ch <> #0 then FuncKey := False else
begin
  FuncKey := True;
  Ch := ReadKey;
end;
```

The *CheckBreak* variable controls whether *Ctrl-Break* should abort the program or be returned like any other key. When *CheckBreak* is False, *ReadKey* returns a *Ctrl-C* (#3) for *Ctrl-Break*.

### See also

*KeyPressed*

---

## Readln procedure

---

### Function

Executes the *Read* procedure then skips to the next line of the file.

### Declaration

```
Readln( [ var f: text; ] v1 [, v2,...,vn ] )
```

### Remarks

*Readln* is an extension to *Read*, as it is defined on text files. After executing the *Read*, *Readln* skips to the beginning of the next line of the file.

*Readln(f)* with no parameters causes the current file position to advance to the beginning of the next line (if

there is one; otherwise, it goes to the end of the file). *Readln* with no parameter list altogether corresponds to *Readln(Input)*.

With *{I-}*, *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

**Restrictions** Works only on text files, including standard input. File must be open for input.

**See also** *Read*

---

## Rectangle procedure

## Graph

**Function** Draws a rectangle using the current line style and color.

**Declaration** *Rectangle*(x1, y1, x2, y2: integer)

**Remarks** (x1, y1) define the upper left corner of the rectangle, and (x2, y2) define the lower right corner (0 <= x1 < x2 <= *GetMaxX*, and 0 <= y1 < y2 <= *GetMaxY*).

The rectangle will be drawn in the current line style and color, as set by *SetLineStyle* and *SetColor*. Use *SetWriteMode* to determine whether the rectangle is copied or XOR'd to the screen.

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *Bar*, *Bar3D*, *GetViewSettings*, *InitGraph*, *SetColor*, *SetLineStyle*, *SetViewport*, *SetWriteMode*

**Example**

```
uses Crt, Graph;
var
  GraphDriver, GraphMode: integer;
  x1, y1, x2, y2: integer;
begin
  GraphDriver := Detect;
  InitGraph(GraphDriver, GraphMode, '');
  if GraphResult <> grOk then
    Halt(1);
  Randomize;
  repeat
    x1 := Random(GetMaxX);
    y1 := Random(GetMaxY);
    x2 := Random(GetMaxX-x1) + x1;
    y2 := Random(GetMaxY-y1) + y1;
```

## Rectangle procedure

```
    Rectangle(x1, y1, x2, y2);  
until KeyPressed;  
CloseGraph;  
end.
```

---

## RegisterBGIdriver function

## Graph

**Function** Registers a user-loaded or linked-in BGI driver with the graphics system.

**Declaration** RegisterBGIdriver(driver: pointer) : integer;

**Remarks** If an error occurs, the return value is less than 0; otherwise, the internal driver number is returned. This routine enables a user to load a driver file and "register" the driver by passing its memory location to *RegisterBGIdriver*. When that driver is used by *InitGraph*, the registered driver will be used (instead of being loaded from disk by the *Graph* unit). A user-registered driver can be loaded from disk onto the heap, or converted to an .OBJ file (using BINOBJ.EXE) and linked into the .EXE.

*grInvalidDriver* is a possible error return, where the error code equals -4 and the driver header is not recognized.

The following program loads the CGA driver onto the heap, registers it with the graphics system, and calls *InitGraph*:

```
program LoadDrv;  
uses Graph;  
var  
    Driver, Mode: integer;  
    DriverF: file;  
    DriverP: pointer;  
begin  
    { Open driver file, read into memory, register it }  
    Assign(DriverF, 'CGA.BGI');  
    Reset(DriverF, 1);  
    GetMem(DriverP, FileSize(DriverF));  
    BlockRead(DriverF, DriverP^, FileSize(DriverF));  
    if RegisterBGIdriver(DriverP) < 0 then  
    begin  
        Writeln('Error registering driver: ',  
            GraphErrorMsg(GraphResult));  
        Halt(1);  
    end;  
end;
```

```

end;
{ Init graphics }
Driver := CGA;
Mode := CGAHi;
InitGraph(Driver, Mode, '');
if GraphResult < 0 then
    Halt(1);
    OutText('Driver loaded by user program');
    Readln;
    CloseGraph;
end.

```

The program begins by loading the CGA driver file from disk and registering it with the *Graph* unit. Then a call is made to *InitGraph* to initialize the graphics system. You may wish to incorporate one or more driver files directly into your .EXE file. In this way, the graphics drivers that your program needs will be built-in and only the .EXE will be needed in order to run. The process for incorporating a driver file into your .EXE is straightforward:

1. Run BINOBJ on the driver file(s).
2. Link the resulting .OBJ file(s) into your program.
3. Register the linked-in driver file(s) before calling *InitGraph*.

For a detailed explanation and example of the preceding, refer to the comments at the top of the GRLINK.PAS example program on the distribution disks. For information on the BINOBJ utility, refer to Appendix C of the *User's Guide*, "Turbo Pascal Utilities."

It is also possible to register font files; refer to the description of *RegisterBGIfont*.

A similar routine exists in Turbo C 2.0.

### Restrictions

Note that the driver must be registered *before* the call to *InitGraph*. If a call is made to *RegisterBGIdriver* once graphics have been activated, a value of -11 (*grError*) will be returned.

### See also

*InitGraph*, *InstallUserDriver*, *RegisterBGIfont*

## RegisterBGIfont function

## Graph

**Function** Registers a user-loaded or linked-in BGI font with the graphics system.

**Declaration** RegisterBGIfont(font: pointer) : integer;

**Remarks** The return value is less than 0 if an error occurs; otherwise, the internal font number is returned. This routine enables a user to load a font file and "register" the font by passing its memory location to *RegisterBGIfont*. When that font is selected with a call to *SetTextStyle*, the registered font will be used (instead of being loaded from disk by the *Graph* unit). A user-registered font can be loaded from disk onto the heap, or converted to an .OBJ file (using BINOBJ.EXE) and linked into the .EXE.

Here are some possible error returns:

Error Code	Error Identifier	Comments
-11	grError	There is no room in the font table to register another font. (The font table holds up to 10 fonts, and only 4 are provided, so this error should not occur.)
-13	grInvalidFont	The font header is not recognized.
-14	grInvalidFontNum	The font number in the font header is not recognized.

The following program loads the triplex font onto the heap, registers it with the graphics system, and then alternates between using triplex and another stroked font that *Graph* loads from disk (*SansSerifFont*):

```

program LoadFont;
uses Graph;
var
    Driver, Mode: integer;
    FontF: file;
    FontP: pointer;
begin

```

```

{ Open font file, read into memory, register it }
Assign(FontF, 'TRIP.CHR');
Reset(FontF, 1);
GetMem(FontP, FileSize(FontF));
BlockRead(FontF, FontP^, FileSize(FontF));
if RegisterBGIfont(FontP) < 0 then
begin
    Writeln('Error registering font: ',
            GraphErrorMsg(GraphResult));
    Halt(1);
end;
{ Init graphics }
Driver := Detect;
InitGraph(Driver, Mode, '..\');
if GraphResult < 0 then
    Halt(1);
Readln;
{ Select registered font }
SetTextStyle(TriplexFont, HorizDir, 4);
OutText('Triplex loaded by user program');
MoveTo(0, TextHeight('a'));
Readln;
{ Select font that must be loaded from disk }
SetTextStyle(SansSerifFont, HorizDir, 4);
OutText('Your disk should be spinning...');
MoveTo(0, GetY + TextHeight('a'));
Readln;
{ Re-select registered font (already in memory) }
SetTextStyle(TriplexFont, HorizDir, 4);
OutText('Back to Triplex');
Readln;
CloseGraph;
end.

```

The program begins by loading the triplex font file from disk and registering it with the *Graph* unit. Then a call to *InitGraph* is made to initialize the graphics system. Watch the disk drive indicator and press *Enter*. Because the triplex font is already loaded into memory and registered, *Graph* does not have to load it from disk (and therefore your disk drive should not spin). Next, the program will activate the sans serif font by loading it from disk (it is unregistered). Press *Enter* again and watch the drive spin. Finally, the triplex font is selected again. Since it is in memory and already registered, the drive will not spin when you press *Enter*.

There are several reasons to load and register font files. First, *Graph* only keeps one stroked font in memory at a

time. If you have a program that needs to quickly alternate between stroked fonts, you may want to load and register the fonts yourself at the beginning of your program. Then *Graph* will not load and unload the fonts each time a call to *SetTextStyle* is made.

Second, you may wish to incorporate the font files directly into your .EXE file. This way, the font files that your program needs will be built-in, and only the .EXE and driver files will be needed in order to run. The process for incorporating a font file into your .EXE is straightforward:

1. Run BINOBJ on the font file(s).
2. Link the resulting .OBJ file(s) into your program.
3. Register the linked-in font file(s) before calling *InitGraph*.

For a detailed explanation and example of the preceding, refer to the comments at the top of the GRLINK.PAS example program on the distribution disks. Documentation on the BINOBJ utility is available in Appendix C of the *User's Guide*.

Note that the default (8×8 bit-mapped) font is built into GRAPH.TPU, and thus is always in memory. Once a stroked font has been loaded, your program can alternate between the default font and the stroked font without having to reload either one of them.

It is also possible to register driver files; refer to the description of *RegisterBGIDriver*.

A similar routine exists in Turbo C 2.0.

See also

*InitGraph*, *InstallUserDriver*, *InstallUserFont*, *RegisterBGIfont*, *SetTextStyle*

---

## Release procedure

---

Function	Returns the heap to a given state.
Declaration	Release( <b>var</b> p: pointer)
Remarks	<i>p</i> is a pointer variable of any pointer type that was previously assigned by the <i>Mark</i> procedure. <i>Release</i>

disposes all dynamic variables that were allocated by *New* or *GetMem* since *p* was assigned by *Mark*.

**Restrictions** *Mark* and *Release* cannot be used interchangeably with *Dispose* and *FreeMem* unless certain rules are observed. For a complete discussion of this topic, refer to the section "The Heap Manager" on page 181.

**See also** *Dispose*, *FreeMem*, *GetMem*, *Mark*, *New*

---

## Rename procedure

---

**Function** Renames an external file.

**Declaration** `Rename (var f; newname: string)`

**Remarks** *f* is a file variable of any file type. *newname* is a string-type expression. The external file associated with *f* is renamed to *newname*. Further operations on *f* will operate on the external file with the new name.

With `{I-}`, *IOResult* will return 0 if the operation was successful; otherwise, it will return a nonzero error code.

**Restrictions** *Rename* must never be used on an open file.

**See also** *Erase*

---

## Reset procedure

---

**Function** Opens an existing file.

**Declaration** `Reset (var f [ : file; recsize: word ] )`

**Remarks** *f* is a file variable of any file type, which must have been associated with an external file using *Assign*. *recsize* is an optional expression of type `word`, which can only be specified if *f* is an untyped file.

*Reset* opens the existing external file with the name assigned to *f*. It's an error if no existing external file of the given name exists. If *f* was already open, it is first closed and then re-opened. The current file position is set to the beginning of the file.



## Reset procedure

If *f* was assigned an empty name, such as *Assign(f, '')*, then after the call to *Reset*, *f* will refer to the standard input file (standard handle number 0).

If *f* is a text file, *f* becomes read-only. After a call to *Reset*, *Eof(f)* is True if the file is empty; otherwise, *Eof(f)* is False.

If *f* is an untyped file, *recsize* specifies the record size to be used in data transfers. If *recsize* is omitted, a default record size of 128 bytes is assumed.

With *{\$I-}*, *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

### Differences

In 3.0, an empty file name was invalid.

### See also

*Append, Assign, Close, Rewrite, Truncate*

### Example

```
function FileExists(FileName: string): boolean;
{ Boolean function that returns True if the file exists;
  otherwise, it returns False. Closes the file if it exists. }
var
  f: file;
begin
  {$I-}
  Assign(f, FileName);
  Reset(f);
  Close(f);
  {$I+}
  FileExists := (IOResult = 0) and (FileName <> '');
end; { FileExists }

begin
  if FileExists(ParamStr(1)) then { Get file name from command
                                     line }
    Writeln('File exists')
  else
    Writeln('File not found');
end.
```

---

## RestoreCrtMode procedure

## Graph

### Function

Restores the screen mode to its original state before graphics was initialized.

### Declaration

RestoreCrtMode

<b>Remarks</b>	Restores the original video mode detected by <i>InitGraph</i> . Can be used in conjunction with <i>SetGraphMode</i> to switch back and forth between text and graphics modes.
<b>Restrictions</b>	Must be in graphics mode.  A similar routine exists in Turbo C 2.0.
<b>See also</b>	<i>CloseGraph</i> , <i>DetectGraph</i> , <i>GetGraphMode</i> , <i>InitGraph</i> , <i>SetGraphMode</i>
<b>Example</b>	<pre> <b>uses</b> Graph; <b>var</b>   Gd, Gm: integer;   Mode : integer; <b>begin</b>   Gd := Detect;   InitGraph(Gd, Gm, '');   <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>     Halt(1);   OutText('&lt;ENTER&gt; to leave graphics:');   Readln;   RestoreCrtMode;   Writeln('Now in text mode');   Write('&lt;ENTER&gt; to enter graphics mode:');   Readln;   SetGraphMode(GetGraphMode);   OutTextXY(0, 0, 'Back in graphics mode');   OutTextXY(0, TextHeight('H'), '&lt;ENTER&gt; to quit:');   Readln;   CloseGraph; <b>end.</b> </pre>

---

## Rewrite procedure

---

<b>Function</b>	Creates and opens a new file.
<b>Declaration</b>	<code>Rewrite(<b>var</b> f [ : <b>file</b>; recsize: word ] )</code>
<b>Remarks</b>	<p><i>f</i> is a file variable of any file type, which must have been associated with an external file using <i>Assign</i>. <i>recsize</i> is an optional expression of type <i>word</i>, which can only be specified if <i>f</i> is an untyped file.</p> <p><i>Rewrite</i> creates a new external file with the name assigned to <i>f</i>. If an external file with the same name already exists, it is deleted and a new empty file is</p>

## Rewrite procedure

created in its place. If *f* was already open, *Rewrite* closes and recreates it. The current file position is set to the beginning of the empty file.

If *f* was assigned an empty name, such as *Assign(f, '')*, then after the call to *Rewrite*, *f* will refer to the standard output file (standard handle number 1).

If *f* is a text file, *f* becomes write-only. After a call to *Rewrite*, *Eof(f)* is always True.

If *f* is an untyped file, *recsize* specifies the record size to be used in data transfers. If *recsize* is omitted, a default record size of 128 bytes is assumed.

With *{I-}*, *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

### Differences

In 3.0, an empty file name was invalid.

### See also

*Append, Assign, Reset, Truncate*

### Example

```
var f: text;
begin
  Assign(f, 'NEWFILE.$$$');
  Rewrite(f);
  Writeln(f, 'Just created file with this text in it...');
  Close(f);
end.
```

---

## Rmdir procedure

---

### Function

Removes an empty subdirectory.

### Declaration

*Rmdir*(*s*: **string**)

### Remarks

*s* is a string-type expression. The subdirectory with the path specified by *s* is removed. If the path does not exist, is non-empty, or is the currently logged directory, an I/O error will occur.

With *{I-}*, *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

### See also

*Mkdir, ChDir, GetDir*

### Example

```
begin
  {I-}
  Rmdir(ParamStr(1)); { Get directory name from command line }
```

```

if IOResult <> 0 then
    Writeln('Cannot remove directory')
else
    Writeln('directory removed');
end.

```

---

## Round function

---

<b>Function</b>	Rounds a real-type value to an integer-type value.
<b>Declaration</b>	Round(x: real)
<b>Result type</b>	longint
<b>Remarks</b>	<i>x</i> is a real-type expression. <i>Round</i> returns a longint value that is the value of <i>x</i> rounded to the nearest whole number. If <i>x</i> is exactly halfway between two whole numbers, the result is the number with the greatest absolute magnitude. A run-time error occurs if the rounded value of <i>x</i> is not within the longint range.
<b>Differences</b>	In 3.0, <i>Round</i> returned an integer value.
<b>See also</b>	<i>Int</i> , <i>Trunc</i>

---

## RunError procedure

---

<b>Function</b>	Stops program execution and generates a run-time error.
<b>Declaration</b>	RunError [ ( ErrorCode : word ) ]
<b>Remarks</b>	The <i>RunError</i> procedure corresponds to the <i>Halt</i> procedure except that in addition to stopping the program, it generates a run-time error at the current statement. <i>ErrorCode</i> is the run-time error number (0 if omitted). If the current module is compiled with Debug Information set to On and you're running the program from the IDE, Turbo Pascal automatically takes you to the <i>RunError</i> call, just as if an ordinary run-time error had occurred.
<b>See also</b>	<i>Exit</i> , <i>Halt</i>

## Sector procedure

### Example

```
{IFDEF Debug}  
  if P = nil then RunError(204);  
{ENDIF}
```

---

## Sector procedure

## Graph

---

**Function** Draws and fills an elliptical sector.

**Declaration** Sector(x, y: integer; StAngle, EndAngle,  
XRradius, YRradius: word)

**Remarks** Using (X,Y) as the center point, *XRradius* and *YRradius* specify the horizontal and vertical radii, respectively; *Sector* draws from *StAngle* to *EndAngle*. The sector is outlined using the current color, and filled using the pattern and color defined by *SetFillStyle* or *SetFillPattern*.

A start angle of 0 and an end angle of 360 will draw and fill a complete ellipse. The angles for *Arc*, *Ellipse*, *FillEllipse*, *PieSlice*, and *Sector* are counterclockwise with 0 degrees at 3 o'clock, 90 degrees at 12 o'clock, and so on.

If an error occurs while filling the sector, *GraphResult* will return a value of -6 (*grNoScanMem*).

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *Arc*, *Circle*, *Ellipse*, *FillEllipse*, *GetArcCoords*, *GetAspectRatio*, *PieSlice*, *SetFillStyle*, *SetFillPattern*, *SetGraphBufSize*

### Example

```
uses  
  Graph;  
const  
  R = 50;  
var  
  Driver, Mode : integer;  
  Xasp, Yasp : word;  
begin  
  Driver := Detect; { Put in graphics mode }  
  InitGraph(Driver, Mode, '');  
  if GraphResult < 0 then  
    Halt(1);  
  Sector(GetMaxX div 2, GetMaxY div 2, 0, 45, R, R);  
  GetAspectRatio(Xasp, Yasp); { Draw circular sector }
```

```

Sector(GetMaxX div 2, GetMaxY div 2,      { Center point }
      180, 135,                          { Mirror angle above }
      R, R * LongInt(Xasp) div Yasp);    { Circular }
Readln;
Closegraph;
end.

```

---

## Seek procedure

---

<b>Function</b>	Moves the current position of a file to a specified component.
<b>Declaration</b>	Seek( <b>var</b> f; n: longint)
<b>Remarks</b>	<p><i>f</i> is any file variable type except text, and <i>n</i> is an expression of type longint. The current file position of <i>f</i> is moved to component number <i>n</i>. The number of the first component of a file is 0. In order to expand a file, it is possible to seek one component beyond the last component; that is, the statement <i>Seek(f,FileSize(f))</i> moves the current file position to the end of the file.</p> <p>With <i>{I-}</i>, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>
<b>Restrictions</b>	Cannot be used on text files. File must be open.
<b>Differences</b>	In 3.0, <i>n</i> was an integer; <i>LongSeek</i> took a real number value for <i>n</i> .
<b>See also</b>	<i>FilePos</i>

---

## SeekEof function

---

<b>Function</b>	Returns the end-of-file status of a file.
<b>Declaration</b>	SeekEof [ ( <b>var</b> f: text) ]
<b>Result type</b>	boolean
<b>Remarks</b>	<p><i>SeekEof</i> corresponds to <i>Eof</i> except that it skips all blanks, tabs, and end-of-line markers before returning the end-of-file status. This is useful when reading numeric values from a text file.</p>

## SeekEof function

With *{I-}*, *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

**Restrictions** Can only be used on text files. File must be open.

**See also** *Eof, SeekEoln*

---

## SeekEoln function

---

**Function** Returns the end-of-line status of a file.

**Declaration** `SeekEoln [ (var f: text) ]`

**Result type** boolean

**Remarks** *SeekEoln* corresponds to *Eoln* except that it skips all blanks and tabs before returning the end-of-line status. This is useful when reading numeric values from a text file.

With *{I-}*, *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

**Restrictions** Can only be used on text files. File must be open.

**See also** *Eoln, SeekEof*

---

## Seg function

---

**Function** Returns the segment of a specified object.

**Declaration** `Seg (x)`

**Result type** word

**Remarks** *x* is any variable, or a procedure or function identifier. The result, of type word, is the segment part of the address of *x*.

**See also** *Addr, Ofc*

---

## SetActivePage procedure

---

## Graph

---

<b>Function</b>	Set the active page for graphics output.
<b>Declaration</b>	SetActivePage (Page: word)
<b>Remarks</b>	<p>Makes <i>Page</i> the active graphics page. All graphics output will now be directed to <i>Page</i>.</p> <p>Multiple pages are only supported by the EGA (256K), VGA, and Hercules graphics cards. With multiple graphics pages, a program can direct graphics output to an off-screen page, then quickly display the off-screen image by changing the visual page with the <i>SetVisualPage</i> procedure. This technique is especially useful for animation.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>SetVisualPage</i>
<b>Example</b>	<pre> <b>uses</b> Graph; <b>var</b>     Gd, Gm: integer; <b>begin</b>     Gd := Detect;     InitGraph(Gd, Gm, '');     <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>         Halt(1);     <b>if</b> (Gd=HercMono) <b>or</b> (Gd=EGA) <b>or</b>         (Gd=EGA64) <b>or</b> (Gd=VGA) <b>then</b>         <b>begin</b>             SetVisualPage(0);             SetActivePage(1);             Rectangle(10, 20, 30, 40);             SetVisualPage(1);         <b>end</b>     <b>else</b>         OutText('No paging supported.');</pre> <p>Readln; CloseGraph; <b>end.</b></p>



---

## SetAllPalette procedure

## Graph

---

**Function** Changes all palette colors as specified.

**Declaration** SetAllPalette(**var** Palette)

**Remarks** *Palette* is an untyped parameter. The first byte is the length of the palette. The next *n* bytes will replace the current palette colors. Each color may range from -1 to 15. A value of -1 will not change the previous entry's value.

Note that valid colors depend on the current graphics driver and current graphics mode.

If invalid input is passed to *SetAllPalette*, *GraphResult* will return a value of -11 (*grError*), and no changes to the palette settings will occur.

Changes made to the palette are seen immediately on the screen. In the example listed here, several lines are drawn on the screen, then the palette is changed. Each time a palette color is changed, all occurrences of that color on the screen will be changed to the new color value.

The following types and constants are defined:

```
const
  Black      = 0;
  Blue       = 1;
  Green      = 2;
  Cyan       = 3;
  Red        = 4;
  Magenta    = 5;
  Brown      = 6;
  LightGray  = 7;
  DarkGray   = 8;
  LightBlue  = 9;
  LightGreen = 10;
  LightCyan  = 11;
  LightRed   = 12;
  LightMagenta = 13;
  Yellow     = 14;
  White      = 15;
  MaxColors  = 15;
```

```

type
  PaletteType = record
    Size: byte;
    Colors: array[0...MaxColors] of shortint;
  end;

```

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode, and can only be used with EGA, EGA 64, or VGA (not the IBM 8514 or the VGA in 256-color mode).

**See also** *GetBkColor, GetColor, GetPalette, GraphResult, SetBkColor, SetColor, SetPalette, SetRGBPalette*

**Example**

```

uses Graph;
var
  Gd, Gm : integer;
  Palette: PaletteType;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  Line(0, 0, GetMaxX, GetMaxY);
  with Palette do
    begin
      Size      := 4;
      Colors[0] := 5;
      Colors[1] := 3;
      Colors[2] := 1;
      Colors[3] := 2;
      SetAllPalette(Palette);
    end;
  Readln;
  CloseGraph;
end.

```

---

## SetAspectRatio procedure

## Graph

---

<b>Function</b>	Changes the default aspect-ratio correction factor.
<b>Declaration</b>	SetAspectRatio(Xasp, Yasp : word)
<b>Result type</b>	word
<b>Remarks</b>	<i>SetAspectRatio</i> is used to change the default aspect ratio of the current graphics mode. The aspect ratio is used to

## SetAspectRatio procedure

draw round circles. If circles appear elliptical, the monitor is not aligned properly. This can be corrected in the hardware by realigning the monitor, or can be corrected in the software by changing the aspect ratio using *SetAspectRatio*. To read the current aspect ratio from the system, use *GetAspectRatio*.

A similar routine exists in Turbo C 2.0.

### Restrictions

Must be in graphics mode.

### See also

*GetAspectRatio*

### Example

```
uses
  Crt, Graph;
const
  R = 50;
var
  Driver, Mode : integer;
  Xasp, Yasp : word;
begin
  DirectVideo := false;
  Driver := Detect;                      { Put in graphics mode }
  InitGraph(Driver, Mode, '');
  if GraphResult < 0 then
    Halt(1);
  GetAspectRatio(Xasp, Yasp);           { Get default aspect ratio }
  { Adjust for VGA and 8514. They have 1:1 aspect }
  if Xasp = Yasp then
    Yasp := 5 * Xasp;
  { Keep modifying aspect ratio until 1:1 or key is pressed }
  while (Xasp < Yasp) and not KeyPressed do
  begin
    SetAspectRatio(Xasp, Yasp);
    Circle(GetMaxX div 2, GetMaxY div 2, R);
    Inc(Xasp, 20);
  end;
  SetTextJustify(JustifyCenter, JustifyCenter);
  OutTextXY(GetMaxX div 2, GetMaxY div 2, 'Done!');
  Readln;
  CloseGraph;
end.
```

---

## SetBkColor procedure

## Graph

### Function

Sets the current background color using the palette.

### Declaration

SetBkColor(ColorNum: word)

<b>Remarks</b>	<p>Background colors may range from 0 to 15, depending on the current graphics driver and current graphics mode. On a CGA, <i>SetBkColor</i> sets the flood overscan color.</p> <p><i>SetBkColor(N)</i> makes the <i>N</i>th color in the palette the new background color. The only exception is <i>SetBkColor(0)</i>, which always sets the background color to black.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>GetBkColor, GetColor, GetPalette, SetAllPalette, SetColor, SetPalette, SetRGBPalette</i>
<b>Example</b>	<pre> <b>uses</b> Crt, Graph; <b>var</b>     GraphDriver, GraphMode: integer;     Palette: PaletteType; <b>begin</b>     GraphDriver := Detect;     InitGraph(GraphDriver, GraphMode, '');     Randomize;     <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>         Halt(1);     GetPalette(Palette);     <b>repeat</b>         <b>if</b> Palette.Size &lt;&gt; 1 <b>then</b>             SetBkColor(Random(Palette.Size));             LineTo(Random(GetMaxX), Random(GetMaxY));         <b>until</b> KeyPressed;     CloseGraph; <b>end.</b> </pre>

---

## SetCBreak procedure

Dos

---

<b>Function</b>	Sets the state of <i>Ctrl-Break</i> checking in DOS.
<b>Declaration</b>	<code>SetCBreak(Break: boolean)</code>
<b>Remarks</b>	<p><i>SetCBreak</i> sets the state of <i>Ctrl-Break</i> checking in DOS. When off (False), DOS only checks for <i>Ctrl-Break</i> during I/O to console, printer, or communication devices. When on (True), checks are made at every system call.</p>
<b>See also</b>	<i>GetCBreak</i>

---

## SetColor procedure

## Graph

---

<b>Function</b>	Sets the current drawing color using the palette.
<b>Declaration</b>	<code>SetColor(Color: word)</code>
<b>Remarks</b>	<p><i>SetColor(5)</i> makes the fifth color in the palette the current drawing color. Drawing colors may range from 0 to 15, depending on the current graphics driver and current graphics mode.</p> <p><i>GetMaxColor</i> returns the highest valid color for the current driver and mode.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>DrawPoly, GetBkColor, GetColor, GetMaxColor, GetPalette, GraphResult, SetAllPalette, SetBkColor, SetPalette, SetRGBPalette</i>
<b>Example</b>	<pre> <b>uses</b> Crt, Graph; <b>var</b>     GraphDriver, GraphMode: integer; <b>begin</b>     GraphDriver := Detect;     InitGraph(GraphDriver, GraphMode, '');     <b>if</b> GraphResult &lt;&gt; grOk <b>then</b>         Halt(1);     Randomize;     <b>repeat</b>         SetColor(Random(GetMaxColor)+1);         LineTo(Random(GetMaxX), Random(GetMaxY));     <b>until</b> KeyPressed; <b>end.</b> </pre>

---

## SetDate procedure

## Dos

---

<b>Function</b>	Sets the current date in the operating system.
<b>Declaration</b>	<code>SetDate(Year, Month, Day : word)</code>
<b>Remarks</b>	Valid parameter ranges are <i>Year</i> 1980..2099, <i>Month</i> 1..12, and <i>Day</i> 1..31. If the date is invalid, the request is ignored.

See also *GetDate, GetTime, SetTime*

---

## SetFAttr procedure

## Dos

---

<b>Function</b>	Sets the attributes of a file.
<b>Declaration</b>	SetFAttr( <b>var</b> f; Attr: word)
<b>Remarks</b>	<p><i>f</i> must be a file variable (typed, untyped, or text file) that has been assigned but not opened. The attribute value is formed by adding the appropriate attribute masks defined as constants in the <i>Dos</i> unit.</p> <pre> const   ReadOnly  = \$01;   Hidden    = \$02;   SysFile   = \$04;   VolumeID  = \$08;   Directory = \$10;   Archive   = \$20; </pre> <p>Errors are reported in <i>DosError</i>; possible error codes are 3 (Invalid Path) and 5 (File Access Denied).</p>
<b>Restrictions</b>	<i>f</i> cannot be open.
<b>See also</b>	<i>GetFAttr, GetFTime, SetFTime</i>
<b>Example</b>	<pre> uses Dos; var   f: file; begin   Assign(f, 'C:\AUTOEXEC.BAT');   SetFAttr(f, Hidden);           {Uh-oh}   Readln;   SetFAttr(f, Archive);         { Whew!} end. </pre>

---

## SetFillPattern procedure

## Graph

---

<b>Function</b>	Selects a user-defined fill pattern.
<b>Declaration</b>	SetFillPattern(Pattern: FillPatternType; Color: word)

## SetFillPattern procedure

### Remarks

Sets the pattern and color for all filling done by *FillPoly*, *FloodFill*, *Bar*, *Bar3D*, and *PieSlice* to the bit pattern specified in *Pattern* and the color specified by *Color*. If invalid input is passed to *SetFillPattern*, *GraphResult* will return a value of -11 (*grError*), and the current fill settings will be unchanged. *FillPatternType* is predefined as follows:

**type**

*FillPatternType* = **array**[1..8] of byte;

The fill pattern is based on the underlying byte values contained in the *Pattern* array. The pattern array is 8 bytes long with each byte corresponding to 8 pixels in the pattern. Whenever a bit in a pattern byte is valued at 1, a pixel will be plotted. For example, the following pattern represents a checkerboard (50 % gray scale):

Binary	Hex
10101010	= \$AA (1st byte)
01010101	= \$55 (2nd byte)
10101010	= \$AA (3rd byte)
01010101	= \$55 (4th byte)
10101010	= \$AA (5th byte)
01010101	= \$55 (6th byte)
10101010	= \$AA (7th byte)
01010101	= \$55 (8th byte)

User-defined fill patterns enable you to create patterns different from the predefined fill patterns that can be selected with the *SetFillStyle* procedure. Whenever you select a new fill pattern with *SetFillPattern* or *SetFillStyle*, all fill operations will use that fill pattern. Calling *SetFillStyle* (*UserField*, *SomeColor*) will always select the user-defined pattern. This lets you define and use a new pattern using *SetFillPattern*, then switch between your pattern and the built-ins by making calls to *SetTextStyle*.

A similar routine exists in Turbo C 2.0.

### Restrictions

Must be in graphics mode.

### See also

*Bar*, *Bar3D*, *FillPoly*, *GetFillPattern*, *GetFillSettings*, *GraphResult*, *PieSlice*

## Example

```

uses Graph;
const
  Gray50: FillPatternType = ($AA,$55,$AA,$55,
                             $AA,$55,$AA,$55);
var
  Gd, Gm: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  SetFillPattern(Gray50, White);
  Bar(0, 0, 100, 100);    { Draw a bar in a 50% gray scale }
  Readln;
  CloseGraph;
end.

```

---

SetFillStyle procedure

---

Graph

<b>Function</b>	Sets the fill pattern and color.
<b>Declaration</b>	SetFillStyle(Pattern: word; Color: word)
<b>Remarks</b>	Sets the pattern and color for all filling done by <i>FillPoly</i> , <i>Bar</i> , <i>Bar3D</i> , and <i>PieSlice</i> . A variety of fill patterns are available. The default pattern is solid, and the default color is the maximum color in the palette. If invalid input is passed to <i>SetFillStyle</i> , <i>GraphResult</i> will return a value of -11 ( <i>grError</i> ), and the current fill settings will be unchanged. The following constants are defined:

```

const
  { Fill patterns for Get/SetFillStyle: }
  EmptyFill      = 0;    { Fills area in background color }
  SolidFill      = 1;    { Fills area in solid fill color }
  LineFill       = 2;    { --- fill }
  LtSlashFill    = 3;    { /// fill }
  SlashFill      = 4;    { /// fill with thick lines }
  BkSlashFill    = 5;    { \\\ fill with thick lines }
  LtBkSlashFill  = 6;    { \\\ fill }
  HatchFill      = 7;    { Light hatch fill }
  XHatchFill     = 8;    { Heavy cross hatch fill }
  InterleaveFill = 9;    { Interleaving line fill }
  WideDotFill    = 10;   { Widely spaced dot fill }
  CloseDotFill   = 11;   { Closely spaced dot fill }
  UserFill       = 12;   { User-defined fill }

```



## SetFillStyle procedure

If *Pattern* equals *UserFill*, the user-defined pattern (set by a call to *SetFillPattern*) becomes the active pattern.

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *Bar, Bar3D, FillPoly, GetFillSettings, PieSlice, GetMaxColor, GraphResult*

**Example**

```
uses Graph;
var
  Gm, Gd : integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  SetFillStyle(SolidFill,0);
  Bar(0, 0, 50, 50);
  SetFillStyle(XHatchFill,1);
  Bar(60, 0, 110, 50);
  Readln;
  CloseGraph;
end.
```

---

## SetFTime procedure

Dos

---

**Function** Sets the date and time a file was last written.

**Declaration** SetFTime(**var** f; Time: longint)

**Remarks** *f* must be a file variable (typed, untyped, or text file) that has been assigned and opened. The *Time* parameter can be created through a call to *PackTime*. Errors are reported in *DosError*; the only possible error code is 6 (Invalid File Handle).

**Restrictions** *f* must be open.

**See also** *GetFTime, PackTime, SetFAttr, UnpackTime*

---

## SetGraphBufSize procedure

Graph

---

**Function** Allows you to change the size of the buffer used for scan and flood fills.

**Declaration** SetGraphBufSize(BufSize: word);

<b>Remarks</b>	<p>The internal buffer size is set to <i>BufSize</i>, and a buffer is allocated on the heap when a call is made to <i>InitGraph</i>.</p> <p>The default buffer size is 4K, which is large enough to fill a polygon with about 650 vertices. Under rare circumstances, enlarging the buffer may be necessary in order to avoid a buffer overflow.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Note that once a call to <i>InitGraph</i> has been made, calls to <i>SetGraphBufSize</i> are ignored.
<b>See also</b>	<i>FloodFill</i> , <i>FillPoly</i> , <i>InitGraph</i>

---

## SetGraphMode procedure

## Graph

<b>Function</b>	Sets the system to graphics mode and clears the screen.
<b>Declaration</b>	<code>SetGraphMode (Mode: integer)</code>
<b>Remarks</b>	<p><i>Mode</i> must be a valid mode for the current device driver. <i>SetGraphMode</i> is used to select a graphics mode different than the default one set by <i>InitGraph</i>.</p> <p><i>SetGraphMode</i> can also be used in conjunction with <i>RestoreCrtMode</i> to switch back and forth between text and graphics modes.</p> <p><i>SetGraphMode</i> resets all graphics settings to their defaults (current pointer, palette, color, viewport, and so forth).</p> <p><i>GetModeRange</i> returns the lowest and highest valid modes for the current driver.</p> <p>If an attempt is made to select an invalid mode for the current device driver, <i>GraphResult</i> will return a value of <code>-10</code> (<i>grInvalidMode</i>).</p>

## SetGraphMode procedure

The following constants are defined:

Graphics Driver	Graphics Modes	Value	Column x Row	Palette	Pages
CGA	CGAC0	0	320x200	C0	1
	CGAC1	1	320x200	C1	1
	CGAC2	2	320x200	C2	1
	CGAC3	3	320x200	C3	1
	CGAHi	4	640x200	2 color	1
MCGA	MCGAC0	0	320x200	C0	1
	MCGAC1	1	320x200	C1	1
	MCGAC2	2	320x200	C2	1
	MCGAC3	3	320x200	C3	1
	MCGAMed	4	640x200	2 color	1
	MCGAHi	5	640x480	2 color	1
EGA	EGALo	0	640x200	16 color	4
	EGAHi	1	640x350	16 color	2
EGA64	EGA64Lo	0	640x200	16 color	1
	EGA64Hi	1	640x350	4 color	1
EGA-MONO	EGAMonoHi	3	640x350	2 color	1*
	EGAMonoHi	3	640x350	2 color	2**
HERC	HercMonoHi	0	720x348	2 color	2
ATT400	ATT400C0	0	320x200	C0	1
	ATT400C1	1	320x200	C1	1
	ATT400C2	2	320x200	C2	1
	ATT400C3	3	320x200	C3	1
	ATT400Med	4	640x200	2 color	1
	ATT400Hi	5	640x400	2 color	1
VGA	VGALo	0	640x200	16 color	2
	VGAMed	1	640x350	16 color	2
	VGAHi	2	640x480	16 color	1
PC3270	PC3270Hi	0	720x350	2 color	1
8514	IBM8514Lo	0	640x480	256 color	1
8514	IBM8514Hi	0	1024x768	256 color	1

\* 64K on EGAMono card

\*\* 256K on EGAMono card

A similar routine exists in Turbo C 2.0.

### Restrictions

A successful call to *InitGraph* must have been made before calling this routine.

**See also** *ClearDevice, CloseGraph, DetectGraph, GetGraphMode, InitGraph, RestoreCrtMode, GraphResult, GetModeRange*

**Example**

```

uses Graph;
var
    GraphDriver: integer;
    GraphMode  : integer;
    LowMode    : integer;
    HighMode   : integer;
begin
    GraphDriver := Detect;
    InitGraph(GraphDriver, GraphMode, '');
    if GraphResult <> grOk then
        Halt(1);
    GetModeRange(GraphDriver, LowMode, HighMode);
    SetGraphMode(LowMode);          { Select low-resolution mode }
    Line(0, 0, GetMaxX, GetMaxY);
    Readln;
    CloseGraph;
end.

```

---

## SetIntVec procedure

## Dos

<b>Function</b>	Sets a specified interrupt vector to a specified address.
<b>Declaration</b>	SetIntVec(IntNo: byte; Vector: pointer)
<b>Remarks</b>	<p><i>IntNo</i> specifies the interrupt vector number (0..255), and <i>Vector</i> specifies the address. <i>Vector</i> is often constructed with the @ operator to produce the address of an interrupt procedure. Assuming <i>Int1BSave</i> is a variable of type pointer, and <i>Int1BHandler</i> is an interrupt procedure identifier, the following statement sequence installs a new interrupt \$1B handler and later restores the original handler:</p>

```

    GetIntVec($1B, Int1BSave);
    SetIntVec($1B, @Int1BHandler);
    :
    :
    SetIntVec($1B, Int1BSave);

```

**See also** *GetIntVec*

# SetLineStyle procedure

## Graph

<b>Function</b>	Sets the current line width and style.
<b>Declaration</b>	SetLineStyle(LineStyle: word; Pattern: word; Thickness: word)
<b>Remarks</b>	Affects all lines drawn by <i>Line</i> , <i>LineTo</i> , <i>Rectangle</i> , <i>DrawPoly</i> , <i>Arc</i> , and so on. Lines can be drawn solid, dotted, centerline, or dashed. If invalid input is passed to <i>SetLineStyle</i> , <i>GraphResult</i> will return a value of -11 ( <i>grError</i> ), and the current line settings will be unchanged. The following constants are declared:

```

const
  SolidLn      = 0;
  DottedLn     = 1;
  CenterLn     = 2;
  DashedLn     = 3;
  UserBitLn    = 4;           { User-defined line style }
  NormWidth    = 1;
  ThickWidth   = 3;

```

*LineStyle* is a value from *SolidLn* to *UserBitLn*(0..4), *Pattern* is ignored unless *LineStyle* equals *UserBitLn*, and *Thickness* is *NormWidth* or *ThickWidth*. When *LineStyle* equals *UserBitLn*, the line is output using the 16-bit pattern defined by the *Pattern* parameter. For example, if *Pattern* = \$AAAA, then the 16-bit pattern looks like this:

```

1010101010101010      { NormWidth }
1010101010101010      { ThickWidth }
1010101010101010
1010101010101010

```

A similar routine exists in Turbo C 2.0.

<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>DrawPoly</i> , <i>GetLineSettings</i> , <i>Line</i> , <i>LineRel</i> , <i>LineTo</i> , <i>GraphResult</i> , <i>SetWriteMode</i>

<b>Example</b>	<pre> uses Graph; var   Gd, Gm: integer;   x1, y1, x2, y2: integer; begin   Gd := Detect;   InitGraph(Gd, Gm, '');   if GraphResult &lt;&gt; grOk then     Halt(1); </pre>
----------------	--

```

x1 := 10;
y1 := 10;
x2 := 200;
y2 := 150;
SetLineStyle(DottedLn, 0, NormWidth);
Rectangle(x1, y1, x2, y2);
SetLineStyle(UserBitLn, $C3, ThickWidth);
Rectangle(Pred(x1), Pred(y1), Succ(x2), Succ(y2));
Readln;
CloseGraph;
end.

```

---

## SetPalette procedure

## Graph

---

<b>Function</b>	Changes one palette color as specified by <i>ColorNum</i> and <i>Color</i> .
<b>Declaration</b>	SetPalette(ColorNum: word; Color: shortint)
<b>Remarks</b>	Changes the <i>ColorNum</i> entry in the palette to <i>Color</i> . <i>SetPalette(0, LightCyan)</i> makes the first color in the palette light cyan. <i>ColorNum</i> may range from 0 to 15, depending on the current graphics driver and current graphics mode. If invalid input is passed to <i>SetPalette</i> , <i>GraphResult</i> will return a value of -11 ( <i>grError</i> ), and the palette will be unchanged.

Changes made to the palette are seen immediately on the screen. In the example here, several lines are drawn on the screen, then the palette is changed randomly. Each time a palette color is changed, all occurrences of that color on the screen will be changed to the new color value.

The following constants are defined:

```

const
  Black      = 0;
  Blue       = 1;
  Green      = 2;
  Cyan       = 3;
  Red        = 4;
  Magenta    = 5;
  Brown      = 6;
  LightGray  = 7;
  DarkGray   = 8;
  LightBlue  = 9;

```

## SetPalette procedure

```
LightGreen  = 10;  
LightCyan   = 11;  
LightRed    = 12;  
LightMagenta = 13;  
Yellow      = 14;  
White       = 15;
```

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode, and can only be used with EGA, EGA 64, or VGA (not the IBM 8514 or the VGA in 256-color mode).

**See also** *GetBkColor, GetColor, GetPalette, GraphResult, SetAllPalette, SetBkColor, SetColor, SetRGBPalette*

**Example**

```
uses Crt, Graph;  
var  
    GraphDriver, GraphMode: integer;  
    Color: word;  
    Palette: PaletteType;  
begin  
    GraphDriver := Detect;  
    InitGraph(GraphDriver, GraphMode, '');  
    if GraphResult <> grOk then  
        Halt(1);  
    GetPalette(Palette);  
    if Palette.Size <> 1 then  
        begin  
            for Color := 0 to Pred(Palette.Size) do  
                begin  
                    SetColor(Color);  
                    Line(0, Color*5, 100, Color*5);  
                end;  
            Randomize;  
            repeat  
                SetPalette(Random(Palette.Size), Random(Palette.Size));  
            until KeyPressed;  
        end  
    else  
        Line(0, 0, 100, 0);  
    Readln;  
    CloseGraph;  
end.
```

## SetRGBPalette procedure

## Graph

<b>Function</b>	<p>Modifies palette entries for the IBM 8514 and VGA drivers.</p>
<b>Declaration</b>	<pre>SetRGBPalette(ColorNum, RedValue,               GreenValue, BlueValue: integer)</pre>
<b>Remarks</b>	<p><i>ColorNum</i> defines the palette entry to be loaded, while <i>RedValue</i>, <i>GreenValue</i>, and <i>BlueValue</i> define the component colors of the palette entry.</p> <p>For the IBM 8514 display, <i>ColorNum</i> is in the range 0..255. For the VGA in 256K color mode, <i>ColorNum</i> is the range 0..15. Only the lower byte of <i>RedValue</i>, <i>GreenValue</i> or <i>BlueValue</i> is used, and out of this byte, only the 6 most-significant bits are loaded in the palette.</p> <p><b>Note:</b> For compatibility with other IBM graphics adapters, the BGI driver defines the first 16 palette entries of the IBM 8514 to the default colors of the EGA/VGA. These values can be used as is, or they can be changed by using <i>SetRGBPalette</i>.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	<p><i>SetRGBPalette</i> can only be used with the IBM 8514 driver and the VGA.</p>
<b>See also</b>	<p><i>GetBkColor</i>, <i>GetColor</i>, <i>GetPalette</i>, <i>GraphResult</i>, <i>SetAllPalette</i>, <i>SetBkColor</i>, <i>SetColor</i>, <i>SetPalette</i></p>
<b>Example</b>	<pre>uses     Graph; type     RGBRec = record         RedVal, GreenVal, BlueVal : integer;     end; const     EGAColors : array[0..MaxColors] of RGBRec =         (             (NAME          COLOR)             (RedVal:\$00;GreenVal:\$00;BlueVal:\$00), (Black      EGA  0)             (RedVal:\$00;GreenVal:\$00;BlueVal:\$FC), (Blue       EGA  1)             (RedVal:\$24;GreenVal:\$FC;BlueVal:\$24), (Green      EGA  2)             (RedVal:\$00;GreenVal:\$FC;BlueVal:\$FC), (Cyan       EGA  3)             (RedVal:\$FC;GreenVal:\$14;BlueVal:\$14), (Red        EGA  4)             (RedVal:\$B0;GreenVal:\$00;BlueVal:\$FC), (Magenta    EGA  5)             (RedVal:\$70;GreenVal:\$48;BlueVal:\$00), (Brown      EGA 20)             (RedVal:\$C4;GreenVal:\$C4;BlueVal:\$C4), (White     EGA  7)             (RedVal:\$34;GreenVal:\$34;BlueVal:\$34), (Gray      EGA 56)</pre>



## SetRGBPalette procedure

```
(RedVal:$00;GreenVal:$00;BlueVal:$70),{Lt Blue   EGA 57}
(RedVal:$00;GreenVal:$70;BlueVal:$00),{Lt Green  EGA 58}
(RedVal:$00;GreenVal:$70;BlueVal:$70),{Lt Cyan   EGA 59}
(RedVal:$70;GreenVal:$00;BlueVal:$00),{Lt Red    EGA 60}
(RedVal:$70;GreenVal:$00;BlueVal:$70),{Lt Magenta EGA 61}
(RedVal:$FC;GreenVal:$fc;BlueVal:$24),{Yellow   EGA 62}
(RedVal:$FC;GreenVal:$fc;BlueVal:$FC) {Br. White EGA 63}
);

var
  Driver, Mode,
  i : integer;
begin
  Driver := IBM8514;                { Override detection }
  Mode := IBM8514Hi;
  InitGraph(Driver, Mode, '');      { Put in graphics mode }
  if GraphResult < 0 then
    Halt(1);
  { Zero palette, make all graphics output invisible }
  for i := 0 to MaxColors do
    with EGAColors[i] do
      SetRGBPalette(i, 0, 0, 0);
  { Display something }
  { Change 1st 16 8514 palette entries }
  for i := 1 to MaxColors do
    begin
      SetColor(i);
      OutTextXY(10, i * 10, ' ..Press any key.. ');
    end;
  { Restore default EGA colors to 8514 palette }
  for i := 0 to MaxColors do
    with EGAColors[i] do
      SetRGBPalette(i, RedVal, GreenVal, BlueVal);
  Readln;
  Closegraph;
end.
```

---

## SetTextBuf procedure

---

<b>Function</b>	Assigns an I/O buffer to a text file.
<b>Declaration</b>	SetTextBuf( <b>var</b> f: text; <b>var</b> buf [ ; size: word ] )
<b>Remarks</b>	<p><i>f</i> is a text-file variable, <i>buf</i> is any variable, and <i>Size</i> is an optional expression of type word.</p> <p>Each text-file variable has an internal 128-byte buffer that, by default, is used to buffer <i>Read</i> and <i>Write</i></p>

operations. This buffer is adequate for most applications. However, heavily I/O-bound programs, such as applications that copy or convert text files, will benefit from a larger buffer, because it reduces disk head movement and file system overhead.

*SetTextBuf* changes the text file *f* to use the buffer specified by *buf* instead of *f*'s internal buffer. *Size* specifies the size of the buffer in bytes. If *Size* is omitted, *SizeOf(buf)* is assumed; that is, by default, the entire memory region occupied by *buf* is used as a buffer. The new buffer remains in effect until *f* is next passed to *Assign*.

### Restrictions

*SetTextBuf* should never be applied to an open file, although it can be called immediately after *Reset*, *Rewrite*, and *Append*. Calling *SetTextBuf* on an open file once I/O operations has taken place can cause loss of data because of the change of buffer.

Turbo Pascal doesn't ensure that the buffer exists for the entire duration of I/O operations on the file. In particular, a common error is to install a local variable as a buffer, and then use the file outside the procedure that declared the buffer.

### Differences

Alternative to 3.0's syntax: **var** f:text[2048].

### Example

```
var
  f : text;
  ch : char;
  buf: array[1..10240] of char;           { 10K buffer }
begin
  { Get file to read from command line }
  Assign(f, ParamStr(1));
  { Bigger buffer for faster reads }
  SetTextBuf(f, buf);
  Reset(f);
  { Dump text file onto screen }
  while not Eof(f) do
    begin
      Read(f, ch);
      Write(ch);
    end;
  end.
```

---

## SetTextJustify procedure

## Graph

---

<b>Function</b>	Sets text justification values used by <i>OutText</i> and <i>OutTextXY</i> .
<b>Declaration</b>	SetTextJustify(Horiz, Vert: word)
<b>Remarks</b>	Text output after a <i>SetTextJustify</i> will be justified around the current pointer in the manner specified. Given the following:

```

    SetTextJustify(CenterText, CenterText);
    OutTextXY(100, 100, 'ABC');

```

The point(100,100) will appear in the middle of the letter B. The default justification settings can be restored by *SetTextJustify(LeftText, TopText)*. If invalid input is passed to *SetTextJustify*, *GraphResult* will return a value of -11 (*grError*), and the current text justification settings will be unchanged.

The following constants are defined:

```

const
  { Horizontal justification }
  LeftText   = 0;
  CenterText = 1;
  RightText  = 2;
  { Vertical justification }
  BottomText = 0;
  CenterText = 1;           { Not declared twice }
  TopText    = 2;

```

A similar routine exists in Turbo C 2.0.

<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>GetTextSettings</i> , <i>GraphResult</i> , <i>OutText</i> , <i>OutTextXY</i> , <i>SetLineStyle</i> , <i>SetUserCharSize</i> , <i>TextHeight</i> , <i>TextWidth</i>

<b>Example</b>	<pre> uses Graph; var   Gd, Gm: integer; begin   Gd := Detect;   InitGraph(Gd, Gm, '');   if GraphResult &lt;&gt; grOk then     Halt(1);   { Center text onscreen }   SetTextJustify(CenterText, CenterText); </pre>
----------------	--

```

OutTextXY(Succ(GetMaxX)
  div 2, Succ(GetMaxY)
  div 2, 'Easily Centered');
Readln;
CloseGraph;
end.

```

---

## SetTextStyle procedure

## Graph

**Function** Sets the current text font, style, and character magnification factor.

**Declaration** SetTextStyle(Font: word; Direction: word; CharSize: word)

**Remarks** Affects all text output by *OutText* and *OutTextXY*. One 8×8 bit-mapped font and several “stroked” fonts are available. Font directions supported are normal (left to right) and vertical (90 degrees to normal text, starts at the bottom and goes up). The size of each character can be magnified using the *CharSize* factor. A *CharSize* value of one will display the 8×8 bit-mapped font in an 8×8 pixel rectangle on the screen, a *CharSize* value equal to 2 will display the 8×8 bit-mapped font in a 16×16 pixel rectangle and so on (up to a limit of 10 times the normal size). Always use *TextHeight* and *TextWidth* to determine the actual dimensions of the text.

The normal size values for text are 1 for the default font and 4 for a stroked font. These are the values that should be passed as the *CharSize* parameter to *SetTextStyle*. *SetUserCharSize* can be used to customize the dimensions of stroked font text.

Normally, stroked fonts are loaded from disk onto the heap when a call is made to *SetTextStyle*. However, you can load the fonts yourself or link them directly to your .EXE file. In either case, use *RegisterBGIfont* to register the font with the *Graph* unit.

When “stroked” fonts are loaded from disk, errors can occur when trying to load them. If an error occurs, *GraphResult* will return one of the following values:

- 8 Font file not found
- 9 Not enough memory to load the font selected
- 11 Graphics error

## SetTextStyle procedure

- 12 Graphics I/O error
- 13 Invalid font file
- 14 Invalid font number

The following type and constants are declared:

```
const
  DefaultFont  = 0;           { 8x8 bit mapped font }
  TriplexFont  = 1;           { "Stroked" fonts }
  SmallFont    = 2;
  SansSerifFont = 3;
  GothicFont   = 4;

  HorizDir     = 0;           { Left to right }
  VertDir      = 1;           { Bottom to top }
```

A similar routine exists in Turbo C 2.0.

### Restrictions

Must be in graphics mode.

### See also

*GetTextSettings, GraphResult, OutText, OutTextXY, RegisterBGIfont, SetTextJustify, SetUserCharSize, TextHeight, TextWidth*

### Example

```
uses Graph;
var
  Gd, Gm : integer;
  Y, Size: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  Y := 0;
  for Size := 1 to 4 do
  begin
    SetTextStyle(DefaultFont, HorizDir, Size);
    OutTextXY(0, Y, 'Size = ' + Chr(Size+48));
    Inc(Y, TextHeight('H') + 1);
  end;
  Readln;
  CloseGraph;
end.
```

---

## SetTime procedure

Dos

### Function

Sets the current time in the operating system.

### Declaration

SetTime(Hour, Minute, Second, Sec100: word)

<b>Remarks</b>	Valid parameter ranges are <i>Hour</i> 0..23, <i>Minute</i> 0..59, <i>Second</i> 0..59, and <i>Sec100</i> (hundredths of seconds) 0-99. If the time is not valid, the request is ignored.
<b>See also</b>	<i>GetDate, GetTime, PackTime, SetDate, UnpackTime</i>

---

## SetUserCharSize procedure

## Graph

<b>Function</b>	Allows the user to vary the character width and height for stroked fonts.
<b>Declaration</b>	<code>SetUserCharSize(MultX, DivX, MultY, DivY: word)</code>
<b>Remarks</b>	<p><i>MultX:DivX</i> is the ratio multiplied by the normal width for the active font; <i>MultY:DivY</i> is the ratio multiplied by the normal height for the active font. In order to make text twice as wide, for example, use a <i>MultX</i> value of 2, and set <i>DivX</i> equal to 1 (<math>2 \text{ div } 1 = 2</math>).</p> <p>You don't have to call <i>SetTextStyle</i> immediately after calling <i>SetUserCharSize</i> to make that character size take effect. Calling <i>SetUserCharSize</i> sets the current character size to the values given.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>SetTextStyle, OutText, OutTextXY, TextHeight, TextWidth</i>
<b>Example</b>	The following program shows how to change the height and width of text:

```

uses Graph;
var
    Driver, Mode : integer;
begin
    Driver := Detect;
    InitGraph(Driver, Mode, '');
    if GraphResult <> grOK then
        Halt(1);
    { Showoff }
    SetTextStyle(TriplexFont, Horizdir, 4);
    OutText('Norm');
    SetUserCharSize(1, 3, 1, 1);
    OutText('Short ');
    SetUserCharSize(3, 1, 1, 1);
    OutText('Wide');

```

## SetVerify procedure

```
    Readln;  
    CloseGraph;  
end.
```

---

## SetVerify procedure

Dos

---

<b>Function</b>	Sets the state of the verify flag in DOS.
<b>Declaration</b>	<code>SetVerify(Verify: boolean)</code>
<b>Remarks</b>	<i>SetVerify</i> sets the state of the verify flag in DOS. When off (False), disk writes are not verified. When on (True), all disk writes are verified to ensure proper writing.
<b>See also</b>	<i>GetVerify</i>

---

---


## SetViewport procedure

Graph

---

<b>Function</b>	Sets the current output viewport or window for graphics output.
<b>Declaration</b>	<code>SetViewport(x1, y1, x2, y2: integer; Clip: boolean)</code>
<b>Remarks</b>	<p>(<i>x1</i>, <i>y1</i>) define the upper left corner of the viewport, and (<i>x2</i>, <i>y2</i>) define the lower right corner (<math>0 \leq x1 &lt; x2</math> and <math>0 \leq y1 &lt; y2</math>). The upper left corner of a viewport is (0,0).</p> <p>The Boolean variable <i>Clip</i> determines whether drawings are clipped at the current viewport boundaries. <i>SetViewport</i>(0, 0, <i>GetMaxX</i>, <i>GetMaxY</i>, <i>True</i>) always sets the viewport to the entire graphics screen. If invalid input is parsed to <i>SetViewport</i>, <i>GraphResult</i> will return -11 (<i>grError</i>), and the current view settings will be unchanged. The following constants are defined:</p> <pre>const     ClipOn  = True;     ClipOff = False;</pre> <p>All graphics commands (for example, <i>GetX</i>, <i>OutText</i>, <i>Rectangle</i>, <i>MoveTo</i>, and so on) are viewport-relative. In the example, note that <i>MoveTo</i> moves the current pointer to (5,5) <i>inside</i> the viewport (the absolute coordinates would be (15,25)).</p>

---



If the Boolean variable *Clip* is set to True when a call to *SetViewport* is made, all drawings will be clipped to the current viewport. Note that the "current pointer" is never clipped. The following will not draw the complete line requested because the line will be clipped to the current viewport:

```
SetViewport(10, 10, 20, 20, ClipOn);
Line(0, 5, 15, 5);
```

The line would start at absolute coordinates (10,15) and terminate at absolute coordinates (25,15) if no clipping was performed. But since clipping was performed, the actual line that would be drawn would start at absolute coordinates (10,15) and terminate at coordinates (20,15).

*InitGraph*, *GraphDefaults*, and *SetGraphMode* all reset the viewport to the entire graphics screen. The current viewport settings are available by calling the procedure *GetViewSettings*, which accepts a parameter of the following global type:

```
type
  ViewPortType = record
    x1, y1, x2, y2: integer;
    Clip: boolean;
  end;
```

*SetViewport* moves the current pointer to (0,0).

A similar routine exists in Turbo C 2.0.

## Restrictions

Must be in graphics mode.

## See also

*ClearViewport*, *GetViewSettings*, *GraphResult*



## SetViewport procedure

### Example

```
uses Graph;
var
  Gd, Gm: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  if (Gd = HercMono)
    or (Gd = EGA) or (Gd = EGA64) or (Gd = VGA) then
    begin
      SetVisualPage(0);
      SetActivePage(1);
      Rectangle(10, 20, 30, 40);
      SetVisualPage(1);
    end
  else
    OutText('No paging supported.');
```

Readln;  
CloseGraph;  
end.

---

## SetVisualPage procedure

## Graph

---

**Function** Sets the visual graphics page number.

**Declaration** SetVisualPage(Page: word)

**Remarks** Makes *Page* the visual graphics page.

Multiple pages are only supported by the EGA (256K), VGA, and Hercules graphics cards. With multiple graphics pages, a program can direct graphics output to an off-screen page, then quickly display the off-screen image by changing the visual page with the *SetVisualPage* procedure. This technique is especially useful for animation.

A similar routine exists in Turbo C 2.0.

**Restrictions** Must be in graphics mode.

**See also** *SetActivePage*

### Example

```
uses Graph;
var
  Gd, Gm: integer;
begin
  Gd := Detect;
```

```

InitGraph(Gd, Gm, '');
if GraphResult <> grOk then
  Halt(1);
if (Gd = HercMono)
  or (Gd = EGA) or (Gd = EGA64) or (Gd = VGA) then
begin
  SetVisualPage(0);
  SetActivePage(1);
  Rectangle(10, 20, 30, 40);
  SetVisualPage(1);
end
else
  OutText('No paging supported.');
```

Readln;  
CloseGraph;  
end.

---

## SetWriteMode procedure

---

## Graph

---

**Function** Sets the writing mode for line drawing.

**Declaration** SetWriteMode(WriteMode : integer)

**Remarks** The following constants are defined:

```

const
  CopyPut = 0;      { MOV }
  XORPut  = 1;      { XOR }
```

Each constant corresponds to a binary operation between each byte in the line and the corresponding bytes on the screen. *CopyPut* uses the assembly language **MOV** instruction, overwriting with the line whatever is on the screen. *XORPut* uses the **XOR** command to combine the line with the screen. Two successive **XOR** commands will erase the line and restore the screen to its original appearance.

**Note:** *SetWriteMode* only affects calls to the following routines: *DrawPoly*, *Line*, *LineRel*, *LineTo*, and *Rectangle*.

A similar routine exists in Turbo C 2.0.

**See also** *Line*, *LineTo*, *PutImage*, *SetLineStyle*

**Example**

```

uses
  Crt, Graph;
var
  Driver, Mode,
```

## SetWriteMode procedure

```
i : integer;
x1, y1, dx, dy : integer;
FillInfo : FillSettingsType;
begin
  DirectVideo := false;           { Turn off screen write }
  Randomize;
  Driver := Detect;               { Put in graphics mode }
  InitGraph(Driver, Mode, '');
  if GraphResult < 0 then
    Halt(1);
    { Fill screen with background pattern }
  GetFillSettings(FillInfo);      { Get current settings }
  SetFillStyle(WideDotFill, FillInfo.Color);
  Bar(0, 0, GetMaxX, GetMaxY);
  dx := GetMaxX div 4;           { Determine rectangle's dimensions }
  dy := GetMaxY div 4;
  SetLineStyle(SolidLn, 0, ThickWidth);
  SetWriteMode(XORput);          { XOR mode for rectangle }
  repeat                          { Draw until a key is pressed }
    x1 := Random(GetMaxX - dx);
    y1 := Random(GetMaxY - dy);
    Rectangle(x1, y1, x1 + dx, y1 + dy);      { Draw it }
    Delay(10);                                { Pause briefly }
    Rectangle(x1, y1, x1 + dx, y1 + dy);      { Erase it }
  until KeyPressed;
  Readln;
  Closegraph;
end.
```

---

## Sin function

---

<b>Function</b>	Returns the sine of the argument.
<b>Declaration</b>	Sin(x: real)
<b>Result type</b>	real
<b>Remarks</b>	<i>x</i> is a real-type expression. The result is the sine of <i>x</i> . <i>x</i> is assumed to represent an angle in radians.
<b>See also</b>	<i>ArcTan</i> , <i>Cos</i>
<b>Example</b>	<pre>var   r: real; begin   r := Sin(Pi); end.</pre>

---

## SizeOf function

---

<b>Function</b>	Returns the number of bytes occupied by the argument.
<b>Declaration</b>	SizeOf(x)
<b>Result type</b>	word
<b>Remarks</b>	<p><i>x</i> is either a variable reference or a type identifier. <i>SizeOf</i> returns the number of bytes of memory occupied by <i>x</i>.</p> <p><i>SizeOf</i> should always be used when passing values to <i>FillChar</i>, <i>Move</i>, <i>GetMem</i>, and so on:</p> <pre>FillChar(s, SizeOf(s), 0); GetMem(p, SizeOf(RecordType));</pre>

**Example**

```

type
  CustRec = record
    Name : string[30];
    Phone : string[14];
  end;

var
  p: ^CustRec;
begin
  GetMem(p, SizeOf(CustRec));
end.
```

---

## Sound procedure

---

Crt

<b>Function</b>	Starts the internal speaker.
<b>Declaration</b>	Sound(Hz: word)
<b>Remarks</b>	<p><i>Hz</i> specifies the frequency of the emitted sound in hertz. The speaker continues until explicitly turned off by a call to <i>NoSound</i>.</p>
<b>See also</b>	<i>NoSound</i>
<b>Example</b>	<pre> uses Crt; begin   Sound(220);   Delay(200);   NoSound; end.</pre> <div style="text-align: right;"> <pre> { Beep } { Pause } { Relief! }</pre> </div>

---

## SPtr function

---

<b>Function</b>	Returns the current value of the SP register.
<b>Declaration</b>	SPtr
<b>Result type</b>	word
<b>Remarks</b>	The result, of type word, is the offset of the stack pointer within the stack segment.
<b>See also</b>	SSeg

---

## Sqr function

---

<b>Function</b>	Returns the square of the argument.
<b>Declaration</b>	Sqr( <i>x</i> )
<b>Result type</b>	Same type as parameter.
<b>Remarks</b>	<i>x</i> is an integer-type or real-type expression. The result, of the same type as <i>x</i> , is the square of <i>x</i> , or $x * x$ .

---

## Sqrt function

---

<b>Function</b>	Returns the square root of the argument.
<b>Declaration</b>	Sqrt( <i>x</i> : real)
<b>Result type</b>	real
<b>Remarks</b>	<i>x</i> is a real-type expression. The result is the square root of <i>x</i> .

---

## SSeg function

---

<b>Function</b>	Returns the current value of the SS register.
<b>Declaration</b>	SSeg
<b>Result type</b>	word

<b>Remarks</b>	The result, of type <i>word</i> , is the segment address of the stack segment.
<b>See also</b>	<i>SPtr</i> , <i>CSeg</i> , <i>DSeg</i>

---

## Str procedure

---

<b>Function</b>	Converts a numeric value to its string representation.
<b>Declaration</b>	<code>Str(x [ : width [ : decimals ] ]); var s: string)</code>
<b>Remarks</b>	<i>x</i> is an integer-type or real-type expression. <i>width</i> and <i>decimals</i> are integer-type expressions. <i>s</i> is a string-type variable. <i>Str</i> converts <i>x</i> to its string representation, according to the <i>width</i> and <i>decimals</i> formatting parameters. The effect is exactly the same as a call to the <i>Write</i> standard procedure with the same parameters, except that the resulting string is stored in <i>s</i> instead of being written to a text file.
<b>See also</b>	<i>Val</i> , <i>Write</i>
<b>Example</b>	<pre> <b>function</b> IntToStr(i: longint): <b>string</b>; { Convert any integer type to a string } <b>var</b>     s: <b>string</b>[11]; <b>begin</b>     Str(i, s);     IntToStr := s; <b>end</b>;  <b>begin</b>     Writeln(IntToStr(-5322)); <b>end</b>. </pre>

---

## Succ function

---

<b>Function</b>	Returns the successor of the argument.
<b>Declaration</b>	<code>Succ(x)</code>
<b>Result type</b>	Same type as parameter.
<b>Remarks</b>	<i>x</i> is an ordinal-type expression. The result, of the same type as <i>x</i> , is the successor of <i>x</i> .

## Swap function

See also *Inc, Pred*

---

## Swap function

---

Function	Swaps the high- and low-order bytes of the argument.
Declaration	<code>Swap(x)</code>
Result type	Same type as parameter.
Remarks	<i>x</i> is an expression of type integer or word.
See also	<i>Hi, Lo</i>
Example	<pre><b>var</b>   x: word; <b>begin</b>   x := Swap(\$1234); { \$3412 } <b>end.</b></pre>

---

## SwapVectors procedure

Dos

---

Function	Swaps interrupt vectors.
Declaration	<code>SwapVectors</code>
Remarks	Swaps the contents of the <i>SaveIntXX</i> pointers in the <i>System</i> unit with the current contents of the interrupt vectors. <i>SwapVectors</i> is typically called just before and just after a call to <i>Exec</i> . This ensures that the <i>Exec</i> 'd process does not use any interrupt handlers installed by the current process and vice versa.
See also	<i>Exec</i>
Example	<pre>{ \$M 8192,0,0} <b>uses</b> Dos; <b>var</b>   Command: <b>string</b>[79]; <b>begin</b>   Write('Enter DOS command: ');   ReadLn(Command);</pre>

```

if Command <> '' then
    Command := '/C ' + Command;
    SwapVectors;
    Exec(GetEnv('COMSPEC'), Command);
    SwapVectors;
if DosError <> 0 then
    Writeln('Could not execute COMMAND.COM');
end.

```

---

## TextBackground procedure

## Crt

---

**Function**               Selects the background color.

**Declaration**           TextBackground(Color: byte);

**Remarks**             *Color* is an integer expression in the range 0..7, corresponding to one of the first eight color constants:

```

const
    Black    = 0;
    Blue     = 1;
    Green    = 2;
    Cyan     = 3;
    Red      = 4;
    Magenta  = 5;
    Brown    = 6;
    LightGray = 7;

```

There is a byte variable in *Crt*—*TextAttr*—that is used to hold the current video attribute. *TextBackground* sets bits 4-6 of *TextAttr* to *Color*.

The background of all characters subsequently written will be in the specified color.

**See also**               *TextColor*, *HighVideo*, *NormVideo*, *LowVideo*

---

## TextColor procedure

## Crt

---

**Function**               Selects the foreground character color.

**Declaration**           TextColor(Color: byte)

**Remarks**             *Color* is an integer expression in the range 0..15, corresponding to one of the color constants defined in *Crt*:



## TextColor procedure

```
const
  Black      = 0;
  Blue       = 1;
  Green      = 2;
  Cyan       = 3;
  Red        = 4;
  Magenta    = 5;
  Brown      = 6;
  LightGray  = 7;
  DarkGray   = 8;
  LightBlue  = 9;
  LightGreen = 10;
  LightCyan  = 11;
  LightRed   = 12;
  LightMagenta = 13;
  Yellow     = 14;
  White      = 15;
```

There is a byte variable in *Crt*—*TextAttr*—that is used to hold the current video attribute. *TextColor* sets bits 0-3 to *Color*. If *Color* is greater than 15, the blink bit (bit 7) is also set; otherwise, it is cleared.

You can make characters blink by adding 128 to the color value. The *Blink* constant is defined for that purpose; in fact, for compatibility with Turbo Pascal 3.0, any *Color* value above 15 causes the characters to blink. The foreground of all characters subsequently written will be in the specified color.

### Differences

In 3.0, *Blink* was equal to 16.

### See also

*TextBackground*, *HighVideo*, *NormVideo*, *LowVideo*

### Example

```
TextColor(Green);           { green characters }
TextColor(LightRed+Blink);   { blinking light-red characters }
TextColor(14);               { yellow characters }
```

---

## TextHeight function

## Graph

### Function

Returns the height of a string in pixels.

### Declaration

`TextHeight (TextString: string)`

### Result type

**word**

### Remarks

Takes the current font size and multiplication factor, and determines the height of *TextString* in pixels. This is

useful for adjusting the spacing between lines, computing viewport heights, sizing a title to make it fit on a graph or in a box, and more.

For example, with the 8×8 bit-mapped font and a multiplication factor of 1 (set by *SetTextStyle*), the string *Turbo* is 8 pixels high.

It is important to use *TextHeight* to compute the height of strings, instead of doing the computation manually. In that way, no source code modifications have to be made when different fonts are selected.

A similar routine exists in Turbo C 2.0.

**Restrictions**

Must be in graphics mode.

**See also**

*OutText*, *OutTextXY*, *SetTextStyle*, *TextWidth*, *SetUserCharSize*

**Example**

```
uses Graph;
var
  Gd, Gm : integer;
  Y, Size: integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  Y := 0;
  for Size := 1 to 5 do
    begin
      SetTextStyle(DefaultFont, HorizDir, Size);
      OutTextXY(0, Y, 'Turbo Graphics');
      Inc(Y, TextHeight('Turbo Graphics'));
    end;
  Readln;
  CloseGraph;
end.
```

---

## TextMode procedure

---

**Crt**

**Function**

Selects a specific text mode.

**Declaration**

TextMode (Mode: word)

**Remarks**

The following constants are defined:

## TextMode procedure

```
const
  BW40 = 0;           { 40x25 B/W on color adapter }
  BW80 = 2;           { 80x25 B/W on color adapter }
  Mono = 7;           { 80x25 B/W on monochrome adapter }
  CO40 = 1;           { 40x25 color on color adapter }
  CO80 = 3;           { 80x25 color on color adapter }
  Font8x8 = 256;      { For EGA/VGA 43 and 50 line }
  C40 = CO40;         { For 3.0 compatibility }
  C80 = CO80;         { For 3.0 compatibility }
```

Other values cause *TextMode* to assume C80.

When *TextMode* is called, the current window is reset to the entire screen, *DirectVideo* is set to True, *CheckSnow* is set to True if a color mode was selected, the current text attribute is reset to normal corresponding to a call to *NormVideo*, and the current video is stored in *LastMode*. In addition, *LastMode* is initialized at program startup to the then-active video mode.

Specifying *TextMode*(*LastMode*) causes the last active text mode to be re-selected. This is useful when you want to return to text mode after using a graphics package, such as *Graph* or *Graph3*.

The following call to *TextMode*:

```
TextMode(c80 + Font8x8)
```

will reset the display into 43 lines and 80 columns on an EGA, or 50 lines and 80 columns on a VGA with a color monitor. *TextMode*(*Lo*(*LastMode*)) always turns off 43- or 50-line mode and resets the display (although it leaves the video mode unchanged); while

```
TextMode(Lo(LastMode) + Font8x8)
```

will keep the video mode the same, but reset the display into 43 or 50 lines.

If your system is in 43- or 50-line mode when you load a Turbo Pascal program, the mode will be preserved by the *Crt* startup code, and the window variable that keeps track of the maximum number of lines on the screen (*WindMax*) will be initialized correctly.

Here's how to write a "well-behaved" program that will restore the video mode to its original state:

```
program Video;
uses Crt;
```

```

var
  OrigMode: integer;
begin
  OrigMode := LastMode;           { Remember original mode }
  ...
  TextMode(OrigMode);
end.

```

Note that *TextMode* does not support graphics modes, and therefore *TextMode(OrigMode)* will only restore those modes supported by *TextMode*.

**Differences** In 3.0, a call to *TextMode* with no parameters is now done by calling *TextMode(LastMode)*.

**See also** *RestoreCrtMode*

## TextWidth function

## Graph

<b>Function</b>	Returns the width of a string in pixels.
<b>Declaration</b>	<code>TextWidth(TextString: <b>string</b>)</code>
<b>Result type</b>	word
<b>Remarks</b>	<p>Takes the string length, current font size, and multiplication factor, and determines the width of <i>TextString</i> in pixels. This is useful for computing view-port widths, sizing a title to make it fit on a graph or in a box, and so on.</p> <p>For example, with the 8×8 bit-mapped font and a multiplication factor of 1 (set by <i>SetTextStyle</i>), the string <i>Turbo</i> is 40 pixels wide.</p> <p>It is important to use <i>TextWidth</i> to compute the width of strings, instead of doing the computation manually. In that way, no source code modifications have to be made when different fonts are selected.</p> <p>A similar routine exists in Turbo C 2.0.</p>
<b>Restrictions</b>	Must be in graphics mode.
<b>See also</b>	<i>OutText</i> , <i>OutTextXY</i> , <i>SetTextStyle</i> , <i>TextHeight</i> , <i>SetUserCharSize</i>
<b>Example</b>	<pre> <b>uses</b> Graph; <b>var</b>   Gd, Gm: integer; </pre>

## TextWidth function

```
Row : integer;
Title : string;
Size : integer;
begin
  Gd := Detect;
  InitGraph(Gd, Gm, '');
  if GraphResult <> grOk then
    Halt(1);
  Row := 0;
  Title := 'Turbo Graphics';
  Size := 1;
  while TextWidth(Title) < GetMaxX do
    begin
      OutTextXY(0, Row, Title);
      Inc(Row, TextHeight('M'));
      Inc(Size);
      SetTextStyle(DefaultFont, HorizDir, Size);
    end;
  Readln;
  CloseGraph;
end.
```

---

## Trunc function

---

<b>Function</b>	Truncates a real-type value to an integer-type value.
<b>Declaration</b>	Trunc(x: real)
<b>Result type</b>	longint
<b>Remarks</b>	<i>x</i> is a real-type expression. <i>Trunc</i> returns a longint value that is the value of <i>x</i> rounded toward zero.
<b>Restrictions</b>	A run-time error occurs if the truncated value of <i>x</i> is not within the longint range.
<b>Differences</b>	In 3.0, the result type was an integer.
<b>See also</b>	<i>Round</i> , <i>Int</i>

---

## Truncate procedure

---

<b>Function</b>	Truncates the file size at the current file position.
<b>Declaration</b>	<code>Truncate(var f)</code>
<b>Remarks</b>	<p><i>f</i> is a file variable of any type. All records past <i>f</i> are deleted and the current file position also becomes end-of-file (<i>Eof(f)</i> is True).</p> <p>If I/O-checking is off, the <i>IOResult</i> function will return a nonzero value if an error occurs.</p>
<b>Restrictions</b>	<i>f</i> must be open. <i>Truncate</i> does not work on text files.
<b>See also</b>	<i>Seek, Reset, Rewrite</i>

---



---

## UnpackTime procedure

---

Dos

<b>Function</b>	Converts a 4-byte, packed date-and-time longint returned by <i>GetFTime</i> , <i>FindFirst</i> , or <i>FindNext</i> into an unpacked <i>DateTime</i> record.
<b>Declaration</b>	<code>UnpackTime(Time: longint; var DT: DateTime)</code>
<b>Remarks</b>	<p><i>DateTime</i> is a record declared in the <i>Dos</i> unit:</p> <pre> DateTime = record     Year, Month, Day, Hour,     Min, Sec: word end;</pre> <p>The fields of the <i>Time</i> record are not range-checked.</p>
<b>See also</b>	<i>PackTime, GetFTime, SetFTime, GetTime, SetTime</i>

---



---

## UpCase function

---

<b>Function</b>	Converts a character to uppercase.
<b>Declaration</b>	<code>UpCase(ch: char)</code>
<b>Result type</b>	<code>char</code>

## Val procedure

**Remarks** *ch* is an expression of type `char`. The result of type `char` is *ch* converted to uppercase. Character values not in the range *a..z* are unaffected.

---

## Val procedure

---

**Function** Converts the string value to its numeric representation.

**Declaration** `Val(s: string; var v; var code: integer)`

**Remarks** *s* is a string-type expression. *v* is an integer-type or real-type variable. *code* is a variable of type `integer`. *s* must be a sequence of characters that form a signed whole number according to the syntax shown in the section "Numbers" in Chapter 1. *Val* converts *s* to its numeric representation and stores the result in *v*. If the string is somehow invalid, the index of the offending character is stored in *code*; otherwise, *code* is set to zero.

*Val* performs range-checking differently depending on the state of `{$R}` and the type of the parameter *v*.

With range-checking on, `{$R+}`, an out-of-range value always generates a run-time error. With range-checking off, `{$R-}`, the values for an out-of-range value vary depending upon the data type of *v*. If *v* is a real or `longint` type, the value of *v* is undefined and *code* returns a nonzero value. For any other numeric type, *code* returns a value of zero, and *v* will contain the results of an overflow calculation (assuming the string value is within the long integer range).

Therefore, you should pass *Val* a `longint` variable and perform range-checking before making an assignment of the returned value:

```

{$R-}
Val('65536', LongIntVar, Code)
if (Code <> 0) or
  (LongIntVar < 0) or (LongIntVar > 65535) then
  ...                                     { Error }
else
  WordVar := LongIntVar;
```

In this example, *LongIntVar* would be set to 65536, and *Code* would equal 0. Because 65536 is out of range for a word variable, an error would be reported.

<b>Restrictions</b>	Trailing spaces must be deleted.
<b>See also</b>	<i>Str</i>
<b>Example</b>	<pre> <b>var</b> i, code: integer; <b>begin</b>     { Get text from command line }     Val(ParamStr(1), i, code);     { Error during conversion to integer? }     <b>if</b> code &lt;&gt; 0 <b>then</b>         Writeln('Error at position: ', code)     <b>else</b>         Writeln('Value = ', i);     <b>end.</b> </pre>

---

## WhereX function

## Crt

<b>Function</b>	Returns the X-coordinate of the current cursor position, relative to the current window.
<b>Declaration</b>	<i>WhereX</i>
<b>Result type</b>	byte
<b>See also</b>	<i>WhereY, GotoXY, Window</i>

---

## WhereY function

## Crt

<b>Function</b>	Returns the Y-coordinate of the current cursor position, relative to the current window.
<b>Declaration</b>	<i>WhereY</i>
<b>Result type</b>	byte
<b>See also</b>	<i>WhereX, GotoXY, Window</i>



---

## Window procedure

---

Crt

<b>Function</b>	Defines a text window on the screen.
<b>Declaration</b>	<code>Window(X1, Y1, X2, Y2: byte)</code>
<b>Remarks</b>	<p>X1 and Y1 are the coordinates of the upper left corner of the window, and X2 and Y2 are the coordinates of the lower right corner. The upper left corner of the screen corresponds to (1,1). The minimum size of a text window is one column by one line. If the coordinates are in any way invalid, the call to <i>Window</i> is ignored.</p> <p>The default window is (1,1,80,25) in 25-line mode, and (1,1,80,43) in 43-line mode, corresponding to the entire screen.</p> <p>All screen coordinates (except the window coordinates themselves) are relative to the current window. For instance, <i>GotoXY</i>(1,1) will always position the cursor in the upper left corner of the current window.</p> <p>Many <i>Crt</i> procedures and functions are window-relative, including <i>ClrEol</i>, <i>ClrScr</i>, <i>DelLine</i>, <i>GotoXY</i>, <i>Incline</i>, <i>WhereX</i>, <i>WhereY</i>, <i>Read</i>, <i>Readln</i>, <i>Write</i>, <i>Writeln</i>.</p> <p><i>WindMin</i> and <i>WindMax</i> store the current window definition (refer to the "WindMin and WindMax" section on page 131).</p> <p>A call to the <i>Window</i> procedure always moves the cursor to (1,1).</p>
<b>See also</b>	<i>ClrEol</i> , <i>ClrScr</i> , <i>DelLine</i> , <i>GotoXY</i> , <i>WhereX</i> , <i>WhereY</i>
<b>Example</b>	<pre> <b>uses</b> Crt; <b>var</b>     x, y: byte; <b>begin</b>     TextBackground(Black);           { Clear screen }     ClrScr;     <b>repeat</b>         x := Succ(Random(80));       { Draw random windows }         y := Succ(Random(25));         Window(x, y, x + Random(10), y + Random(8));         TextBackground(Random(16));  { In random colors }         ClrScr;     <b>until</b> KeyPressed; <b>end.</b> </pre>

---

## Write procedure (text files)

---

<b>Function</b>	Writes one or more values to a text file.
<b>Declaration</b>	<code>Write( [ var f: text; ] v1 [, v2,...,vn ] )</code>
<b>Remarks</b>	<p><i>f</i>, if specified, is a text-file variable. If <i>f</i> is omitted, the standard file variable <i>Output</i> is assumed. Each <i>p</i> is a write parameter. Each write parameter includes an output expression whose value is to be written to the file. A write parameter can also contain the specifications of a field width and a number of decimal places. Each output expression must be of a type char, integer, real, string, packed string, or boolean.</p> <p>A write parameter has the form</p> <pre>OutExpr [ : MinWidth [ : DecPlaces ] ]</pre> <p>where <i>OutExpr</i> is an output expression. <i>MinWidth</i> and <i>DecPlaces</i> are type integer expressions.</p> <p><i>MinWidth</i> specifies the minimum field width, which must be greater than 0. Exactly <i>MinWidth</i> characters are written (using leading blanks if necessary) except when <i>OutExpr</i> has a value that must be represented in more than <i>MinWidth</i> characters. In that case, enough characters are written to represent the value of <i>OutExpr</i>. Likewise, if <i>MinWidth</i> is omitted, then the necessary number of characters are written to represent the value of <i>OutExpr</i>.</p> <p><i>DecPlaces</i> specifies the number of decimal places in a fixed-point representation of a type real value. It can be specified only if <i>OutExpr</i> is of type real, and if <i>MinWidth</i> is also specified. When <i>MinWidth</i> is specified, it must be greater than or equal to 0.</p> <p><b>Write with a type char value:</b> If <i>MinWidth</i> is omitted, the character value of <i>OutExpr</i> is written to the file. Otherwise, <i>MinWidth</i> - 1 blanks followed by the character value of <i>OutExpr</i> is written.</p> <p><b>Write with a type integer value:</b> If <i>MinWidth</i> is omitted, the decimal representation of <i>OutExpr</i> is written to the file with no preceding blanks. If <i>MinWidth</i> is specified and its value is larger than the length of the decimal string, enough blanks are written before the decimal string to make the field width <i>MinWidth</i>.</p>

## Write procedure (text files)

**Write with a type real value:** If *OutExpr* has a type real value, its decimal representation is written to the file. The format of the representation depends on the presence or absence of *DecPlaces*.

If *DecPlaces* is omitted (or if it is present, but has a negative value), a floating-point decimal string is written. If *MinWidth* is also omitted, a default *MinWidth* of 17 is assumed; otherwise, if *MinWidth* is less than 8, it is assumed to be 8. The format of the floating-point string is

[ [ - ] <digit> . <decimals> E [ + | - ] <exponent>

The components of the output string are shown in Table 16.1:

Table 16.1: Components of the Output String

[   - ]	" " or "-", according to the sign of <i>OutExpr</i>
<digit>	Single digit, "0" only if <i>OutExpr</i> is 0
<decimals>	Digit string of <i>MinWidth</i> -7 (but at most 10) digits
E	Uppercase [E] character
[ +   - ]	According to sign of exponent
<exponent>	Two-digit decimal exponent

If *DecPlaces* is present, a fixed-point decimal string is written. If *DecPlaces* is larger than 11, it is assumed to be 11. The format of the fixed-point string follows:

[ <blanks> ] [ - ] <digits> [ . <decimals> ]

The components of the fixed-point string are shown in Table 16.2:

Table 16.2: Components of the Fixed-Point String

[ <blanks> ]	Blanks to satisfy <i>MinWidth</i>
[ - ]	If <i>OutExpr</i> is negative
<digits>	At least one digit, but no leading zeros
[ . <decimals> ]	Decimals if <i>DecPlaces</i> > 0

**Write with a string-type value:** If *MinWidth* is omitted, the string value of *OutExpr* is written to the file with no leading blanks. If *MinWidth* is specified, and its value is

## Write procedure (text files)

larger than the length of *OutExpr*, enough blanks are written before the decimal string to make the field width *MinWidth*.

**Write with a packed string type value:** If *OutExpr* is of packed string type, the effect is the same as writing a string whose length is the number of elements in the packed string type.

**Write with a Boolean value:** If *OutExpr* is of type boolean, the effect is the same as writing the strings True or False, depending on the value of *OutExpr*.

With *{I-}*, *IOResult* will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.

<b>Restrictions</b>	File must be open for output.
<b>Differences</b>	See Appendix A in the <i>User's Guide</i> , "Differences Between Turbo Pascal 3.0, 4.0, and 5.0."
<b>See also</b>	<i>Read</i> , <i>Readln</i> , <i>Writeln</i>

---

## Write procedure (typed files)

---

<b>Function</b>	Writes a variable into a file component.
<b>Declaration</b>	<code>Write(f, v1 [, v2,...,vn ] )</code>
<b>Remarks</b>	<p><i>f</i> is a file variable, and each <i>v</i> is a variable of the same type as the component type of <i>f</i>. For each variable written, the current file position is advanced to the next component. If the current file position is at the end of the file—that is, if <i>Eof(f)</i> is True—the file is expanded.</p> <p>With <i>{I-}</i>, <i>IOResult</i> will return a 0 if the operation was successful; otherwise, it will return a nonzero error code.</p>
<b>See also</b>	<i>Writeln</i>

---

## Writeln procedure

---

<b>Function</b>	Executes the <i>Write</i> procedure, then outputs an end-of-line marker to the file.
<b>Declaration</b>	<code>Writeln( [ var f: text; ] v1 [, v2,...,vn ] )</code>

## **Writeln procedure**

<b>Remarks</b>	<p><i>Writeln</i> procedure is an extension to the <i>Write</i> procedure, as it is defined for text files. After executing the <i>Write</i>, <i>Writeln</i> writes an end-of-line marker (carriage-return/line-feed) to the file.</p> <p><i>Writeln(f)</i> with no parameters writes an end-of-line marker to the file. (<i>Writeln</i> with no parameter list altogether corresponds to <i>Writeln(Output)</i>.)</p>
<b>Restrictions</b>	File must be open for output.
<b>Differences</b>	See Appendix A in the <i>User's Guide</i> , "Differences Between Turbo Pascal 3.0, 4.0, and 5.0."
<b>See also</b>	<i>Write</i>

P

A

R

T

---

**2**

## **Appendices**



## Comparing Turbo Pascal 5.0 with ANSI Pascal

This appendix compares Turbo Pascal to ANSI Pascal as defined by ANSI/IEEE770X3.97-1983 in the book *American National Standard Pascal Computer Programming Language* (ISBN 0-471-88944-X, published by The Institute of Electrical and Electronics Engineers in New York).

### Exceptions to ANSI Pascal Requirements

Turbo Pascal complies with the requirements of ANSI/IEEE770X3.97-1983 with the following exceptions:

- In ANSI Pascal, an identifier can be of any length and all characters are significant. In Turbo Pascal, an identifier can be of any length, but only the first 63 characters are significant.
- In ANSI Pascal, the @ symbol is an alternative for the ^ symbol. In Turbo Pascal, the @ symbol is an operator, which is never treated identically with the ^ symbol.
- In ANSI Pascal, a comment can begin with { and end with \*), or begin with (\* and end with }. In Turbo Pascal, comments must begin and end with the same set of symbols.
- In ANSI Pascal, each possible value of the tag type in a variant part must appear once. In Turbo Pascal, this requirement is not enforced.
- In ANSI Pascal, the component type of a file type cannot be a structured type having a component of a file type. In Turbo Pascal, this requirement is not enforced.



- In ANSI Pascal, a file variable has an associated buffer variable, which is referenced by writing the ^ symbol after the file variable. In Turbo Pascal, a file variable does not have an associated buffer variable, and writing the ^ symbol after a file variable is an error.
- In ANSI Pascal, the statement part of a function must contain at least one assignment to the function identifier. In Turbo Pascal, this requirement is not enforced.
- In ANSI Pascal, a field that is the selector of a variant part cannot be an actual variable parameter. In Turbo Pascal, this requirement is not enforced.
- In ANSI Pascal, a component of a variable of a packed type cannot be an actual variable parameter. In Turbo Pascal, this requirement is not enforced.
- In ANSI Pascal, a procedural or functional parameter is declared by writing a procedure or function heading in the formal parameter list. In Turbo Pascal, the declaration of a procedural or functional parameter is achieved through a procedural or functional type, and uses the same syntax as the declaration of other types of parameters.
- In ANSI Pascal, the standard procedures *Reset* and *Rewrite* do not require pre-initialization of file variables. In Turbo Pascal, file variables must be assigned the name of an external file using the *Assign* procedure before they are passed to *Reset* or *Rewrite*.
- ANSI Pascal defines the standard procedures *Get* and *Put*, which are used to read from and write to files. These procedures are not defined in Turbo Pascal.
- In ANSI Pascal, the syntax *New(p,c1,...,cn)* creates a dynamic variable with a specific active variant. In Turbo Pascal, this syntax is not allowed.
- In ANSI Pascal, the syntax *Dispose(q,k1,...,km)* removes a dynamic variable with a specific active variant. In Turbo Pascal, this syntax is not allowed.
- ANSI Pascal defines the standard procedures *Pack* and *Unpack*, which are used to “pack” and “unpack” packed variables. These procedures are not defined in Turbo Pascal.
- In ANSI Pascal, the term  $i \bmod j$  always computes a positive value, and it is an error if  $j$  is zero or negative. In Turbo Pascal,  $i \bmod j$  is computed as  $i - (i \div j) * j$ , and it is not an error if  $j$  is negative.
- In ANSI Pascal, a *goto* statement within a block can refer to a label in an enclosing block. In Turbo Pascal, this is an error.
- In ANSI Pascal, it is an error if the value of the selector in a *case* statement is not equal to any of the case constants. In Turbo Pascal, this is not an error; instead, the *case* statement is ignored unless it contains an *else* clause.

- In ANSI Pascal, statements that *threaten* the control variable of a *for* statement are not allowed. In Turbo Pascal, this requirement is not enforced.
- In ANSI Pascal, a *Read* from a text file with a char-type variable assigns a blank to the variable if *Eoln* was True before the *Read*. In Turbo Pascal, a carriage return character (ASCII 13) is assigned to the variable in this situation.
- In ANSI Pascal, a *Read* from a text file with an integer-type or real-type variable ceases as soon as the next character in the file is not part of a signed integer or a signed number. In Turbo Pascal, reading ceases when the next character in the file is a blank or a control character (including the end-of-line marker).
- In ANSI Pascal, a *Write* to a text file with a packed string-type value causes the string to be truncated if the specified field width is less than the length of the string. In Turbo Pascal, the string is always written in full, even if it is longer than the specified field width.
- ANSI Pascal defines the standard procedure *Page*, which causes all subsequent output to a specific text file to be written on a new page. This procedure is not defined in Turbo Pascal. However, the typical equivalent of *Page(F)* is *Write(F,Chr(12))*.

**Note:** Turbo Pascal is unable to detect whether a program violates any of the exceptions listed here.

## Extensions to ANSI Pascal

---

The following Turbo Pascal features are extensions to Pascal as specified by ANSI/IEEE770X3.97-1983.

- The following are reserved words in Turbo Pascal:

<b>absolute</b>	<b>interface</b>	<b>string</b>
<b>external</b>	<b>interrupt</b>	<b>unit</b>
<b>implementation</b>	<b>shl</b>	<b>uses</b>
<b>inline</b>	<b>shr</b>	<b>xor</b>

- An identifier can contain underscore characters (`_`).
- Integer constants can be written in hexadecimal notation; such constants are prefixed by a `$`.
- Identifiers can serve as labels.
- String constants are compatible with the Turbo Pascal string types, and can contain control characters and other nonprintable characters.
- Label, constant, type, variable, procedure, and function declarations can occur any number of times in any order in a block.

- Wherever the syntax of ANSI Pascal requires a simple constant, Turbo Pascal allows the use of a constant expression (also known as a computed constant).
- Turbo Pascal implements the additional integer types `shortint`, `longint`, `byte`, and `word`, and the additional real types `single`, `double`, `extended`, and `comp`.
- Turbo Pascal implements string types, which differ from the packed string types defined by ANSI Pascal in that they include a dynamic-length attribute that can vary during execution.
- Turbo Pascal implements procedural and functional types. In addition to procedural and functional parameters, these types make possible the declaration and use of procedural and functional variables.
- The type compatibility rules are extended to make char types and packed string types compatible with string types.
- Variables can be declared at absolute memory addresses using an **absolute** clause.
- A variable reference can contain a call to a pointer-type function, the result of which is then dereferenced to denote a dynamic variable.
- String-type variables can be indexed as arrays to access individual characters in a string.
- The type of a variable reference can be changed to another type through a variable typecast.
- Turbo Pascal implements typed constants, which can be used to declare initialized variables of all types except file types.
- Turbo Pascal implements three new logical operators: **xor**, **shl**, and **shr**.
- The **not**, **and**, **or**, and **xor** operators can be used with integer-type operands to perform bitwise logical operations.
- The **+** operator can be used to concatenate strings.
- The relational operators can be used to compare strings.
- Turbo Pascal implements the **@** operator, which is used to obtain the address of a variable or a procedure or function.
- The type of an expression can be changed to another type through a value typecast.
- The **case** statement allows constant ranges in **case** label lists, and provides an optional **else** part.
- Procedures and functions can be declared with **external**, **inline**, and **interrupt** directives to support assembly language subroutines, inline machine code, and interrupt procedures.
- A variable parameter can be untyped (typeless), in which case any variable reference can serve as the actual parameter.

- Turbo Pascal implements units to facilitate modular programming and separate compilation.
- Turbo Pascal implements the following file-handling procedures and functions, which are not available in ANSI Pascal:

<i>Append</i>	<i>Close</i>	<i>Flush</i>	<i>RmDir</i>
<i>BlockRead</i>	<i>Erase</i>	<i>GetDir</i>	<i>Seek</i>
<i>BlockWrite</i>	<i>FilePos</i>	<i>MkDir</i>	<i>SeekEof</i>
<i>ChDir</i>	<i>FileSize</i>	<i>Rename</i>	<i>SeekEoln</i>

- String-type values can be input and output with the *Read*, *Readln*, *Write*, and *Writeln* standard procedures.
- Turbo Pascal implements the following standard procedures and functions, which are not found in ANSI Pascal:

<i>Addr</i>	<i>GetMem</i>	<i>MemAvail</i>	<i>Release</i>
<i>Concat</i>	<i>Halt</i>	<i>Move</i>	<i>RunError</i>
<i>Copy</i>	<i>Hi</i>	<i>Ofs</i>	<i>SPtr</i>
<i>CSeg</i>	<i>Inc</i>	<i>ParamCount</i>	<i>Seg</i>
<i>DSeg</i>	<i>Insert</i>	<i>ParamStr</i>	<i>SizeOf</i>
<i>Dec</i>	<i>Int</i>	<i>Pi</i>	<i>SSeg</i>
<i>Delete</i>	<i>Length</i>	<i>Pos</i>	<i>Str</i>
<i>Exit</i>	<i>Lo</i>	<i>Ptr</i>	<i>Swap</i>
<i>FillChar</i>	<i>Mark</i>	<i>Random</i>	<i>UpCase</i>
<i>Frac</i>	<i>MaxAvail</i>	<i>Randomize</i>	<i>Val</i>
<i>FreeMem</i>			

- Turbo Pascal implements further standard constants, types, variables, procedures, and functions through standard units.

**Note:** Turbo Pascal is unable to detect whether a program uses any of the extensions listed here.

## Implementation-Dependent Features

---

The effect of using an implementation-dependent feature of Pascal, as defined by ANSI/IEEE770X3.97-1983, is unspecified. Programs should not depend on any specific path being taken in cases where an implementation-dependent feature is being used. Implementation-dependent features include:

- the order of evaluation of index expressions in a variable reference
- the order of evaluation of expressions in a set constructor
- the order of evaluation of operands of a binary operator
- the order of evaluation of actual parameters in a function call
- the order of evaluation of the left and right sides of an assignment

- the order of evaluation of actual parameters in a procedure statement
- the effect of reading a text file to which the procedure *Page* was applied during its creation
- the binding of variables denoted by the program parameters to entities external to the program

## Treatment of Errors

---

This section lists those errors from Appendix D of the ANSI Pascal Standard that are not automatically detected by Turbo Pascal. The numbers referred to here are the numbers used in the ANSI Pascal Standard. Errors 6, 19-22, and 25-31 are not detected because they are not applicable to Turbo Pascal.

2. If *t* is a tag field in a variant part and *f* is a field within the active variant of that variant part, it is an error to alter the value of *t* while a reference to *f* exists. This error is not detected.
3. If *p* is a pointer variable, it is an error to reference *p*<sup>^</sup> if *p* is nil. This error is not detected.
4. If *p* is a pointer variable, it is an error to reference *p*<sup>^</sup> if *p* is undefined. This error is not detected.
5. If *p* is a pointer variable, it is an error to alter the value of *p* while a reference to *p*<sup>^</sup> exists. This error is not detected.
42. The function call *Eoln(f)* is an error if *Eof(f)* is True. In Turbo Pascal this is not an error, and *Eoln(f)* is True when *Eof(f)* is True.
43. It is an error to reference a variable in an expression if the value of that variable is undefined. This error is not detected.
46. A term of the form *i mod j* is an error if *j* is zero or negative. In Turbo Pascal, it is not an error if *j* is negative.
48. It is an error if a function does not assign a result value to the function identifier. This error is not detected.
51. It is an error if the value of the selector in a **case** statement is not equal to any of the case constants. In Turbo Pascal, this is not an error; instead, the **case** statement is ignored unless it contains an **else** clause.

## Compiler Directives

Some of the Turbo Pascal compiler's features are controlled through *compiler directives*. A compiler directive is a comment with a special syntax. Turbo Pascal allows compiler directives wherever comments are allowed.

A compiler directive starts with a \$ as the first character after the opening comment delimiter, and is immediately followed by a name (one or more letters) that designates the particular directive. There are three types of directives:

- **Switch directives.** These directives turn particular compiler features on or off by specifying + or – immediately after the directive name.
- **Parameter directives.** These directives specify parameters that affect the compilation, such as file names and memory sizes.
- **Conditional directives.** These directives control conditional compilation of parts of the source text, based on user-definable conditional symbols.

All directives, except switch directives, must have at least one blank between the directive name and the parameters. Here are some examples of compiler directives:

```
{ $B+ }  
{ $R- Turn off range-checking }  
{ $I TYPES.INC }  
{ $O EdFormat }  
{ $M 65520,8192,655360 }  
{ $DEFINE Debug }  
{ $IFDEF Debug }  
{ $ENDIF }
```

You can put compiler directives directly into your source code. You can also change the default directives for both the command-line compiler

(TPC.EXE) and the IDE (TURBO.EXE). The Options/Compiler menu contains all the compiler directives; any changes you make to the settings there will affect all subsequent compilations (see Chapter 7 of the *User's Guide* for details). When using the command-line compiler, you can specify compiler directives on the command line (for example, `TPC /$R+ MYPROG`), or you can place directives in a configuration file (TPC.CFG—refer to Chapter 8 of the *User's Guide* for information). Compiler directives in the source code always override the default values in both the command-line compiler and the IDE.

## Switch Directives

---

Switch directives are either *global* or *local*. Global directives affect the entire compilation, whereas local directives affect only the part of the compilation that extends from the directive until the next occurrence of the same directive.

Global directives must appear before the declaration part of the program or the unit being compiled, that is, before the first **uses**, **label**, **const**, **type**, **procedure**, **function**, or **begin** keyword. Local directives, on the other hand, can appear anywhere in the program or unit.

Multiple switch directives can be grouped in a single compiler directive comment by separating them with commas; for example,

```
{ $B+, R-, S- }
```

There can be no spaces between the directives in this case.

## Align Data

**Syntax:** { \$A+ } or { \$A- }

**Default:** { \$A+ }

**Type:** Global

Menu equivalent: Options/Compiler/Align Data

This directive switches between byte and word alignment of variables and typed constants. Word alignment has no effect on the 8088 CPU. However, on all 80x86 CPUs, word alignment means faster execution, since word-sized items on even addresses are accessed in one memory cycle, in comparison to two memory cycles for words on odd addresses.

In the { \$A+ } state, all variables and typed constants larger than one byte are aligned on a machine-word boundary (an even-numbered address). If required, unused bytes are inserted between variables to achieve word

alignment. The `{$A+}` directive does not affect byte-sized variables; neither does it affect fields of record structures and elements of arrays. A field in a record will align on word boundary only if the total size of all fields before it is even. Likewise, for every element of an array to align on a word boundary, the size of the elements must be even.

In the `{$A-}` state, no alignment measures are taken. Variables and typed constants are simply placed at the next available address, regardless of their size. If you are recompiling programs using the Turbo Pascal Editor Toolbox, make sure to compile all programs that use the toolbox with `{$A-}`.

**Note:** Regardless of the state of the `$A` directive, each global `var` and `const` declaration section always starts at a word boundary. Likewise, the compiler always attempts to keep the stack pointer (SP) word aligned, by allocating an extra unused byte in a procedure's stack frame if required.

**Also note:** The `$A` compiler directive is equivalent to the `Options/Compiler/Align Data` command in the integrated environment; the command-line compiler equivalent is the `/$A` option.

## Boolean Evaluation

**Syntax:** `{$B+}` or `{$B-}`

**Default:** `{$B-}`

**Type:** Local

**Menu equivalent:** `Options/Compiler/Boolean Evaluation`

Boolean Evaluation switches between the two different models of code generation for the `and` and `or` Boolean operators.

In the `{$B+}` state, the compiler generates code for complete Boolean expression evaluation. This means that every operand of a Boolean expression, built from the `and` and `or` operators, is guaranteed to be evaluated, even when the result of the entire expression is already known.

In the `{$B-}` state, the compiler generates code for short-circuit Boolean expression evaluation, which means that evaluation stops as soon as the result of the entire expression becomes evident.

For further details, refer to the section "Boolean Operators" in Chapter 6, "Expressions."



## Debug Information

**Syntax:** {\$D+} or {\$D-}

**Default:** {\$D+}

**Type:** Global

**Menu equivalent:** Options/Compiler/Debug Information

Debug Information enables or disables the generation of debug information. This information consists of a line-number table for each procedure, which maps object code addresses into source text line numbers.

When Debug Information is turned on for a given program or unit, Turbo Pascal's integrated debugger allows you to single-step and set breakpoints in that module. Furthermore, when a run-time error occurs in a program or unit compiled with {\$D+}, Turbo Pascal can automatically take you to the statement that caused the error with Compile/Find Error.

The Debug/Stand-alone Debugging and Options/Linker/Map File switches produce complete information for a given module only if you've compiled that module in the {\$D+} state.

For units, the debug information is recorded in the .TPU file along with the unit's object code. Debug information increases the size of .TPU files, and takes up additional room when compiling programs that use the unit, but it does not affect the size or speed of the executable program.

The debug information switch is usually used in conjunction with the Local Symbols switch, which enables and disables the generation of local symbol information for debugging.

**Note:** If you want to use the Turbo Debugger to debug your program, set Compile/Destination to Disk and Debug/Stand-alone Debugging to On.

## Emulation

**Syntax:** {\$E+} or {\$E-}

**Default:** {\$E+}

**Type:** Global

**Menu equivalent:** Options/Compiler/Emulation

Emulation enables or disables linking with a run-time library that will emulate the 8087 numeric coprocessor if it is not present.

When you compile a program in the {\$N+,E+} state, Turbo Pascal links with the full 8087 emulator. The resulting .EXE file can be used on any machine,

regardless of whether an 8087 is present. If one is found, Turbo Pascal will use it; otherwise, the run-time library emulates it.

In the `{N+,E-}` state, Turbo Pascal links with a substantially smaller floating-point library, which can only be used if an 8087 is present.

The 8087 emulation switch has no effect if used in a unit; it applies only to the compilation of a program. Furthermore, if the program is compiled in the `{N-}` state, and if all the units used by the program were compiled with `{N-}`, then an 8087 run-time library is not required, and the 8087 emulation switch is ignored.

## Force FAR Calls

**Syntax:** `{F+}` or `{F-}`

**Default:** `{F-}`

**Type:** Local

**Menu equivalent:** Options/Compiler/Force Far Calls

Force Far Calls controls which call model to use for subsequently compiled procedures and functions. Procedures and functions compiled in the `{F+}` state always use the FAR call model. In the `{F-}` state, Turbo Pascal automatically selects the appropriate model: FAR if the procedure or function is declared in the **interface** section of a unit; NEAR otherwise.

The NEAR and FAR call models are described in full in Chapter 15, "Inside Turbo Pascal."

**Note:** For programs that use overlays, we suggest that you place a `{F+}` directive at the beginning of the program and each unit, in order to satisfy the FAR call requirement. For more discussion, refer to Chapter 13, "Overlays." For programs that use procedural variables, all such procedures must use the FAR code model. For more discussion, refer to "Procedural Variables" on page 85.

## Input/Output-Checking

**Syntax:** `{I+}` or `{I-}`

**Default:** `{I+}`

**Type:** Local

**Menu equivalent:** Options/Compiler/I/O-Checking

I/O-checking enables or disables the automatic code generation that checks the result of a call to an I/O procedure. I/O procedures are described in Chapter 10, "Input and Output." If an I/O procedure returns a nonzero I/O result when this switch is on, the program terminates, displaying a run-time error message. When this switch is off, you must check for I/O errors by using the *IOResult* function.

## Local Symbol Information

**Syntax:** {\$L+} or {\$L-}

**Default:** {\$L+}

**Type:** Global

**Menu equivalent:** Options/Compiler/Local Symbols

Local Symbols enables or disables the generation of local symbol information. Local symbol information consists of the names and types of all local variables and constants in a module, that is, the symbols in the module's implementation part, and the symbols within the module's procedures and functions.

When local symbols are on for a given program or unit, Turbo Pascal's integrated debugger allows you to examine and modify the module's local variables. Furthermore, calls to the module's procedures and functions can be examined via the Debug/Call Stack menu.

The Options/Linker/Map File and Debug/Stand-alone Debugging switches produce local symbol information for a given module only if that module was compiled in the {\$L+} state.

For units, the local symbol information is recorded in the .TPU file along with the unit's object code. Local symbol information increases the size of .TPU files, and takes up additional room when compiling programs that use the unit, but it does not affect the size or speed of the executable program.

The Local Symbol information switch is usually used in conjunction with the Debug Information switch, which enables and disables the generation of line-number tables for debugging. Note that the \$L directive is ignored if Debug Information is set to Off {\$D-}.

## Numeric Processing

**Syntax:** {\$N+} or {\$N-}

**Default:** {\$N-}

**Type:** Global

**Menu equivalent:** Options/Compiler/Numeric Processing

Numeric Processing switches between the two different models of floating-point code generation supported by Turbo Pascal. In the `{N-}` state, code is generated to perform all real-type calculations in software by calling run-time library routines. In the `{N+}` state, code is generated to perform all real-type calculations using the 8087 numeric coprocessor.

Note that you can also use the `{E+}` directive to emulate the 8087. This gives you access to the IEEE floating-point types without requiring that you install an 8087 chip.

## Overlay Code Generation

**Syntax:** `{O+}` or `{O-}`

**Default:** `{O-}`

**Type:** Global

**Menu equivalent:** Options/Compiler/Overlays Allowed

The `$O` directive enables or disables overlay code generation. Turbo Pascal allows a unit to be overlaid only if it was compiled with `{O+}`. In this state, the code generator takes special precautions when passing string and set constant parameters from one overlaid procedure or function to another.

The use of `{O+}` in a unit does not force you to overlay that unit. It just instructs Turbo Pascal to ensure that the unit can be overlaid, if so desired. If you develop units that you plan to use in overlaid as well as non-overlaid applications, then compiling them with `{O+}` ensures that you can indeed do both with just one version of the unit.

**Note:** A `{O+}` compiler directive is almost always used in conjunction with a `{F+}` directive to satisfy the overlay manager's FAR call requirement.

For further details on overlay code generation, refer to Chapter 13, "Overlays."

## Range-Checking

**Syntax:** `{R+}` or `{R-}`

**Default:** `{R-}`

**Type:** Local

**Menu equivalent:** Options/Compiler/Range-Checking

Range-Checking enables or disables the generation of range-checking code. In the `{R+}` state, all array and string-indexing expressions are verified as being within the defined bounds, and all assignments to scalar and sub-range variables are checked to be within range. If a range check fails, the program terminates and displays a run-time error message. Enabling range-checking slows down your program and makes it larger. Use this option when debugging, then turn it off once the program is bug-free.

## Stack-Overflow Checking

**Syntax:** `{S+}` or `{S-}`

**Default:** `{S+}`

**Type:** Local

**Menu equivalent:** Options/Compiler/Stack-Checking

Stack-Checking enables or disables the generation of stack-overflow checking code. In the `{S+}` state, the compiler generates code at the beginning of each procedure or function that checks whether there is sufficient stack space for the local variables and other temporary storage. When there is not enough stack space, a call to a procedure or function compiled with `{S+}` causes the program to terminate and display a run-time error message. In the `{S-}` state, such a call is most likely to cause a system crash.

## Var-String Checking

**Syntax:** `{V+}` or `{V-}`

**Default:** `{V+}`

**Type:** Local

**Menu equivalent:** Options/Compiler/Var-String Checking

Var-String Checking controls type-checking on strings passed as variable parameters. In the `{V+}` state, strict type-checking is performed, requiring the formal and actual parameters to be of *identical* string types. In the `{V-}` state, any string type variable is allowed as an actual parameter, even if the declared maximum length is not the same as that of the formal parameter.

# Parameter Directives

---

## Include File

**Syntax:** `{I filename}`

**Type:** Local

**Menu equivalent:** Options/Directories/Include Directories

Include Directories instructs the compiler to include the named file in the compilation. In effect, the file is inserted in the compiled text right after the `{I filename}` directive. The default extension for *filename* is `.PAS`. If *filename* does not specify a directory, then, in addition to searching for the file in the current directory, Turbo Pascal searches in the directories specified in the Options/Directories/Include directories menu (or in the directories specified in the `/I` option on the TPC command line).

You can nest Include files up to 15 levels deep.

There is one restriction to the use of Include files: An Include file cannot be specified in the middle of a statement part. In fact, all statements between the **begin** and **end** of a statement part must reside in the same source file.

## Link Object File

**Syntax:** `{L filename}`

**Type:** Local

**Menu equivalent:** Options/Directories/Object Directories

Object Directories instructs the compiler to link the named file with the program or unit being compiled. The `$L` directive is used to link with code written in assembly language for subprograms declared to be **external**. The named file must be an Intel relocatable object file (`.OBJ` file). The default extension for *filename* is `.OBJ`. If *filename* does not specify a directory, then, in addition to searching for the file in the current directory, Turbo Pascal searches in the directories specified in the Options/Directories/Object Directories menu (or in the directories specified in the `/O` option on the TPC command line).

For further details about linking with assembly language, refer to Chapter 15, "Inside Turbo Pascal."

## Memory Allocation Sizes

**Syntax:** {\$M stacksize,heapmin,heapmax}

**Default:** {\$M 16384,0,655360}

**Type:** Global

**Menu equivalent:** Options/Compiler/Memory Sizes

**Memory Sizes** specifies a program's memory allocation parameters. *stacksize* must be an integer number in the range 1024 to 65520, which specifies the size of the stack segment. *heapmin* must be in the range 0 to 655360, and *heapmax* must be in the range *heapmin* to 655360. *heapmin* and *heapmax* specify the minimum and maximum sizes of the heap, respectively.

The stack segment and the heap are further discussed in Chapter 4, "Variables," and Chapter 15, "Inside Turbo Pascal."

**Note:** The \$M directive has no effect when used in a unit.

## Overlay Unit Name

**Syntax:** {\$O unitname}

**Type:** Local

**Menu equivalent:** none

**Overlay Unit Name** turns a unit into an overlay.

The {\$O *unitname*} directive has no effect if used in a unit; when compiling a program, it specifies which of the units used by the program should be placed in an .OVR file instead of in the .EXE file.

{*\$O unitname*} directives must be placed after the program's **uses** clause. Turbo Pascal reports an error if you attempt to overlay a unit that wasn't compiled in the {O+} state. Any unit named in a {*\$O unitname*} directive must have been compiled with Overlays Allowed set to On in the IDE (the equivalent of the {O+} compiler directive).

For further details on overlays, refer to Chapter 13, "Overlays."

## Conditional Compilation

---

Turbo Pascal's conditional compilation directives allow you to produce different code from the same source text, based on conditional symbols.

There are two basic conditional compilation constructs, which closely resemble Pascal's if statement. The first construct

```
{$IFxxx} ... {$ENDIF}
```

causes the source text between {\$IFxxx} and {\$ENDIF} to be compiled only if the condition specified in {\$IFxxx} is True; if the condition is False, the source text between the two directives is ignored.

The second conditional compilation construct

```
{$IFxxx} ... {$ELSE} ... {$ENDIF}
```

causes either the source text between {\$IFxxx} and {\$ELSE} or the source text between {\$ELSE} and {\$ENDIF} to be compiled, based on the condition specified by the {\$IFxxx}.

Here are some examples of conditional compilation constructs:

```
{$IFDEF Debug}
    Writeln('X = ',X);
{$ENDIF}

{$IFDEF CPU87}
    {$N+}
    type
        real = double;
{$ELSE}
    {$N-}
    type
        single = real;
        double = real;
        extended = real;
        comp = real;
{$ENDIF}
```

You can nest conditional compilation constructs up to 16 levels deep. For every {\$IFxxx}, the corresponding {\$ENDIF} must be found within the same source file—which means there must be an equal number of {\$IFxxx}'s and {\$ENDIF}'s in every source file.

## *Conditional Symbols*

---

Conditional compilation is based on the evaluation of conditional symbols. Conditional symbols are defined and undefined (forgotten) using the directives

```
{$DEFINE name}
{$UNDEF name}
```



You can also use the */D* switch in the command-line compiler (or the menu command **O/C/Conditional Defines** from within the integrated environment).

Conditional symbols are best compared to Boolean variables: They are either True (defined) or False (undefined). The `{$DEFINE}` directive sets a given symbol to True, and the `{$UNDEF}` directive sets it to False.

Conditional symbols follow the exact same rules as Pascal identifiers: They must start with a letter, followed by any combination of letters, digits, and underscores. They can be of any length, but only the first 63 characters are significant.

**Note:** Conditional symbols and Pascal identifiers have no correlation whatsoever. Conditional symbols cannot be referenced in the actual program, and the program's identifiers cannot be referenced in conditional directives. For example, the construct

```
const
  Debug = True;
begin
  {$IFDEF Debug}
    Writeln('Debug is on');
  {$ENDIF}
end;
```

will *not* compile the *Writeln* statement. Likewise, the construct

```
{$DEFINE Debug}
begin
  if Debug then
    Writeln('Debug is on');
end;
```

will result in an unknown identifier error in the **if** statement.

Turbo Pascal defines the following standard conditional symbols:

- |              |  |
|--------------|--|
| <b>VER50</b> | Always defined, indicating that this is version 5.0 of Turbo Pascal. Other versions (starting with 4.0) define their corresponding version symbol; for instance, VER40 for version 4.0, and so on.       |
| <b>MSDOS</b> | Always defined, indicating that the operating system is MS-DOS or PC-DOS. Versions of Turbo Pascal for other operating systems will instead define a symbolic name for that particular operating system. |
| <b>CPU86</b> | Always defined, indicating that the CPU belongs to the 80x86 family of processors. Versions of Turbo Pascal for other CPUs will instead define a symbolic name for that particular CPU.                  |

**CPU87** Defined if an 8087 numeric coprocessor is present at compile time. If the construct

```
{ $IFDEF CPU87 } { $N+ } { $ELSE } { $N- } { $ENDIF }
```

appears at the beginning of a compilation, Turbo Pascal automatically selects the appropriate model of floating-point code generation for that particular computer.

Other conditional symbols can be defined before a compilation using the O/C/Conditional Defines menu, or the /D command-line option if you are using TPC.

## The DEFINE Directive

**Syntax:** { \$DEFINE *name* }

Defines a conditional symbol of *name*. The symbol is recognized for the remainder of the compilation of the current module in which the symbol is declared, or until it appears in an { \$UNDEF *name* } directive. The { \$DEFINE *name* } directive has no effect if *name* is already defined.

## The UNDEF Directive

**Syntax:** { \$UNDEF *name* }

Undefines a previously defined conditional symbol. The symbol is forgotten for the remainder of the compilation or until it reappears in a { \$DEFINE *name* } directive. The { \$UNDEF *name* } directive has no effect if *name* is already undefined.

## The IFDEF Directive

**Syntax:** { \$IFDEF *name* }

Compiles the source text that follows it if *name* is defined.

## The IFNDEF Directive

**Syntax:** { \$IFNDEF *name* }

Compiles the source text that follows it if *name* is not defined.

## The IFOPT Directive

**Syntax:** {`IFOPT switch`}

Compiles the source text that follows it if *switch* is currently in the specified state. *switch* consists of the name of a switch option, followed by a + or a – symbol. For example, the construct

```
{IFOPT N+}  
  type real = extended;  
{ENDIF}
```

will compile the type declaration if the `$N` option is currently active.

## The ELSE Directive

**Syntax:** {`ELSE`}

Switches between compiling and ignoring the source text delimited by the last {`IFxxx`} and the next {`ENDIF`}.

## The ENDIF Directive

**Syntax:** {`ENDIF`}

Ends the conditional compilation initiated by the last {`IFxxx`} directive.

## Reference Materials

This chapter is devoted to certain reference materials, including an ASCII table, keyboard scan codes, and extended codes.

### ASCII Codes

The American Standard Code for Information Interchange (ASCII) is a code that translates alphabetic and numeric characters and symbols and control instructions into 7-bit binary code. Table C.1 shows both printable characters and control characters.

Table C.1: ASCII Table

DEC	HEX	CHAR	DEC	HEX	CHAR	DEC	HEX	CHAR	DEC	HEX	CHAR
0	0		32	20		64	40	@	96	60	'
1	1	☺	33	21	!	65	41	A	97	61	a
2	2	☹	34	22	"	66	42	B	98	62	b
3	3	♥	35	23	#	67	43	C	99	63	c
4	4	♦	36	24	\$	68	44	D	100	64	d
5	5	♣	37	25	%	69	45	E	101	65	e
6	6	♠	38	26	&	70	46	F	102	66	f
7	7	•	39	27	'	71	47	G	103	67	g
8	8	■	40	28	(	72	48	H	104	68	h
9	9	○	41	29	)	73	49	I	105	69	i
10	A	◼	42	2A	*	74	4A	J	106	6A	j
11	B	♂	43	2B	+	75	4B	K	107	6B	k
12	C	♀	44	2C	,	76	4C	L	108	6C	l
13	D	♪	45	2D	-	77	4D	M	109	6D	m
14	E	♫	46	2E	.	78	4E	N	110	6E	n
15	F	♠	47	2F	/	79	4F	O	111	6F	o
16	10	▶	48	30	0	80	50	P	112	70	p
17	11	◀	49	31	1	81	51	Q	113	71	q
18	12	↑	50	32	2	82	52	R	114	72	r
19	13	!!	51	33	3	83	53	S	115	73	s
20	14	¶	52	34	4	84	54	T	116	74	t
21	15	§	53	35	5	85	55	U	117	75	u
22	16	■	54	36	6	86	56	V	118	76	v
23	17	±	55	37	7	87	57	W	119	77	w
24	18	↑	56	38	8	88	58	X	120	78	x
25	19	↓	57	39	9	89	59	Y	121	79	y
26	1A	→	58	3A	:	90	5A	Z	122	7A	z
27	1B	←	59	3B	;	91	5B	[	123	7B	{
28	1C	L	60	3C	<	92	5C	\	124	7C	
29	1D	↔	61	3D	=	93	5D	]	125	7D	}
30	1E	▲	62	3E	>	94	5E	^	126	7E	~
31	1F	▼	63	3F	?	95	5F	_	127	7F	Δ

Table C.1: ASCII Table (continued)

DEC	HEX	CHAR	DEC	HEX	CHAR	DEC	HEX	CHAR	DEC	HEX	CHAR
128	80	Ç	160	A0	á	192	C0	Ł	224	E0	α
129	81	ü	161	A1	í	193	C1	ł	225	E1	β
130	82	é	162	A2	ó	194	C2	ṽ	226	E2	Γ
131	83	â	163	A3	ú	195	C3	ṽ	227	E3	π
132	84	ä	164	A4	ñ	196	C4	—	228	E4	Σ
133	85	à	165	A5	Ñ	197	C5	†	229	E5	σ
134	86	å	166	A6	æ	198	C6	‡	230	E6	μ
135	87	ç	167	A7	ø	199	C7	‡	231	E7	τ
136	88	ê	168	A8	ç	200	C8	Ł	232	E8	Φ
137	89	ë	169	A9	ı	201	C9	ṽ	233	E9	θ
138	8A	è	170	AA	ı	202	CA	Ł	234	EA	Ω
139	8B	ï	171	AB	½	203	CB	ṽ	235	EB	δ
140	8C	î	172	AC	¼	204	CC	ṽ	236	EC	∞
141	8D	ì	173	AD	ı	205	CD	=	237	ED	∅
142	8E	Ä	174	AE	«	206	CE	ṽ	238	EE	€
143	8F	Å	175	AF	»	207	CF	±	239	EF	∩
144	90	É	176	B0	■	208	D0	Ł	240	F0	≡
145	91	æ	177	B1	■	209	D1	ṽ	241	F1	±
146	92	Æ	178	B2	■	210	D2	π	242	F2	≥
147	93	ô	179	B3		211	D3	Ł	243	F3	≤
148	94	ö	180	B4	†	212	D4	Ł	244	F4	∫
149	95	ò	181	B5	‡	213	D5	F	245	F5	∫
150	96	û	182	B6	‡	214	D6	π	246	F6	÷
151	97	ù	183	B7	π	215	D7	ṽ	247	F7	≈
152	98	ÿ	184	B8	ı	216	D8	†	248	F8	°
153	99	Ö	185	B9	ṽ	217	D9	ı	249	F9	•
154	9A	Ü	186	BA		218	DA	ı	250	FA	•
155	9B	φ	187	BB	ı	219	DB	■	251	FB	√
156	9C	£	188	BC	ṽ	220	DC	■	252	FC	n
157	9D	¥	189	BD	Ł	221	DD	■	253	FD	²
158	9E	₣	190	BE	ı	222	DE	■	254	FE	▪
159	9F	f	191	BF	ı	223	DF	■	255	FF	

## Extended Key Codes

Extended key codes are returned by those keys or key combinations that cannot be represented by the standard ASCII codes listed in Table C.1. (See *ReadKey* in Chapter 16 for a description about how to determine if an extended key has been pressed.)

Table C.2 shows the second code and what it means.

Table C.2: Extended Key Codes

Second Code	Meaning
3	NUL (null character)
15	Shift Tab (—<vv)
16-25	Alt-Q/W/E/R/T/Y/U/I/O/P
30-38	Alt-A/S/D/F/G/H/I/J/K/L
44-50	Alt-Z/X/C/V/B/N/M
59-68	Keys F1-F10 (disabled as softkeys)
71	Home
72	Up arrow
73	PgUp
75	Left arrow
77	Right arrow
79	End
80	Down arrow
81	PgDn
82	Ins
83	Del
84-93	F11-F20 (Shift-F1 to Shift-F10)
94-103	F21-F30 (Ctrl-F1 through F10)
104-113	F31-F40 (Alt-F1 through F10)
114	Ctrl-PrtSc
115	Ctrl-Left arrow
116	Ctrl-Right arrow
117	Ctrl-End
118	Ctrl-PgDn
119	Ctrl-Home
120-131	Alt-1/2/3/4/5/6/7/8/9/0/-/=
132	Ctrl-PgUp
133	F11
134	F12
135	Shift-F11
136	Shift-F12
137	Ctrl-F11
138	Ctrl-F12
139	Alt-F11
140	Alt-F12

## Keyboard Scan Codes

Keyboard scan codes are the codes returned from the keys on the IBM PC keyboard, as they are seen by Turbo Pascal. These keys are useful when you're working at the assembly language level. Note that the keyboard scan codes displayed in Table C.3 on page 426 are in hexadecimal values.



Table C.3: Keyboard Scan Codes

Key	Scan Code in Hex	Key	Scan Code in Hex
<i>Esc</i>	01	<i>Left/Right arrow</i>	0F
<i>! 1</i>	02	<i>Q</i>	10
<i>@ 2</i>	03	<i>W</i>	11
<i># 3</i>	04	<i>E</i>	12
<i>\$ 4</i>	05	<i>R</i>	13
<i>% 5</i>	06	<i>T</i>	14
<i>^ 6</i>	07	<i>Y</i>	15
<i>&amp; 7</i>	08	<i>U</i>	16
<i>* 8</i>	09	<i>I</i>	17
<i>( 9</i>	0A	<i>O</i>	18
<i>) 0</i>	0B	<i>P</i>	19
<i>-</i>	0C	<i>{ [</i>	1A
<i>=</i>	0D	<i>} ]</i>	1B
<i>Backspace</i>	0E	<i>Return</i>	1C
<i>Ctrl</i>	1D	<i>\  </i>	2B
<i>A</i>	1E	<i>Z</i>	2C
<i>S</i>	1F	<i>X</i>	2D
<i>D</i>	20	<i>C</i>	2E
<i>F</i>	21	<i>V</i>	2F
<i>G</i>	22	<i>B</i>	30
<i>H</i>	23	<i>N</i>	31
<i>J</i>	24	<i>M</i>	32
<i>K</i>	25	<i>&lt; ,</i>	33
<i>L</i>	26	<i>&gt; .</i>	34
<i>;</i>	27	<i>? /</i>	35
<i>"</i>	28	<i>RightShift</i>	36
<i>~ '</i>	29	<i>PrtSc*</i>	37
<i>LeftShift</i>	2A	<i>Alt</i>	38
<i>SpaceBar</i>	39	<i>7 Home</i>	47
<i>Caps Lock</i>	3A	<i>8 Up arrow</i>	48
<i>F1</i>	3B	<i>9 PgUp</i>	49
<i>F2</i>	3C	<i>Minus sign</i>	4A
<i>F3</i>	3D	<i>4 Left arrow</i>	4B
<i>F4</i>	3E	<i>5</i>	4C
<i>F5</i>	3F	<i>6 Right arrow</i>	4D
<i>F6</i>	40	<i>+</i>	4E
<i>F7</i>	41	<i>1 End</i>	4F
<i>F8</i>	42	<i>2 Down arrow</i>	50
<i>F9</i>	43	<i>3 PgDn</i>	51
<i>F10</i>	44	<i>0 Ins</i>	52
<i>F11</i>	D9	<i>Del</i>	53
<i>F12</i>	DA	<i>Num Lock</i>	45
<i>Scroll Lock</i>	46		

# Error Messages and Codes

## Compiler Error Messages

---

The following lists the possible error messages you can get from the compiler during program development. Whenever possible, the compiler will display additional diagnostic information in the form of an identifier or a file name, for example:

Error 15: File not found (WINDOW.TPU).

When an error is detected, Turbo Pascal (in the integrated environment) automatically loads the source file and places the cursor at the error. The command-line compiler displays the error message and number and the source line, and uses a caret (^) to indicate where the error occurred. Note, however, that some errors are not detected until a little later in the source text. For example, a type mismatch in an assignment statement cannot be detected until the entire expression after the := has been evaluated. In such cases, look for the error to the left of or above the cursor.

### 1 Out of memory.

This error occurs when the compiler has run out of memory. There are a number of possible solutions to this problem:

- If Compile/Destination is set to Memory, set it to Disk in the integrated environment.
- If Options/Linker/Link Buffer in the integrated environment is set to Memory, set it to Disk. Use the /L option to link to disk in the command-line compiler.
- If you are using any memory-resident utilities, such as SideKick and SuperKey, remove them from memory.

- If you are using TURBO.EXE, try using TPC.EXE instead—it takes up less memory.

If none of these suggestions help, your program or unit may simply be too large to compile in the amount of memory available, and you may have to break it into two or more smaller units.

## **2 Identifier expected.**

An identifier was expected at this point. You may be trying to redeclare a reserved word.

## **3 Unknown identifier.**

This identifier has not been declared, or may not be visible within the current scope.

## **4 Duplicate identifier.**

The identifier has already been used within the current block.

## **5 Syntax error.**

An illegal character was found in the source text. You may have forgotten the quotes around a string constant.

## **6 Error in real constant.**

The syntax of real-type constants is defined in Chapter 1, "Tokens and Constants."

## **7 Error in integer constant.**

The syntax of integer-type constants is defined in Chapter 1, "Tokens and Constants." Note that whole real numbers outside the maximum integer range must be followed by a decimal point and a zero; for example, 12345678912.0.

## **8 String constant exceeds line.**

You have most likely forgotten the ending quote in a string constant.

## **9 Too many nested files.**

The compiler allows no more than 15 nested source files. Most likely you have more than four nested Include files.

**10 Unexpected end of file.**

You might have gotten this error message because of one of the following:

- Your source file ends before the final **end** of the main statement part. Most likely, your **begins** and **ends** are unbalanced.
- An Include file ends in the middle of a statement part. Every statement part must be entirely contained in one file.
- You didn't close a comment.

**11 Line too long.**

The maximum line length is 126 characters.

**12 Type identifier expected.**

The identifier does not denote a type as it should.

**13 Too many open files.**

If this error occurs, your CONFIG.SYS file does not include a FILES=xx entry or the entry specifies too few files. Increase the number to some suitable value, for instance, 20.

**14 Invalid file name.**

The file name is invalid or specifies a nonexistent path.

**15 File not found.**

The file could not be found in the current directory or in any of the search directories that apply to this type of file.

**16 Disk full.**

Delete some files or use a new disk.

**17 Invalid compiler directive.**

The compiler directive letter is unknown, one of the compiler directive parameters is invalid, or you are using a global compiler directive when compilation of the body of the program has begun.

**18 Too many files.**

There are too many files involved in the compilation of the program or unit. Try not to use that many files, for instance, by merging Include files or making the file names shorter.

**19 Undefined type in pointer definition.**

The type was referenced in a pointer-type declaration previously, but it was never declared.

**20 Variable identifier expected.**

The identifier does not denote a variable as it should.

**21 Error in type.**

This symbol cannot start a type definition.

**22 Structure too large.**

The maximum allowable size of a structured type is 65520 bytes.

**23 Set base type out of range.**

The base type of a set must be a subrange with bounds in the range 0..255 or an enumerated type with no more than 256 possible values.

**24 File components may not be files.**

file of file constructs are not allowed.

**25 Invalid string length.**

The declared maximum length of a string must be in the range 1..255.

**26 Type mismatch.**

This is due to one of the following:

- incompatible types of the variable and the expression in an assignment statement
- incompatible types of the actual and formal parameter in a call to a procedure or function
- an expression type that is incompatible with index type in array indexing
- incompatible types of operands in an expression

**27 Invalid subrange base type.**

All ordinal types are valid base types.

**28 Lower bound greater than upper bound.**

The declaration of a subrange type specifies a lower bound greater than the upper bound.

**29 Ordinal type expected.**

Real types, string types, structured types, and pointer types are not allowed here.

**30 Integer constant expected.**

**31 Constant expected.**

**32 Integer or real constant expected.**

**33 Type identifier expected.**

The identifier does not denote a type as it should.

**34 Invalid function result type.**

Valid function result types are all simple types, string types, and pointer types.

**35 Label identifier expected.**

The identifier does not denote a label as it should.

**36 BEGIN expected.**

A **begin** is expected here, or there is an error in the block structure of the unit or program.

**37 END expected.**

An **end** is expected here, or there is an error in the block structure of the unit or program.

**38 Integer expression expected.**

The preceding expression must be of an integer type.

**39 Ordinal expression expected.**

The preceding expression must be of an ordinal type.

**40 Boolean expression expected.**

The preceding expression must be of type boolean.

**41 Operand types do not match operator.**

The operator cannot be applied to operands of this type, for example, 'A' div '2'.

**42 Error in expression.**

This symbol cannot participate in an expression in the way it does. You may have forgotten to write an operator between two operands.

**43 Illegal assignment.**

- Files and untyped variables cannot be assigned values.
- A function identifier can only be assigned values within the statement part of the function.

**44 Field identifier expected.**

The identifier does not denote a field in the preceding record variable.

**45 Object file too large.**

Turbo Pascal cannot link in .OBJ files larger than 64K.

**46 Undefined external.**

The **external** procedure or function did not have a matching **PUBLIC** definition in an object file. Make sure you have specified all object files in *{L filename}* directives, and check the spelling of the procedure or function identifier in the .ASM file.

**47 Invalid object file record.**

The .OBJ file contains an invalid object record; make sure the file is in fact an .OBJ file.

#### 48 Code segment too large.

The maximum size of the code of a program or unit is 65520 bytes. If you are compiling a program, move some procedures or functions into a unit. If you are compiling a unit, break it into two or more units.

#### 49 Data segment too large.

The maximum size of a program's data segment is 65520 bytes, including data declared by the used units. If you need more global data than this, declare the larger structures as pointers, and allocate them dynamically using the *New* procedure.

#### 50 DO expected.

The reserved word **do** does not appear where it should.

#### 51 Invalid PUBLIC definition.

- The identifier was made public through a **PUBLIC** directive in assembly language, but it has no matching **external** declaration in the Pascal program or unit.
- Two or more **PUBLIC** directives in assembly language define the same identifier.
- The **.OBJ** file defines **PUBLIC** symbols that do not reside in the **CODE** segment.

#### 52 Invalid EXTRN definition.

- The identifier was referred to through an **EXTRN** directive in assembly language, but it is not declared in the Pascal program or unit, nor in the interface part of any of the used units.
- The identifier denotes an **absolute** variable.
- The identifier denotes an **inline** procedure or function.

#### 53 Too many EXTRN definitions.

Turbo Pascal cannot handle **.OBJ** files with more than 256 **EXTRN** definitions.

#### 54 OF expected.

The reserved word **of** does not appear where it should.



### 55 INTERFACE expected.

The reserved word **interface** does not appear where it should.

### 56 Invalid relocatable reference.

- The .OBJ file contains data and relocatable references in segments other than CODE. For example, you are attempting to declare initialized variables in the DATA segment.
- The .OBJ file contains byte-sized references to relocatable symbols. This error occurs if you use the HIGH and LOW operators with relocatable symbols or if you refer to relocatable symbols in DB directives.
- An operand refers to a relocatable symbol that was not defined in the CODE segment or in the DATA segment.
- An operand refers to an EXTRN procedure or function with an offset, for example, *CALL SortProc+8*.

### 57 THEN expected.

The reserved word **then** does not appear where it should.

### 58 TO or DOWNT0 expected.

The reserved word **to** or **downto** does not appear where it should.

### 59 Undefined forward.

- The procedure or function was declared in the **interface** part of a unit, but its definition never occurred in the **implementation** part.
- The procedure or function was declared with **forward**, but its definition was never found.

### 60 Too many procedures.

Turbo Pascal does not allow more than 512 procedures or functions per module. If you are compiling a program, move some procedures or functions into a unit. If you are compiling a unit, break it into two or more units.

### 61 Invalid typecast.

- The sizes of the variable reference and the destination type differ in a variable typecast.
- You are attempting to typecast an expression where only a variable reference is allowed.

## 62 Division by zero.

The preceding operand attempts to divide by zero.

## 63 Invalid file type.

The file type is not supported by the file-handling procedure; for example, *Readln* with a typed file or *Seek* with a text file.

## 64 Cannot Read or Write variables of this type.

- *Read* and *Readln* can input variables of char, integer, real, and string types.
- *Write* and *Writeln* can output variables of char, integer, real, string, and boolean types.

## 65 Pointer variable expected.

The preceding variable must be of a pointer type.

## 66 String variable expected.

The preceding variable must be of a string type.

## 67 String expression expected.

The preceding expression must be of a string type.

## 68 Circular unit reference.

Two units are not allowed to use each other:

```
unit U1;           unit U2;
uses U2;           uses U1;
...                ...
```

In this example, doing a Make on either unit will generate error 68.

## 69 Unit name mismatch.

The name of the unit found in the .TPU file does not match the name specified in the *uses* clause.

## 70 Unit version mismatch.

One or more of the units used by this unit have been changed since the unit was compiled. Use *Compile/Make* or *Compile/Build* in the integrated environment and */M* or */B* options in the command-line compiler to automatically compile units that need recompilation.

**71 Duplicate unit name.**

You have already named this unit in the **uses** clause.

**72 Unit file format error.**

The .TPU file is somehow invalid; make sure it is in fact a .TPU file.

**73 IMPLEMENTATION expected.**

The reserved word **implementation** does not appear where it should.

**74 Constant and case types do not match.**

The type of the **case** constant is incompatible with the **case** statement's selector expression.

**75 Record variable expected.**

The preceding variable must be of a record type.

**76 Constant out of range.**

You are trying to:

- index an array with an out-of-range constant
- assign an out-of-range constant to a variable
- pass an out-of-range constant as a parameter to a procedure or function

**77 File variable expected.**

The preceding variable must be of a file type.

**78 Pointer expression expected.**

The preceding expression must be of a pointer type.

**79 Integer or real expression expected.**

The preceding expression must be of an integer or a real type.

**80 Label not within current block.**

A **goto** statement cannot reference a label outside the current block.

**81 Label already defined.**

The label already marks a statement.

**82 Undefined label in preceding statement part.**

The label was declared and referenced in the preceding statement part, but it was never defined.

**83 Invalid @ argument.**

Valid arguments are variable references and procedure or function identifiers.

**84 UNIT expected.**

The reserved word `unit` does not appear where it should.

**85 ";" expected.**

A semicolon does not appear where it should.

**86 ":" expected.**

A colon does not appear where it should.

**87 "," expected.**

A comma does not appear where it should.

**88 "(" expected.**

An opening parenthesis does not appear where it should.

**89 ")" expected.**

A closing parenthesis does not appear where it should.

**90 "=" expected.**

An equal sign does not appear where it should.

**91 ":= " expected.**

An assignment operator does not appear where it should.

**92 "[" or "(" expected.**

A left bracket does not appear where it should.

**93 "]" or ")" expected.**

A right bracket does not appear where it should.

**94 "." expected.**

A period does not appear where it should.

**95 ".." expected.**

A subrange does not appear where it should.

**96 Too many variables.**

- The total size of the global variables declared within a program or unit cannot exceed 64K.
- The total size of the local variables declared within a procedure or function cannot exceed 64K.

**97 Invalid FOR control variable.**

The **for** statement control variable must be a simple variable defined in the declaration part of the current subprogram.

**98 Integer variable expected.**

The preceding variable must be of an integer type.

**99 Files are not allowed here.**

A typed constant cannot be of a file type.

**100 String length mismatch.**

The length of the string constant does not match the number of components in the character array.

**101 Invalid ordering of fields.**

The fields of a record-type constant must be written in the order of declaration.

**102 String constant expected.**

A string constant does not appear where it should.

**103 Integer or real variable expected.**

The preceding variable must be of an integer or real type.

**104 Ordinal variable expected.**

The preceding variable must be of an ordinal type.

**105 INLINE error.**

The < operator is not allowed in conjunction with relocatable references to variables—such references are always word-sized.

**106 Character expression expected.**

The preceding expression must be of a char type.

**107 Too many relocation items.**

The size of the relocation table part of the .EXE file exceeds 64K, which is Turbo Pascal's upper limit. If you encounter this error, your program is simply too big for Turbo Pascal's linker to handle. It is probably also too big for DOS to execute. You will have to split the program into a "main" part that executes two or more "subprogram" parts using the *Exec* procedure in the *Dos* unit.

**112 CASE constant out of range.**

For integer type *case* statements, the constants must be within the range -32768..32767.

**113 Error in statement.**

This symbol cannot start a statement.

**114 Cannot call an interrupt procedure.**

You cannot directly call an interrupt procedure.

**116 Must be in 8087 mode to compile this.**

This construct can only be compiled in the {\$N+} state. Operations on the 8087 real types, single, double, extended, and comp, are not allowed in the {\$N-} state.

**117 Target address not found.**

The Compile/Find error command in the integrated environment or the /F option in the command-line version could not locate a statement that corresponds to the specified address.

**118 Include files are not allowed here.**

Every statement part must be entirely contained in one file.

**120 NIL expected.**

Typed constants of pointer types may only be initialized to the value `nil`.

**121 Invalid qualifier.**

You are trying to do one of the following:

- index a variable that is not an array
- specify fields in a variable that is not a record
- dereference a variable that is not a pointer

**122 Invalid variable reference.**

The preceding construct follows the syntax of a variable reference, but it does not denote a memory location. Most likely, you are calling a pointer function, but forgetting to dereference the result.

**123 Too many symbols.**

The program or unit declares more than 64K of symbols. If you are compiling with {\$D+}, try turning it off—note, however, that this will prevent you from finding run-time errors in that module. Otherwise, you could try moving some declarations into a separate unit.

**124 Statement part too large.**

Turbo Pascal limits the size of a statement part to about 24K. If you encounter this error, move sections of the statement part into one or more procedures. In any case, with a statement part of that size, it's worth the effort to clarify the structure of your program.

### **126 Files must be var parameters.**

You are attempting to declare a file type value parameter. File type parameters must be var parameters.

### **127 Too many conditional symbols.**

There is not enough room to define further conditional symbols. Try to eliminate some symbols, or shorten some of the symbolic names.

### **128 Misplaced conditional directive.**

The compiler encountered an `{ELSE}` or `{ENDIF}` directive without a matching `{IFDEF}`, `{IFNDEF}`, or `{IFOPT}` directive.

### **129 ENDIF directive missing.**

The source file ended within a conditional compilation construct. There must be an equal number of `{IFxxx}`s and `{ENDIF}`s in a source file.

### **130 Error in initial conditional defines.**

The initial conditional symbols specified in Options/Compiler/Conditional Defines (with the IDE) or in a `/D` directive (with the command-line compiler) are invalid. Turbo Pascal expects zero or more identifiers separated by blanks, commas, or semicolons.

### **131 Header does not match previous definition.**

The procedure or function header specified in the interface part or forward declaration does not match this header.

### **132 Critical disk error.**

A critical error occurred during compilation (for example, drive not ready error).

### **133 Cannot evaluate this expression.**

You are attempting to use a non-supported feature in a constant expression or in a debug expression. For example, you are attempting to use the *Sin* function in a `const` declaration, or you are attempting to call a user-defined function in a debug expression. For a description of the allowed syntax of constant expressions, please refer to Chapter 1, "Tokens and Constants." For a description of the allowed syntax of debug expressions, please refer to Chapter 6 in the *User's Guide*, "Debugging Your Turbo Pascal Programs."



**134 Expression incorrectly terminated.**

Turbo Pascal expects either an operator or the end of the expression at this point, but neither was found.

**135 Invalid format specifier.**

You are using an invalid format specifier, or the numeric argument of a format specifier is out of range. For a list of valid format specifiers, refer to Chapter 6 in the *User's Guide*, "Debugging Your Turbo Pascal Programs"

**136 Invalid indirect reference.**

The statement attempts to make an invalid indirect reference. For example, you are using an **absolute** variable whose base variable is not known in the current module, or you are using an **inline** routine that references a variable not known in the current module.

**137 Structured variables are not allowed here.**

You are attempting to perform a non-supported operation on a structured variable. For example, you are trying to multiply two records.

**138 Cannot evaluate without System unit.**

Your TURBO.TPL library must contain the *System* unit for the debugger to be able to evaluate expressions.

**139 Cannot access this symbol.**

A program's entire set of symbols is available as soon as you have compiled the program. However, certain symbols, such as variables, cannot be accessed until you actually run the program.

**140 Invalid floating-point operation.**

An operation on two real type values produced an overflow or a division by zero.

**141 Cannot compile overlays to memory.**

A program that uses overlays must be compiled to disk.

**142 Procedural or function variable expected.**

In this context, the address operator (@) can only be used with a procedural or function variable.

### 143 Invalid procedure or function reference.

- You are attempting to call a procedure in an expression.
- If you are going to assign a procedure or function to a procedural variable, it must be compiled in the `{F+}` state and cannot be declared with `inline` or `interrupt`.

### 144 Cannot overlay this unit

You are attempting to overlay a unit that wasn't compiled in the `{O+}` state.

### 145 Too many nested scopes.

Your program has too many nested scopes. Each project can have no more than 512 nested scopes with no more than 128 nested scopes in each module. Each unit in a `uses` clause, each nested record type declaration, and each nested `with` context count toward the total number of nested scopes.

## Run-time Errors

---

Certain errors at run time cause the program to display an error message and terminate:

Run-time error *nnn* at *xxxx:yyyy*.

where *nnn* is the run-time error number, and *xxxx:yyyy* is the run-time error address (segment and offset).

The run-time errors are divided into four categories: DOS errors 1-99; I/O errors, 100-149; critical errors, 150-199; and fatal errors, 200-255.

## DOS Errors

---

### 1 Invalid function number.

You made a call to a nonexistent DOS function.

### 2 File not found.

Reported by *Reset*, *Append*, *Rename*, or *Erase* if the name assigned to the file variable does not specify an existing file.

### 3 Path not found.

- Reported by *Reset*, *Rewrite*, *Append*, *Rename*, or *Erase* if the name assigned to the file variable is invalid or specifies a nonexistent subdirectory.
- Reported by *ChDir*, *MkDir*, or *Rmdir* if the path is invalid or specifies a nonexistent subdirectory.

### 4 Too many open files.

Reported by *Reset*, *Rewrite*, or *Append* if the program has too many open files. DOS never allows more than 15 open files per process. If you get this error with less than 15 open files, it may indicate that the CONFIG.SYS file does not include a FILES=xx entry or that the entry specifies too few files. Increase the number to some suitable value, for instance, 20.

### 5 File access denied.

- Reported by *Reset* or *Append* if *FileMode* allows writing and the name assigned to the file variable specifies a directory or a read-only file.
- Reported by *Rewrite* if the directory is full or if the name assigned to the file variable specifies a directory or an existing read-only file.
- Reported by *Rename* if the name assigned to the file variable specifies a directory or if the new name specifies an existing file.
- Reported by *Erase* if the name assigned to the file variable specifies a directory or a read-only file.
- Reported by *Mkdir* if a file with the same name exists in the parent directory, if there is no room in the parent directory, or if the path specifies a device.
- Reported by *Rmdir* if the directory isn't empty, if the path doesn't specify a directory, or if the path specifies the root directory.
- Reported by *Read* or *BlockRead* on a typed or untyped file if the file is not open for reading.
- Reported by *Write* or *BlockWrite* on a typed or untyped file if the file is not open for writing.

### 6 Invalid file handle.

This error is reported if an invalid file handle is passed to a DOS system call. It should never occur; if it does, it is an indication that the file variable is somehow trashed.

## **12 Invalid file access code.**

Reported by *Reset* or *Append* on a typed or untyped file if the value of *FileMode* is invalid.

## **15 Invalid drive number.**

Reported by *GetDir* or *ChDir* if the drive number is invalid.

## **16 Cannot remove current directory.**

Reported by *RmDir* if the path specifies the current directory.

## **17 Cannot rename across drives.**

Reported by *Rename* if both names are not on the same drive.

# ***I/O Errors***

---

These errors cause termination if the particular statement was compiled in the *{I+}* state. In the *{I-}* state, the program continues to execute, and the error is reported by the *IOResult* function.

## **100 Disk read error.**

Reported by *Read* on a typed file if you attempt to read past the end of the file.

## **101 Disk write error.**

Reported by *Close*, *Write*, *Writeln*, *Flush*, or *Page* if the disk becomes full.

## **102 File not assigned.**

Reported by *Reset*, *Rewrite*, *Append*, *Rename*, and *Erase* if the file variable has not been assigned a name through a call to *Assign*.

## **103 File not open.**

Reported by *Close*, *Read*, *Write*, *Seek*, *Eof*, *FilePos*, *FileSize*, *Flush*, *BlockRead*, or *BlockWrite* if the file is not open.

## **104 File not open for input.**

Reported by *Read*, *Readln*, *Eof*, *Eoln*, *SeekEof*, or *SeekEoln* on a text file if the file is not open for input.

**105 File not open for output.**

Reported by *Write* and *Writeln* on a text file if the file is not open for output.

**106 Invalid numeric format.**

Reported by *Read* or *Readln* if a numeric value read from a text file does not conform to the proper numeric format.

## ***Critical Errors***

---

**150 Disk is write-protected.**

**151 Unknown unit.**

**152 Drive not ready.**

**153 Unknown command.**

**154 CRC error in data.**

**155 Bad drive request structure length.**

**156 Disk seek error.**

**157 Unknown media type.**

**158 Sector not found.**

**159 Printer out of paper.**

**160 Device write fault.**

**161 Device read fault.**

**162 Hardware failure.**

Refer to your DOS programmer's reference manual for more information about critical errors.

## ***Fatal Errors***

---

These errors always immediately terminate the program.

### **200 Division by zero.**

The program attempted to divide a number by zero during a `/`, `mod`, or `div` operation.

### **201 Range check error.**

This error is reported by statements compiled in the `{SR+}` state when one of the following situations arises:

- The index expression of an array qualifier was out of range.
- You attempted to assign an out-of-range value to a variable.
- You attempted to assign an out-of-range value as a parameter to a procedure or function.

### **202 Stack overflow error.**

This error is reported on entry to a procedure or function compiled in the `{S+}` state when there is not enough stack space to allocate the sub-program's local variables. Increase the size of the stack by using the `$M` compiler directive.

This error may also be caused by infinite recursion, or by an assembly language procedure that does not maintain the stack project.

### **203 Heap overflow error.**

This error is reported by *New* or *GetMem* when there is not enough free space in the heap to allocate a block of the requested size.

For a complete discussion of the heap manager, refer to Chapter 15, "Inside Turbo Pascal."

### **204 Invalid pointer operation.**

This error is reported by *Dispose* or *FreeMem* if the pointer is `nil` or points to a location outside the heap, or if the free list cannot be expanded due to a full free list or to *HeapPtr* being too close to the bottom of the free list.

### **205 Floating point overflow.**

A floating-point operation produced a number too large for Turbo Pascal or the numeric coprocessor (if any) to handle.

### **206 Floating point underflow**

A floating-point operation produced an underflow. This error is only reported if you are using the 8087 numeric coprocessor with a control word that unmask underflow exceptions. By default, an underflow causes a result of zero to be returned.

### **207 Invalid floating point operation**

- The real value passed to *Trunc* or *Round* could not be converted to an integer within the longint range (-2147483648 to 2147483647).
- The argument passed to the *Sqrt* function was negative.
- The argument passed to the *Ln* function was zero or negative.
- An 8087 stack overflow occurred. For further details on correctly programming the 8087, refer to Chapter 14, "Using the 8087."

### **208 Overlay manager not installed**

Your program is calling an overlaid procedure or function, but the overlay manager is not installed. Most likely, you are not calling *OvrInit*, or the call to *OvrInit* failed. Note that, if you have initialization code in any of your overlaid units, you must create an additional non-overlaid unit which calls *OvrInit*, and use that unit before any of the overlaid units. For a complete description of the overlay manager, refer to Chapter 13, "Overlays."

### **209 Overlay file read error**

A read error occurred when the overlay manager tried to read an overlay from the overlay file.

# Index



\$ *See* compiler, directives  
8087/80287/80387 coprocessor *See*  
    numeric coprocessor  
256-color mode 134  
@ (address-of) operator *See* address-  
    of (@) operator  
^ (pointer) symbol 32, 42  
# (pound) character 14

## A

\$A compiler directive 219, 408  
Abs function 111, 218, 224  
absolute clause 39  
actual parameters 62, 66  
Addr function 112, 224  
address-of (@) operator 32, 42, 61, 90  
    double 90  
    versus ^ (pointer) symbol 401  
    versus Addr 224  
Align Data command 408  
aligning data 408  
and operator 56, 137  
AndPut constant 332  
ANSI Pascal 401  
    errors in 406  
Append procedure 101, 104, 225  
.ARC files 2  
Arc procedure 147, 148, 155, 226  
ArcTan function 111, 226  
arithmetic  
    functions 110  
    operators 54  
array-type constants 47  
arrays 28, 41, 47  
    types 28, 193  
    variables 41  
ASCII codes 421  
.ASM files 178  
aspect ratio 265  
    correction factor, changing 355  
assembly language 199, 415  
    8087 emulation and 178  
    examples 201  
    inline  
        directives 207  
        statements 205  
    interfacing program routines with  
        200

    routines, overlays and 169  
Assign procedure 101, 102, 211, 227  
AssignCrt procedure 132, 211, 228  
assignment statements 66  
automatic  
    call model selection, overriding  
        197  
    word alignment 219  
Aux (version 3.0) 212  
AUXINOUT.PAS 212  
AX register 196, 207

## B

\$B compiler directive 409  
Back procedure 155  
Bar3D procedure 133, 145, 148, 229  
Bar procedure 148, 229  
BGI, Zenith Z-449 and 299  
.BGI files 133  
BINOBJ 3, 340, 342  
BIOS 126, 130  
bit images 137, 276  
bit-mapped fonts 136  
bit-oriented routines 133  
BitBlt  
    operations 137, 332  
    operators 146  
bitwise operators 56  
BlockRead procedure 105, 230  
blocks, program 17  
BlockWrite procedure 105, 232  
Boolean  
    evaluation, compiler switch 409  
    operators 56  
    type 24, 189  
    values 24  
Boolean Evaluation command 409  
BP register 169, 199, 206, 209  
brackets, in expressions 63  
buffers, flushing 261  
BX register 196, 209  
byte data type 23

## C

calling conventions 195  
case statements 69  
CBreak variable 154

- CGA 128, 133
  - CheckSnow and 130
- char data type 24, 189
- characters
  - special 127
  - strings 14
- ChDir procedure 102, 233
- CheckBreak variable 129
- CheckEOF variable 130
- CheckSnow variable 130
- .CHR files 133
- Chr function 110, 218, 233
- Circle procedure 133, 148, 155, 234
- circular unit references 97
- ClearDevice procedure 148, 234
- clearing the overlay buffer 323
- ClearScreen procedure 155
- ClearViewPort procedure 148, 235
- clipping parameters 287
- Close function 212
- Close procedure 102, 210, 236
- CloseGraph procedure 133, 148, 236
- ClrEol procedure 132, 237
- ClrScr procedure 132, 237
- CODE 199
- colors 272, 273
  - background 266
  - drawing 267
- ColorTable procedure 155
- COM devices 107, 212
- command-line compiler 3
- command-line parameters 113, 328
- comments, program 16
- common type 23
- communications, serial 212
- comp floating-point type 173, 191
- comparing values of real types 174
- compilation, conditional 416
- compiler
  - command-line 3
  - directives 16, 407-420
    - \$A 219, 408
    - \$B 409
    - Boolean evaluation 409
    - conditional 407, 416-420
    - \$D 410
    - \$DEFINE 417, 419
    - \$E 172, 410
    - \$ELSE 420
    - \$ENDIF 420
    - \$F 86, 165, 197, 411
    - \$I 102, 119, 306, 411, 415
    - \$IFDEF 419
    - \$IFNDEF 419
    - \$IFOPT 420
    - \$L 199, 412, 415
    - local symbol 412
    - \$M 38, 181, 307, 313, 314, 327, 416
    - \$N 26, 171, 223, 412
    - \$O 164, 413, 416
      - non-overlay units and 168
    - parameter 407, 415-416
    - \$R 413
    - \$S 38, 414
    - switch 407, 408-414
    - \$UNDEF 417, 419
    - \$V 414
  - error messages 427
  - integrated environment 1
- compound statements 67
- CON device 107
- Concat function 112, 238
- concatenation 58
- conditional
  - compilation 416
  - statements 68
  - symbols 417
- CONFIG.SYS 326
- constant expressions 15
  - restrictions 15
  - type definition 26
- constants 120
  - array-type 47
  - Crt mode 128
  - declaration part 18
  - declarations 15
  - defined by Overlay unit 161
  - file attribute 121
  - folding 218
  - Graph3 unit 155
  - Graph unit 142
  - merging 218
  - pointer-type 49
  - record-type 48
  - set-type 48
  - simple 15
  - simple-type 46

- string-type 46
- structured-type 46
- text color 128
- typed 45
- control characters 14, 421
- Copy function 112, 239
- Cos function 111, 239
- CPU symbols 418, 419
- critical errors
  - messages 446
  - trapping 118
- Crt unit 103, 108, 115, 116, 126, 153
  - AssignCrt procedure 228
  - ClrEol procedure 237
  - ClrScr procedure 237
  - constants 128
  - Delay procedure 240
  - DelLine procedure 241
  - functions 132
  - GotoXY procedure 290
  - HighVideo procedure 295
  - InsLine procedure 300
  - KeyPressed function 307
  - line input 127
  - LowVideo procedure 312
  - mode constants 128
  - NormVideo procedure 319
  - NoSound procedure 319
  - procedures 132
  - ReadKey function 337
  - Sound procedure 381
  - special characters 127
  - text color 128
  - TextBackground procedure 385
  - TextColor procedure 385
  - TextMode procedure 387
  - variables 129
  - WhereX function 393
  - WhereY function 393
  - Window procedure 394
- CS register 209, 240
- CSEG 199, 200
- CSeg function 112, 199, 200, 240
- current pointer 135
- cursor position
  - reading 393
  - setting 290
- customizing Turbo Pascal 3
- CX register 209

## D

- \$D compiler directive 410
- DATA 199
- data
  - alignment 408
  - encryption 118
  - ports 208
  - segment 38
  - types *See* types
- date and time procedures 124
  - GetDate 268
  - GetFTime 274
  - GetTime 287
  - SetDate 358
  - SetFTime 362
  - SetTime 374
- DateTime type 122
- dead code removal 220
- Debug Information command 410
- debugging
  - information switch 410
  - overlays 169
  - range-checking switch 413
  - run-time error messages 443
  - stack overflow switch 414
- Dec procedure 111, 240
- decimal notation 13
- declaration part, block 17
- \$DEFINE compiler directive 417, 419
- Delay procedure 132, 240
- Delete procedure 112, 241
- DelLine procedure 132, 241
- DetectGraph procedure 143, 148, 242
- devices 106, 234
  - drivers 210
    - installing 301
  - handlers 153, 209, 210
- DI register 209
- direct memory 208
- directives *See* compiler, directives
- directories 269
  - changing 233
  - procedures 348
  - scan procedures for 122
  - searching 258, 262
- DirectVideo variable 130
- DiskFree function 124, 243
- disks
  - distribution 1

- space 243
  - status functions 124
  - DiskSize function 124, 243
  - Dispose procedure 110, 182, 183, 185, 244
  - distribution disks 1
  - div operator 55
  - DOS
    - device handling 210
    - devices 106
    - environment 179
    - error level 217
    - exit code 216
    - operating system routines 119
    - Pascal functions for 318
    - registers and 122
    - verify flag 287
      - setting 376
  - Dos unit 115, 119
    - constants 120
    - date and time procedures 124
    - disk status functions 124
    - DiskFree function 243
    - DiskSize function 243
    - DosError in 123
    - DosExitCode function 245
    - DosVersion function 245
    - EnvCount function 248
    - environment-handling functions 125
    - EnvStr function 248
    - Exec procedure 251
    - FExpand function 254
    - file-handling procedures and functions 124
    - FindFirst procedure 258
    - FindNext procedure 259
    - FSearch function 262
    - FSplit procedure 263
    - GetCBreak procedure 267
    - GetDate procedure 268
    - GetEnv function 270
    - GetFAttr procedure 271
    - GetFTime procedure 274
    - GetIntVec procedure 277
    - GetTime procedure 287
    - GetVerify procedure 287
    - interrupt support procedures 123
    - Intr procedure 305
    - Keep procedure 307
    - miscellaneous procedures and functions 125
    - MsDos procedure 318
    - PackTime procedure 328
    - process-handling procedures and functions 125
    - SetCBreak procedure 357
    - SetFTime procedure 362
    - SetIntVec procedure 365
    - SetTime procedure 374
    - SetVerify 376
    - SwapVectors procedure 384
    - types 120
    - UnpackTime procedure 391
  - DosError variable 123, 251, 258, 259, 271, 274, 359, 362
  - DosExitCode function 125, 245
  - DosVersion function 126, 245
  - double floating-point type 172, 190
  - Draw procedure 156
  - DrawPoly procedure 133, 148, 246
  - drivers
    - active, returning
      - maximum mode number 279
      - name 270
    - graphics 133
  - DS register 199, 206, 209, 247
  - DSEG 199, 200
  - DSeg function 112, 199, 200, 247
  - DX register 196, 209
  - dynamic
    - memory allocation 116
      - functions 109
    - variables 32, 38, 42, 181
- ## E
- \$E compiler directive 172, 410
  - East constant 155
  - EGA, CheckSnow and 130
  - ellipse, drawing 256
  - Ellipse procedure 147, 148, 247
  - elliptical sector, drawing and filling 350
  - \$ELSE compiler directive 420
  - empty set 31
  - EMS memory, overlay files and 159, 165

- emulating numeric coprocessor (8087) 27
  - compiler switch 410
- Emulation command 410
- end of file
  - error messages 429
  - status 249
- \$ENDIF compiler directive 420
- entry code, procedures and functions 198
- enumerated type 24, 189
- EnvCount function 125, 248
- EnvStr function 125, 248
- Eof function 103, 249
- Eoln function 104, 250
- Erase procedure 102, 250
- ErrorAddr variable 118, 217
- errors
  - ANSI Pascal 406
  - codes for graphics operations 291, 292
  - critical 446
  - fatal, in OvrInit 167
  - handling 137
  - messages 291, 427
    - critical 446
    - fatal 447
  - range 413
  - reporting 216
  - run-time *See* run-time, errors
- ES register 209
- .EXE files 159
  - building 220
- Exec procedure 125, 251
- exit
  - codes 245
  - functions 198
  - procedures 198, 216, 253
    - implementing 118
- Exit procedure 109
- ExitCode variable 118, 217
- exiting a program 216
- ExitProc variable 118, 216
- Exp function 111, 253
- Expanded Memory Specification *See* EMS memory
- exponents 189
- expressions 51
  - constant 15

- examples 54
- extended
  - floating-point type 173
  - key codes 126, 424
  - memory support *See* EMS
  - memory
    - range arithmetic 173
- extended floating-point type 191
- extensions, ANSI Pascal 403
- external
  - declarations 79, 199, 415
  - procedure errors 432
- ExternProc 169
- EXTRN definition errors 199, 200, 433

## F

- \$F compiler directive 86, 165, 197, 411
- factor (syntax) 52
- FAR calls 197
  - model 164
    - forcing use of 216, 411
    - requirement 160
- fatal run-time errors 447
- FExpand function 125, 254
- Fibonacci numbers 175
- field
  - designators 41
  - list (of records) 29
- file-handling procedures 124, 405
  - Rename 345
  - Reset 345
  - Rewrite 347
  - routines 119
  - Seek 351
  - SetFAttr 359
  - Truncate 391
- FileMode variable 105, 118
- FilePos function 105, 254
- FileRec 120, 193
- files
  - access, read-only 105
  - access-denied error 444
  - .ASM 178
  - Assign procedure 227
  - attributes 271
    - constants 121
  - .BGI 133
  - buffer 194

- .CHR 133
  - closing 236
  - erasing 250
  - .EXE 159
    - building 220
  - handles 193, 194
  - I/O 116, 126
  - modes 193, 194
    - constants 120
  - .OBJ 199
    - linking with 415
  - .OVR 159
  - record types 120
  - text 103
  - typed 118, 193
  - types 31, 193
  - untyped 105, 118, 193
    - variable 230, 232
  - FileSize function 105, 255
  - fill patterns 272
  - FillChar procedure 112, 255
  - FillEllipse procedure 148, 256
  - filling areas 259
  - FillPattern procedure 156
  - FillPoly procedure 137, 148, 257
  - FillScreen procedure 156
  - FillShape procedure 156
  - FindFirst procedure 121, 124, 258
    - SearchRec and 122
  - FindNext procedure 121, 124, 259
    - SearchRec and 122
  - fixed part (of records) 29
  - flags constants 120
  - floating-point
    - calculations, type real and 173
    - code generation, switching 171
    - errors 447
    - numbers 171
    - numeric coprocessor (8087) 27
    - parameters 196
    - routines 116
    - software 26
    - types *See* types, floating-point
  - FloodFill procedure 134, 137, 149, 259
  - Flush function 212
  - Flush procedure 104, 261
  - Font8x8 variable 128, 387, 388
  - fonts
  - files 141
    - installing 304
    - stroked 375
  - for statements, syntax 72
  - Force Far Calls command 86, 165, 411
  - force FAR calls compiler switch 411
  - formal parameters 66, 82
  - forward declarations 78
  - Forwd procedure 156
  - Frac function 111, 261
  - fractions, returning 261
  - free list 185
    - overflow 187
  - FreeMem procedure 110, 182, 183, 185, 187, 261
  - FreeMin variable 118, 186
  - FreePtr variable 118, 185
  - FSearch function 125, 262
  - FSplit procedure 124, 254, 263
  - functions 77
    - address 112
    - arithmetic 110
    - body 80
    - calls 62, 195
    - Crt unit 132
    - declarations 80
    - disk status 124
    - dynamic allocation 109
    - file-handling 124
    - Graph unit 151
    - headings 80
    - nested 86
    - non-ANSI 405
    - ordinal 111
    - pointer 112
    - results 196
    - standard 109
    - string 112
    - transfer 110
    - Turbo3 unit 154
- ## G
- GetArcCoords procedure 147, 149, 264
  - GetAspectRatio procedure 149, 265
  - GetBkColor function 151, 266
  - GetCBreak procedure 125, 267
  - GetColor function 151, 267
  - GetDate procedure 124, 268

- GetDefaultPalette function 146, 151, 268
- GetDir procedure 102, 269
- GetDotColor procedure 156
- GetDriverName function 151, 270
- GetEnv function 125, 270
- GetFAttr procedure 121, 125, 271
- GetFillPattern procedure 147, 149, 272
- GetFillSettings procedure 145, 147, 149, 273
- GetFTime procedure 124, 274
- GetGraphMode function 151, 274
- GetImage procedure 133, 149, 276
- GetIntVec procedure 123, 277
- GetLineSettings procedure 145, 146, 149, 277
- GetMaxColor function 151, 278
- GetMaxMode function 151, 279
- GetMaxX function 151, 280
- GetMaxY function 151, 281
- GetMem procedure 110, 186, 187, 188, 281
- GetModeName function 151, 282
- GetModeRange procedure 143, 149, 283
- GetPalette procedure 146, 149, 283
  - IBM 8514 and 284
- GetPaletteSize function 151, 284
- GetPic procedure 156
- GetPixel function 137, 151, 285
- GetTextSettings procedure 136, 145, 147, 149, 285
- GetTime procedure 124, 287
- GetVerify procedure 126, 287
- GetViewSettings procedure 147, 149, 287
- GetX function 151, 288
- GetY function 151, 289
- goto statements 67
- GotoXY procedure 132, 290
- GRAPH3.TPU 3
- Graph3 unit 115, 116, 155
  - constants 155
  - procedures 155
- GRAPH.BIN 155
- GRAPH.P 155
- GRAPH.TPU 2, 134
- Graph unit 115, 133, 166

- Arc procedure 226
- Bar3D procedure 229
- Bar procedure 229
- bit images in 137
- Circle procedure 234
- ClearDevice procedure 234
- ClearViewPort procedure 235
- CloseGraph procedure 236
- colors 137
- constants 142
- DetectGraph procedure 242
- DrawPoly procedure 246
- Ellipse procedure 247
- error-handling 137
- figures and styles in 136
- FillEllipse procedure 256
- FillPoly procedure 257
- FloodFill procedure 259
- functions 151
- GetArcCoords procedure 264
- GetAspectRatio procedure 265
- GetBkColor function 266
- GetColor function 267
- GetDefaultPalette function 268
- GetDriverName function 270
- GetFillPattern procedure 272
- GetFillSettings procedure 273
- GetGraphMode function 274
- GetImage procedure 276
- GetLineSettings procedure 277
- GetMaxColor function 278
- GetMaxMode function 279
- GetMaxX function 280
- GetMaxY function 281
- GetModeName function 282
- GetModeRange procedure 283
- GetPalette procedure 283
- GetPaletteSize function 284
- GetPixel function 285
- GetTextSettings procedure 285
- GetViewSettings procedure 287
- GetX function 288
- GetY function 289
- GraphDefaults procedure 291
- GraphErrorMsg function 291
- GraphResult function 292
- heap management routines 140
- ImageSize function 296
- InitGraph procedure 297

- InstallUserDriver function 301
- InstallUserFont function 304
- Line procedure 308
- LineRel procedure 309
- LineTo procedure 310
- MoveRel procedure 316
- MoveTo procedure 317
- OutText procedure 320
- OutTextXY procedure 322
- paging 137
- PieSlice procedure 329
- procedures 148
- PutImage procedure 331
- PutPixel procedure 334
- Rectangle procedure 339
- RegisterBGIDriver function 340
- RegisterBGIFont function 342
- RestoreCrtMode procedure 346
- sample program 138, 139
- Sector procedure 350
- SetActivePage procedure 353
- SetAllPalette procedure 354
- SetAspectRatio procedure 355
- SetBkColor procedure 356
- SetColor procedure 358
- SetFillPattern procedure 359
- SetFillStyle procedure 361
- SetGraphBufSize procedure 362
- SetGraphMode procedure 363
- SetLineStyle procedure 366
- SetPalette procedure 367
- SetRGBPalette procedure 369
- SetTextJustify procedure 372
- SetTextStyle procedure 373
- SetUserCharSize procedure 375
- SetViewPort procedure 376
- SetVisualPage procedure 378
- SetWriteMode 379
- text in 136
- TextHeight function 386
- TextWidth function 389
- types 146
- variables 148
- viewports in 137
- GraphBackground procedure 156
- GraphColorMode procedure 156
- GraphDefaults procedure 149, 291
- GraphDriver variable
  - IBM 8514 and 134, 299
- GraphErrorMsg function 151, 291
- GraphFreeMem procedure 140
- GraphFreeMemPtr variable 148
- GraphGetMem procedure 140
- GraphGetMemPtr variable 148
- graphics
  - bit-image operations 331
  - cards 242, 298
  - CloseGraph 133
  - current pointer in 135
  - drawing operations 308, 309, 310, 329, 339, 366
  - drivers 133, 297
  - figures and styles 136
  - fill operations 359, 361
  - InitGraph in 133
  - mode 274, 297, 309, 310, 311
  - page operations 353, 378
  - palette operations 354, 356, 358, 367
  - plotting operations 334
  - pointer operations 317
  - polygons, drawing 246
  - resolution 265
  - sample program 138, 139
  - system operations 363
  - text operations 320, 322, 372, 386
  - turtlegraphics 155
  - video mode operations 346
  - viewport operations 376
- GraphMode procedure 156, 297
- GraphResult function 137, 138, 142, 151, 292
  - error codes 292
- GraphWindow procedure 156
- GREP.COM 3
- grError 293
- grInvalidFont 293
- grInvalidFontNum 293
- grIOerror 293
- GROUP directives 199

## H

- Halt procedure 109, 216, 294
- handles
  - DOS 227
  - file 193, 194
- hardware, interrupts 209



- Heading procedure 156
- heap management 179, 181
  - allocating 181, 182, 185, 187
  - deallocating 182
  - dynamic memory allocation 118
  - fragmenting 181
  - free list 185
  - granularity 186
  - map 179
  - pointers 180
  - procedures 344
  - routines 140
  - sizes 416
- HeapError variable 118, 187
- HeapOrg variable 118, 181, 183
- HeapPtr variable 118, 181, 186
- HELPME!.DOC 1
- hexadecimal constants 13
- Hi function 113, 218, 295
- HideTurtle procedure 156
- high
  - intensity characters 295
  - order bytes 295
  - resolution graphics 134
- HighVideo procedure 132, 154, 295
- HiRes procedure 156
- HiResColor procedure 156
- Home procedure 156
- host type 25

**I**

- \$I compiler directive 102, 119, 306, 411, 415
- I/O 101
  - checking 306
  - devices 211
  - DOS standard 227
  - error-checking 102, 411
  - errors 445
  - files 116, 126
    - standard 118
  - redirection 126
  - variables 101
- I/O-Checking command 411
- IBM 8514 133
  - driver support 134-134
  - GetPalette procedure and 284
  - GraphDriver variable and 134, 299

- InitGraph procedure and 134, 299
  - palette entries, modifying 369
  - SetAllPalette procedure and 355
  - SetPalette procedure and 368
  - SetRGBPalette and 134
- IBM8514.BGI 134
- IBM8514HI mode 134
- IBM8514LO mode 134
- identifiers 11
- if statements 68
- \$IFDEF compiler directive 419
- \$IFNDEF compiler directive 419
- \$IFOPT compiler directive 420
- ImageSize function 151, 296
- implementation
  - dependent features, Pascal 405
    - part (program) 95, 197
    - sections 99
- in operator 58, 60
- Inc procedure 111, 297
- Include Directories command 415
- include directories command-line
  - option 415
- Include files 415
  - nesting 415
- index expressions 41
- indirect unit references 96
- InitGraph procedure 133, 143, 149, 297
  - SetGraphMode and 363
- initialization part (program) 96
- initialized variables 45
- inline
  - declarations 80
  - directives 207
  - machine code 205
  - statements 205
- InOut function 212
- InOutRes variable 118
- input
  - DOS standard 227
  - files 101, 118
- Input standard file 118
- Insert procedure 112, 300
- inserting
  - lines 300
  - strings 300
- InsLine procedure 132, 300
- INSTALL.EXE 2, 4

- INSTALL utility 2
- installation, Turbo Pascal 2, 4
- InstallUserDriver function 152, 301
- InstallUserFont function 152, 304
- INT 24 handler 118
- Int function 111, 305
- integer data type 23, 188
- integrated environment, using 1
- interface section (program) 95, 100, 152, 197, 199
- interfacing Turbo Pascal with Turbo Assembler 200
- internal data formats 179, 188
- interrupt
  - directives 78
  - handlers 209
    - units and 169
  - handling routines 118, 209
  - procedures 365
  - service routines (ISRs) 209
  - support procedures 123
  - vectors 118, 119, 277
    - swapping 384
- Intr procedure 123, 305
  - registers and 122
- invalid typecasting errors 434
- IOResult function 103, 118, 154, 306
- IP flag 209
- ISRs (interrupt service routines) 209

## J

- justification, font 285

## K

- Kbd 153
- Keep procedure 125, 307
- key codes 424
- keyboard
  - operations 307, 337
  - scan codes 425
  - status 128
- KeyPressed function 128, 132, 307

## L

- \$L compiler directive 199, 412, 415
- labels 12
  - declaration part 17

- LastMode variable 131
- Length function 112, 218, 308
- line
  - drawing, setting writing mode for 379
  - input, Crt 127
  - settings 277
- Line procedure 149, 308
- LineRel procedure 149, 309
- LineTo procedure 149, 310
- linking
  - assembly language 199
  - object files 415
  - smart 220
- Ln function 111, 311
- Lo function 113, 218, 312
- local symbol information switch 412
- Local Symbols command 412
- logical operators 56
- LongFilePos function 154
- LongFileSize function 154
- longint data type 23
- LongSeek procedure 154
- LowVideo procedure 132, 154, 312
- LPT devices 107, 119
- Lst variable 119

## M

- \$M compiler directive 38, 181, 307, 313, 314, 327, 416
- machine code 205
- macros, inline 207
- MAKE utility 3
- Mark procedure 110, 182, 313
- math coprocessor *See* numeric coprocessor
- MaxAvail function 110, 155, 186, 313
- Mem array 208
- MemAvail function 110, 152, 155, 186, 314
- MemL array 208
- memory 261, 281
  - allocation 166
    - compiler directive 416
  - DirectVideo and 130
  - error messages 427
  - map 179
  - size 416

- Memory Sizes command 416
- MemW array 208
- MicroCalc 2
- MkDir procedure 102, 314
- mod operator 55
- .MODEL directive
  - setting up calling conventions with 200
- modular programming 94
- monochrome adapters, CheckSnow and 130
- Move procedure 113, 315
- MoveRel procedure 149, 316
- MoveTo procedure 149, 317
- MSdos procedure 124, 318
- MSDOS symbol 418

## N

- \$N compiler directive 26, 171, 223, 412
- NEAR calls 197
- nested scopes 443
- nesting
  - files 415
  - procedures and functions 197
- network file access, read-only 105
- New procedure 32, 110, 181, 186, 188, 318
- nil 32, 42
- NormalPut constant 332
- NormVideo procedure 132, 154, 319
- North constant 155
- NoSound procedure 132, 319
- not operator 56, 137
- NotPut constant 332
- NoWrap procedure 156
- NUL device 107
- null strings 14, 27
- numbers, counting 13, 188
- numeric coprocessor
  - compiler switch 412
  - detecting 176
  - emulating 27, 116, 172
    - assembly language and 178
  - evaluation stack 175
  - floating-point 27
  - mode 440
  - numeric processing option 27

- using 171-178
- Numeric Processing command 172, 413

## O

- \$O compiler directive 164, 413, 416
  - non-overlay units and 168
- .OBJ files 199
  - linking with 415
- object
  - directories, compiler directive 415
  - files 199
    - linking with 415
- Object Directories command 415
- Odd function 111, 218, 319
- Ofs function 112, 320
- op code 205
- Open function 211
- operands 51
- operators 10, 51, 54
  - @ (address-of) 32, 42
    - versus ^ (pointer) symbol 401
  - address-of (@) 90
  - and 56, 137
  - arithmetic 54
  - BitBlt 146
  - bitwise 56
  - Boolean 56
  - div 55
  - logical 56
  - mod 55
  - not 56, 137
  - or 56, 137
  - precedence of 51, 55
  - relational 58
  - set 58
  - shl 56
  - shr 56
  - string 57
  - xor 56, 137
- optimization of code 217
- or operator 56, 137
- Ord function 22, 25, 110, 218, 320
- order of evaluation 219
- ordinal
  - functions 111
  - procedures 111
  - types 22

- OrPut constant 332
- out-of-memory errors 427
- output
  - DOS standard 227
  - files 101, 118
- Output standard file 118
- OutText procedure 136, 149, 320
- OutTextXY procedure 136, 150, 322
- overlaid
  - code, storing 181
  - initialization code 167
  - programs
    - designing 164
    - writing 160
  - routines, calling via procedure pointers 169
- Overlay unit 115, 117, 160
  - name option 416
  - OvrClearBuf procedure 163, 323
  - OvrGetBuf function 163, 324
  - OvrInit procedure 162, 325
  - OvrInitEMS procedure 162, 325
  - OvrResult variable 161
  - OvrSetBuf procedure 163, 327
- overlays 159, 159-170
  - assembly language routines and 169
  - BP register and 169
  - buffers
    - clearing 163, 323
    - size
      - default 181
      - increasing 118
      - with OvrSetBuf 181
    - returning 163, 324
    - setting 163, 327
  - cautions 168
  - code generation, compiler switch 413
  - debugging 169
  - files
    - loading into EMS 165, 325
    - opening 325
  - loading
    - into EMS 162
    - into memory 159
  - manager 116
    - implementing 117
    - initializing 162, 165, 167, 325

- Overlays Allowed command 413
- .OVR files 159
- OvrClearBuf procedure 163, 323
- OvrCodeList variable 117
- OvrDebugPtr variable 117
- OvrDosHandle variable 117
- OvrEmsHandle variable 117
- OvrGetBuf function 163, 324
- OvrHeapEnd variable 117
- OvrHeapOrg variable 117
- OvrHeapPtr variable 117
- OvrHeapSize variable 117
- OvrInit procedure 162, 325
- OvrInitEMS procedure 162, 166, 325
- OvrLoadList variable 117
- OvrResult variable 161
- OvrSetBuf procedure 118, 163, 166, 327
- OvrSetBuf routine, increasing size of overlay buffer with 181

## P

- Pack procedure 110
- packed (reserved word) 28
- PackTime procedure 124, 328
  - DateTime and 122
- palette
  - color lookup table, returning size 284
  - definition record 268
  - manipulation routines 134
- Palette procedure 156
- ParamCount function 113, 328
- parameter directives *See* compiler, directives, parameter
- parameters
  - actual 66
  - command-line 113, 328
  - floating-point 196
  - formal 66, 82
  - passing 66, 195
  - procedural type 87
  - value 82, 195
  - variable 83
    - untyped 83
- ParamStr function 113, 328
- .PAS files 2
- Pattern procedure 156

- PenDown procedure 156
- PenUp procedure 157
- Pi function 111, 329
- PieSlice procedure 150, 329
- pixel values 285
- Plot procedure 157
- pointer (^) symbol 32, 42
- pointer and address functions 112
- pointer-type constants 49
- pointers
  - comparing 60
  - types 32, 192
  - values 42
  - variables 42, 61
- polygons, drawing 246
- port access 208
- Port array 208
- PortW array 208
- Pos function 112, 330
- pound (#) character 14
- precedence of operators 51, 55
- Pred function 22, 111, 218, 331
- PreFixSeg variable 179
- PrefixSeg variable 118
- printer devices 107
- Printer unit 115, 119
- PRN 107
- PROC directive, defining parameters with 200
- procedural
  - types 33, 84, 84-91
    - declarations 84
    - in expressions 89
    - in statements 89
    - variable declaration 85
    - variable typecasts and 90
  - values, assigning 85
  - variables 85
    - restrictions 86
    - using standard procedures and functions with 86
- procedural type parameters 87
- procedure and function declaration
  - part (program) 18
- procedures 77
  - body 77
  - declarations 77
  - dynamic allocation 109
  - Exit 109
  - file-handling 124
  - Graph3 unit 155
  - Graph unit 148
  - Halt 109
  - headings 78
  - nesting 86, 197
  - non-ANSI 405
  - ordinal 111
  - pointers, calling overlaid routines 169
  - standard 109
  - statements 66
  - string 112
  - Turbo3 unit 154
- process-handling routines 125, 307
- Program Segment Prefix (PSP) 118, 179
- programs
  - execution, stopping 349
  - halting 294
  - headings 93
  - lines 16
  - parameters 93
  - syntax 93
  - termination 216
- Ptr function 32, 112, 218, 331
- PUBLIC 199
  - definition errors 433
- PutImage procedure 133, 137, 146, 150, 331
- PutPic procedure 157
- PutPixel procedure 137, 150, 334

## Q

- qualified identifiers 11, 19

## R

- \$R compiler directive 413
- Random function 113, 118, 334
- random number generator 118
- Randomize procedure 113, 335
- RandSeed function 118
- range-checking
  - compile time 219
  - compiler switch 413
  - Val and 392
- Range-Checking command 413
- read-only file access 105

- Read procedure
  - text files 102, 104, 335
  - typed files 337
- reading records 230
- ReadKey function 128, 132, 153, 337
- Readln procedure 104, 338
- README 1
- README.COM 3
- real
  - numbers 26, 171, 189
  - types 26
- record-type constants 48
- records 29, 41, 48, 193
- Rectangle procedure 150, 339
- redeclaration 19, 37
- redirection 126
- reentrant code 209, 210
- referencing errors 440
- register-saving conventions 199
- RegisterBGIDriver function 133, 141, 152, 169, 340
- RegisterBGIfont function 141, 152, 169, 342
- registers
  - AX 196, 207
  - BP 199, 206, 209
    - overlays and 169
  - BX 196, 209
  - CS 209, 240
  - CX 209
  - DI 209
  - DS 199, 206, 209
  - DX 196, 209
  - ES 209
  - SI 209
  - SP 118, 199
  - SS 199
    - using 196, 199, 206, 209
- Registers type 122
- relational operators 58
- relaxed string parameter-checking 414
- Release procedure 110, 182, 344
- relocatable reference errors 434
- Rename procedure 102, 345
- repeat statements 70
- repetitive statements 70
- reserved words 10, 403
- Reset procedure 101, 103, 118, 345

- resolution, graphics 265
- RestoreCrtMode procedure 133, 150, 346
- result codes 161
- Rewrite procedure 101, 103, 347
- Rmdir procedure 103, 348
- Round function 110, 218, 349
- round-off errors, minimizing 174
- routines, operating system 125
- rules, scope 19
- run-time
  - errors 216, 443
    - fatal 447
    - generating 349
    - support routines 116
- RunError procedure 349

## S

- \$\$ compiler directive 38, 414
- SaveInitXX variables 118
- SaveInt24 119
- scale factor 13
- scan codes, keyboard 425
- scope (of declaration) 19
- scopes, nested 443
- screen
  - mode control 126
  - output operations 126
- search utility 3
- searching directories 258
- SearchRec type 122
- Sector procedure 150, 350
- Seek procedure 102, 105, 351
- SeekEof function 104, 351
- SeekEoln function 104, 352
- Seg function 352
- Seq function 112
- serial communications port 212
- set-type constants 48
- set types 31, 192
- SetActivePage procedure 150, 353
- SetAllPalette procedure 144, 146, 150, 354
  - IBM 8514 and 355
- SetAspectRatio procedure 150, 355
- SetBkColor procedure 150, 356
- SetCBreak procedure 126, 357
- SetColor procedure 150, 358

- SetDate procedure 124, 358
- SetFAttr procedure 121, 125, 359
- SetFillPattern procedure 137, 145, 147, 150, 359
- SetFillStyle procedure 137, 145, 150, 361
- SetFTime procedure 124, 362
- SetGraphBufSize procedure 141, 150, 362
- SetGraphMode procedure 133, 150, 363
- SetHeading procedure 157
- SetIntVec procedure 124, 365
- SetLineStyle procedure 137, 145, 150, 366
- SetPalette procedure 144, 150, 367
  - IBM 8514 and 368
- SetPenColor procedure 157
- SetPosition procedure 157
- SetRGBPalette procedure 144, 150, 369
  - IBM 8514 and 134
- SetRGBPalette routine 134
- sets
  - comparing 60
  - constructors 52, 63
  - membership 60
  - operators 58
- SetTextBuf procedure 104, 370
- SetTextJustify procedure 136, 145, 150, 372
- SetTextStyle procedure 136, 145, 150, 373
  - OutText and 320
  - OutTextXY and 323
- SetTime procedure 124, 374
- SetUserCharSize procedure 136, 150, 375
- SetVerify procedure 126, 376
- SetViewPort procedure 133, 145, 150, 376
- SetVisualPage procedure 151, 378
- SetWriteMode procedure 146, 151, 379
- shl operator 56
- short-circuit Boolean evaluation 218, 409
- shortint data type 23
- ShowTurtle procedure 157
- shr operator 56
- SI register 209
- signed number (syntax) 14
- significand 189
- simple
  - statements 65
  - types 22
- simple-type constants 46
- Sin function 111, 380
- single floating-point type 172, 190
- SizeOf function 113, 256, 381
- smart linking 220
- snow-checking 130
- software
  - floating-point 26
  - interrupts 209, 305
  - numeric processing *See* numeric coprocessor, emulating
- sound operations
  - NoSound 132, 319
  - Sound 132, 381
- Sound procedure 132, 381
- source debugging compiler switch 410
- South constant 155
- SP register 118, 199, 206
- space characters 9
- SPtr function 112, 382
- Sqr function 111, 382
- Sqrt function 111, 382
- SS register 199, 206
- SSeg function 112, 382
- stack
  - 8087 175
  - checking switch directive 414
  - overflow 38
    - switch directive 414
  - segment 38
  - size 416
- Stack-Checking command 414
- StackLimit variable 118
- standard
  - functions, constant expressions and 16
  - Pascal 401
  - units *See* units, standard
- statement part (program) 18
- statements 65
  - assignment 66

- case 69
- compound 67
- conditional 68
  - for 72
  - goto 67
  - if 68
- procedure 66
- repeat 70
- repetitive 70
- simple 65
- structured 67
- uses 93
- while 71
- with 74
- storing overlaid code 181
- Str procedure 112, 383
- string-type constants 46
- strings 46
  - character 14
  - comparing 59, 60
  - concatenation 58, 238
  - construction 238
  - deletion 241
  - functions 112
  - handling 116
  - initializing 255
  - length byte 192, 255
  - maximum length 192
  - null 27
  - operators 57
  - procedures 112, 300, 383, 392
  - relaxed parameter-checking 414
  - types 27, 192
  - variables 41
- stroked fonts 133, 136, 375
- structured
  - statements 67
  - types 28
    - declaring 87
- structured-type constants 46
- subrange type 25
- substrings
  - copying 239
  - deleting 241
  - inserting 300
  - position 330
- Succ function 22, 111, 218, 383
- Swap function 113, 218, 384
- SwapVectors procedure 119, 125, 384

- switch compiler directives 407, 408-414
- symbols 9
  - conditional 417
  - CPU 418
  - local information 412
- syntax diagrams, reading 9
- System unit 94, 115, 116, 223
  - floating-point routines 172
  - interrupt vectors and 118
  - trapping critical errors 118
  - variables in 116-119

## T

- tag field (of records) 30
- technical support 5
- terminating a program 216, 253
- terms (syntax) 53
- Test8087 variable 118
- text 136
  - attributes 285
  - color constants 128
  - files 103, 249
    - devices 108
    - drivers 210
  - records 194
- TextAttr variable 131
  - ClrEol and 237
  - ClrScr and 237
  - HighVideo and 295
  - LowVideo and 312
  - NormVideo and 319
  - TextBackground and 385
  - TextColor and 386
- TextBackground procedure 128, 132, 385
- TextColor procedure 128, 132, 385
- TextHeight function 152, 386
- TextMode procedure 128, 132, 387
- TextRec records 120, 193, 210
- TextWidth function 152, 389
- THELP.COM 2
- THELP utility 2
- time procedures
  - GetFTime 274
  - GetTime 287
  - SetFTime 362
  - SetTime 374



- TINST 2
  - TINSTXFR.EXE 3
  - TINSTXFR utility 3
  - tokens 9
  - TOUCH 3
  - TPC.EXE 2
  - TPCONFIG.EXE 3
  - TPUMOVER.EXE 2, 116
  - transfer functions 110
  - trapping
    - critical errors 118
    - critical errors, System unit and 118
    - I/O errors 411
    - interrupts 209
  - Trunc function 110, 218, 390
  - Truncate procedure 105, 391
  - TURBO3.TPU 3
  - Turbo3 unit 115, 116, 152
    - CBreak 154
    - functions 154
    - interface section 152
    - Kbd in 153
    - procedures 154
  - Turbo Assembler 199, 200
    - 8087 emulation and 178
    - example program 204
  - TURBO.EXE 1
  - TURBO.HLP 2
  - Turbo Pascal 3.0 3
    - compatibility with 5.0 115
    - conversion
      - ANSI compatibility 401
      - chaining 392
    - versus 5.0 306, 307, 313, 314
  - Turbo Pascal, installing 2
  - Turbo Pascal Editor Toolbox 409
  - TURBO.TPL 1, 116
  - TurnLeft procedure 157
  - TurnRight procedure 157
  - TurtleDelay procedure 157
  - turtlegraphics 155
  - TurtleThere procedure 157
  - TurtleWindow procedure 157
  - type-checking, strings and 414
  - typecasting, invalid 434
  - typed
    - constants 45
    - files 118, 193
  - types 21
  - array 28, 193
  - boolean 24, 189
  - byte 23
  - char 24, 189
  - common 23
  - compatibility 34
  - declaration 21
    - part 18, 35
  - definition, constant expressions and 26
  - enumerated 24, 189
  - file 31
  - floating-point 172, 189
    - comp 26, 173, 191
    - comparing values of 174
    - double 26, 172, 190
    - extended 26, 173, 191
    - single 26, 172, 190
  - Graph unit 146
  - host 25
  - identity 33
  - integer 23, 188
  - longint 23
  - mismatches, error messages 430
  - ordinal 22
  - pointer 32, 192
  - procedural 33, 84, 89
  - real 26
  - real numbers 189
  - record 29, 193
  - set 31, 192
  - shortint 23
  - simple 22
  - string 27, 192
  - structured 28
  - subrange 25
  - word 23
- ## U
- \$UNDEF compiler directive 417, 419
  - units 1
    - 8087 coprocessor and 176
    - circular references 97
    - dependencies 116
    - heading 95
    - identifiers 11
    - indirect references 96
    - initialization code 167

- non-overlay 168
- scope of 19
- standard 115
  - Crt 103, 108, 126
  - Dos 119
  - Graph 133
  - Graph3 155
  - Overlay 160
  - overlays and 161
  - Printer 119
  - System 116
  - system 94
  - Turbo3 152
- syntax 94
- version
  - mismatch errors 435
  - number 97
- Unpack procedure 110
- UnpackTime procedure 124, 391
  - DateTime and 122
- unsigned
  - constant 52
  - integer 13
  - number 13
  - real 13
- untyped
  - files 105, 118, 193
    - variable 230, 232
  - var parameters 83
- UpCase function 113, 391
- UPGRADE.DTA 3
- UPGRADE.EXE 3
- uses statement 93, 116
- utilites
  - INSTALL 2
- utilities
  - GREP 3
  - MAKE 3
  - THELP 2
  - TINST 3
  - TINSTXFR 3
  - TOUCH 3
  - TPC 2
  - TPCONFIG 3
  - TPUMOVER 2
  - UPGRADE 3

## V

- \$V compiler directive 414
- Val procedure 112, 392
- value
  - parameters 82, 195
  - typecasts 64
- var
  - declaration section 221
  - parameters 83, 195
    - untyped 83
  - string checking, compiler switch 414
- Var-String Checking command 414
- variables 37
  - absolute 39
  - arrays 41
  - CBreak 154
  - CheckBreak 129
  - CheckEOF 130
  - CheckSnow 130
  - Crt 129
  - declaration part 18
  - declarations 37
  - defined by Overlay unit 161
  - DirectVideo 130
  - disposing of 244, 261
  - DosError 123, 251, 258, 259, 271, 274, 359, 362
  - dynamic 32, 42, 181
  - FileMode 105
  - global 38
  - Graph unit 148
  - I/O 101
  - increasing 297
  - initializing 45
  - LastMode 131
  - local 38
  - Lst 119
  - parameters 195
  - pointer 42, 61
  - procedural 85
    - restrictions 86
  - record 41
  - references 39
  - strings 41
  - TextAttr 131
  - typecasts 42, 90
  - WindMax 131

- WindMin 131
- variant part (syntax) 30
- VER50 symbol 418
- VGA
  - driver, modifying palette entries for 369
  - modes 242, 275, 364
    - emulated 134, 299
- VGAHi 275, 364
- VGA Lo 275, 364
- VGAMed 275, 364
- video
  - memory 126
  - operations
    - AssignCrt 228
    - ClrEol 237
    - ClrScr 237
    - DelLine procedure 241
    - GotoXY 290
    - HighVideo 295
    - InsLine 300
    - LowVideo 312
    - NormVideo 319
    - RestoreCrtMode 346
    - TextBackground 385
    - TextColor 385
    - WhereX 393
    - WhereY 393
    - Window 394
    - Write (text) 395
    - Write (typed) 397
    - Writeln 397
- viewports 137, 235
  - parameter 287

## W

- West constant 155
- WhereX function 132, 393
- WhereY function 132, 393

- while statements (syntax) 71
- WindMax variable 131
- WindMin variable 131
- Window procedure 126, 132, 394
  - current coordinates 131
- windows 126
- with statements 74
- word
  - alignment 200
    - automatic 219
  - data type 23
- Wrap procedure 157
- write
  - procedures 101
  - statements
    - 8087 coprocessor and 176
    - AUX devices and 212
    - BIOS 130
    - DirectVideo and 130
    - DOS 227
- Write procedure 104
  - text files 395
  - typed files 397
- Writeln procedure 104, 397
  - 8087 coprocessor and 176
  - DirectVideo and 130
- writing records 232

## X

- XCor procedure 157
- xor operator 56, 137
- XORPut constant 332

## Y

- YCor procedure 157

## Z

- Zenith Z-449, BGI and 299

# TURBO PASCAL<sup>®</sup>

REFERENCE  
GUIDE

**B O R L A N D**